

Operation Manual

 **CUBASE PRO** 9.5

 **CUBASE ARTIST** 9.5

Cristina Bachmann, Heiko Bischoff, Lillie Harris, Christina Kaboth, Insa Mingers, Matthias Obrecht, Sabine Pfeifer, Benjamin Schütte, Marita Sladek

This PDF provides improved access for vision-impaired users. Please note that due to the complexity and number of images in this document, it is not possible to include text descriptions of images.

The information in this document is subject to change without notice and does not represent a commitment on the part of Steinberg Media Technologies GmbH. The software described by this document is subject to a License Agreement and may not be copied to other media except as specifically allowed in the License Agreement. No part of this publication may be copied, reproduced, or otherwise transmitted or recorded, for any purpose, without prior written permission by Steinberg Media Technologies GmbH. Registered licensees of the product described herein may print one copy of this document for their personal use.

All product and company names are ™ or ® trademarks of their respective owners. For more information, please visit www.steinberg.net/trademarks.

© Steinberg Media Technologies GmbH, 2018.

All rights reserved.

Cubase_9.5.40_en-US_2018-10-16

Table of Contents

8	Introduction	105	Instrument Tracks
8	Platform-Independent Documentation	112	MIDI Tracks
8	About the Documentation	118	Sampler Tracks
9	Conventions	124	Arranger Track
10	Key Commands	126	Chord Track
11	Setting Up Your System	128	FX Channel Tracks
11	Setting Up Audio	134	Folder Tracks
18	Setting Up MIDI	135	Group Channel Tracks
20	Connecting a Synchronizer	140	Marker Track
21	Audio Connections	142	Ruler Track
21	Audio Connections Window	143	Signature Track
27	Renaming the Hardware Inputs and Outputs	144	Tempo Track
28	Adding Input and Output Busses	145	Transpose Track
28	Adding Child Busses (Cubase Pro only)	146	VCA Fader Track (Cubase Pro only)
29	Presets for Input and Output Busses	148	Video Track
30	Adding Group and FX Channels (Cubase Pro only)	151	Track Handling
30	About Monitoring	151	Adding Tracks
30	External Instruments and Effects (Cubase Pro only)	153	Importing Tracks (Cubase Pro only)
36	Editing the Bus Configurations	156	Exporting Tracks as Track Archive (Cubase Pro only)
38	Project Window	157	Exporting MIDI Tracks as Standard MIDI File
39	Showing/Hiding Zones	159	Removing Tracks
39	Project Zone	159	Moving Tracks in the Track List
51	Left Zone	160	Renaming Tracks
61	Lower Zone	160	Coloring Tracks
67	Right Zone	161	Showing Track Pictures
73	Keyboard Focus in the Project Window	162	Setting the Track Height
74	Zooming in the Project Window	163	Selecting Tracks
78	Snap Function	164	Duplicating Tracks
81	Cross-Hair Cursor	164	Disabling Tracks
82	Edit History Dialog	164	Organizing Tracks in Folder Tracks
83	Project Handling	165	Handling Overlapping Audio
83	Creating New Projects	166	Track Folding
84	Hub	167	How Events are Displayed on Folder Tracks
85	Project Assistant	167	Modifying Event Display on Folder Tracks
85	About Project Files	167	Working with Lanes
86	About Template Files	170	Defining the Track Time Base
87	Project Setup Dialog	171	TrackVersions
90	Opening Project Files	179	Track Presets
91	Saving Project Files	185	Parts and Events
92	Reverting to the Last Saved Version	185	Events
92	Choosing a Project Location	188	Parts
93	Creating Self-Contained Projects	190	Editing Techniques for Parts and Events
95	Tracks	204	Range Editing
95	Track Inspector Settings	204	Creating a Selection Range
96	Track Control Settings	205	Editing Selection Ranges
98	Audio Tracks	208	Playback and Transport
		208	Transport Panel
		210	Transport Menu

215	Transport	315	Importing and Exporting Markers
217	Transport Pop-Up Window	317	MixConsole
218	Time Display Window	317	MixConsole in Lower Zone
219	Left and Right Locators	320	MixConsole Window
220	Setting the Project Cursor Position	365	VCA Faders (Cubase Pro only)
221	Auto-Scroll	365	VCA Fader Settings
221	Time Formats	367	Creating VCA Faders
222	Pre-Roll and Post-Roll	368	Assigning VCA Faders to Link Groups
223	Punch In and Punch Out	368	Removing VCA Faders from Link Groups
224	Metronome Click	369	Nested VCA Faders
232	Chase	369	VCA Fader Automation
234	On-Screen Keyboard	372	Control Room (Cubase Pro only)
234	Recording MIDI With the On-Screen Keyboard	372	Adding Channels to the Control Room
235	On-Screen Keyboard Options	373	Output Routing
236	Recording	373	Exclusive Assignment of Monitor Channels
236	Basic Recording Methods	373	Control Room Channels
239	Monitoring	374	Control Room - Main Tab
242	Audio Recording Specifics	380	Control Room - Inserts Tab
246	MIDI Recording Specifics	382	Setting Up a Cue Mix
252	Remaining Record Time	383	Adjusting the Overall Cue Send Level
252	Lock Record	385	Metering and Loudness (Cubase Pro only)
254	Importing Audio and MIDI Files	385	Metering
254	Importing Audio Files	386	Loudness Measurement
261	Importing MIDI Files	391	Audio Effects
264	Quantizing MIDI and Audio	391	Insert Effects and Send Effects
264	Quantize Functions	393	Insert Effects
265	Quantizing MIDI Event Starts	400	Send Effects
266	Quantizing MIDI Event Lengths	405	Side-Chain Input
266	Quantizing MIDI Event Ends	407	Dither Effects
266	Quantizing Audio Event Starts	408	External Effects (Cubase Pro only)
267	Quantizing Audio Event Lengths (AudioWarp Quantizing) (Cubase Pro only)	408	Effect Control Panel
267	Quantizing Multiple Audio Tracks (Cubase Pro only)	409	Effect Presets
269	Quantize Panel	414	System Component Information Window
278	Fades, Crossfades, and Envelopes	416	Direct Offline Processing
278	Event-Based Fades	417	Direct Offline Processing Workflow
282	Creating Clip-Based Fades	417	Direct Offline Processing Window
283	Crossfades	425	Built-In Audio Processes
285	Auto Fades and Crossfades	433	Applying Direct Offline Processing Using Key Commands
288	Event Envelopes	435	Time Stretch and Pitch Shift Algorithms
290	Arranger Track	435	élastique
290	Adding Arranger Events on the Arranger Track	436	MPEX
291	Arranger Editor	436	Standard
294	Setting up an Arranger Chain and Adding Events	437	Limitations
296	Jump Mode	438	Audio Functions
298	Arranging Music to Video	438	Detect Silence
299	Transpose Functions	440	Spectrum Analyzer
299	Project Root Key	443	Statistics
302	Transpose Track	445	Sample Editor
304	Keep Transpose in Octave Range	447	Toolbar
305	Transpose on the Info Line	451	Info Line
306	Excluding Individual Parts or Events from Global Transpose	451	Overview Line
307	Markers	452	Sample Editor Inspector
307	Position Markers	455	Ruler
307	Cycle Markers	455	Waveform Display
308	Markers Window	457	Range Editing
312	Marker Track	461	Regions List
		463	Snap Point

465	Hitpoints	601	MixConvert V6
465	Calculating Hitpoints	605	Surround Mix Export
468	Locating to Hitpoints in the Project Window	606	Automation
468	Slices	606	Automation Curves
470	Creating a Groove Quantize Map	606	Static Value Line
470	Creating Markers	606	Write/Read Automation
471	Creating Regions	607	Writing Automation Data
471	Creating Events	609	Editing Automation Events
471	Creating Warp Markers	614	Automation Tracks
472	Creating MIDI Notes	615	Virgin Territory vs. Initial Value (Cubase Pro only)
474	Tempo Matching Audio	616	Automation Panel (Cubase Pro only)
474	Algorithm Presets	625	MIDI Controller Automation
475	Stretching Audio Events to the Project Tempo	628	VST Instruments
475	Musical Mode	628	Adding VST Instruments
477	Auto Adjust	629	Creating Instrument Tracks
477	Manual Adjust	629	VST Instruments in the Right Zone
479	Free Warp	630	VST Instruments Window
481	Flattening Realtime Processing	630	VST Instruments Toolbar
481	Unstretching Audio Files	631	VST Instrument Controls
483	VariAudio (Cubase Pro only)	632	Presets for Instruments
483	VariAudio and Offline Processes	634	Playing Back VST Instruments
484	Segmenting Monophonic Audio	635	Latency
485	Segments and Gaps	636	Import and Export Options
485	Manual Editing of Segments	638	VST Quick Controls
490	Pitch Changes	639	Side-Chain Input for VST Instruments
493	Micro-Pitch Changes	640	External Instruments (Cubase Pro only)
497	Timing Modifications	641	Installing and Managing Plug-Ins
498	Reset Functions	641	Installing VST Plug-Ins
499	Extracting MIDI from Audio	641	VST Plug-In Manager
501	Flattening Realtime Processing	644	Compiling a New Effects Collection
502	Harmony Voices for Audio	645	Track Quick Controls
503	Audio Part Editor	646	Parameter Assignment
505	Toolbar	649	Quick Controls and Automatable Parameters
509	Info Line	651	Connecting Track Quick Controls with Remote Controllers
509	The Ruler	652	Remote Controlling Cubase
510	About Lanes	652	Connecting Remote Devices
510	Operations	652	Removing the Remote Input from All MIDI Inputs
514	Controlling Sample Playback with Sampler Tracks	653	Setting Up Remote Devices
514	Loading Audio Samples into Sampler Control	655	Remote Devices and Automation
514	Loading MIDI Parts into Sampler Control	655	Assigning Commands to Remote Devices
515	Creating Sampler Tracks	656	Generic Remote
515	Sampler Control	661	The Remote Control Editor
524	Sample Editing and Playback Functions	665	Joysticks
526	Transferring Samples from Sampler Control to VST Instruments	665	Apple Remote (macOS only)
527	Pool	666	Track Quick Controls
527	Pool Window	667	VST Quick Controls
531	Working with the Pool	668	MIDI Realtime Parameters and MIDI Effects
546	MediaBay	668	MIDI Track Parameters
546	Media Rack in Right Zone	670	MIDI Modifiers
552	MediaBay Window	675	MIDI Effects
578	Working with MediaBay-Related Windows	678	Transpose and Velocity on the Info Line
580	Working with Volume Databases	679	Using MIDI devices
582	MediaBay Settings	679	MIDI devices – general settings and patch handling
583	MediaBay Key Commands	687	About Device panels (Cubase Pro only)
584	Surround Sound (Cubase Pro only)	690	MIDI Functions
584	Deliverables	690	Transpose Setup
585	Available Surround Channel Configurations		
586	Preparations for Creating Surround Mixes		
589	VST MultiPanner		

691	Merging MIDI Events into a New Part	837	Chord Pads
692	Dissolve Part	837	Chord Pads
694	Bouncing MIDI Parts	840	Functions Menu
695	Repeating MIDI Events of Independent Track Loops	840	Preparations
695	Extending MIDI Notes	841	Chord Assistant
696	Fixing MIDI Note Lengths	843	Assigning Chords to Chord Pads
696	Fixing MIDI Note Velocities	846	Moving and Copying Chord Pads
696	Rendering Sustain Pedal Data to Note Lengths	847	Playing Back and Recording Chords
697	Deleting Overlaps	848	Chord Pad Settings – Remote Control
697	Editing Velocity	852	Chord Pad Settings – Players
698	Deleting Double Notes	857	Chord Pad Settings – Pad Layout
698	Deleting Controller Data	858	Chord Pads Presets
698	Deleting Continuous Controller Data	858	Creating Events from Chord Pads
699	Restricting Polyphonic Voices	860	Logical Editor
699	Thinning Out Controller Data	860	Window overview
699	Extracting MIDI Automation	861	Filter Conditions
700	Reversing the Playback Order of MIDI Events	870	Selecting a function
700	Inverting the Order of Selected MIDI Events	871	Specifying actions
700	Creating a Tempo Track from Tapping (Cubase Pro only)	874	Applying the Defined Actions
		874	Presets
702	MIDI Editors	876	Project Logical Editor (Cubase Pro only)
702	Common MIDI Editor Functions	876	Window Overview
709	Key Editor	877	Filter Conditions
720	Key Editor Operations	886	Specifying Actions
737	Basic Score Editor (Cubase Artist only)	889	Selecting a Function
743	Score Editor Operations (Cubase Artist only)	890	Applying Macros
750	Drum Editor	890	Applying the Defined Actions
764	Drum Editor Operations	890	Presets
767	Drum Maps	892	Editing Tempo and Time Signature
771	List Editor	892	Project Tempo Modes
780	List Editor Operations	892	Track Time Base
785	In-Place Editor	893	Tempo Track Editor
788	Expression Maps (Cubase Pro only)	894	Tempo Track
789	Articulations	896	Setting up Tempo Changes for Projects
789	Expression Map Setup	900	Setting up a Fixed Project Tempo
790	Creating and Editing Expression Maps	902	Beat Calculator
797	Inserting Articulations	903	Tempo Detection (Cubase Pro only)
800	Note Expression	904	Exporting a Tempo Track (Cubase Pro only)
800	VST 3 Controller Parameters	904	Importing a Tempo Track (Cubase Pro only)
801	MIDI Controller Parameters	905	Process Tempo (Cubase Pro only)
801	Note Expression Inspector Section	906	Process Bars (Cubase Pro only)
804	Note Expression Tools	906	Time Warp (Cubase Pro only)
805	Controller Parameter Mapping	908	Set Definition From Tempo
806	Recording	908	Time Signature Events
809	Note Expression Event Editor	911	Project Browser (Cubase Pro only)
814	Trimming Note Expression Data	911	Toolbar
815	Removing All Note Expression Data	912	Project Structure
815	Note Expression MIDI Setup Dialog	912	Event Display
819	Chord Functions	915	Rendering Audio and MIDI
819	Chord Track	915	Render Tracks
820	Chord Events	917	Render Selection
827	Scale Events	920	Export Audio Mixdown
828	Voicings	921	Mixing Down to Audio Files
830	Converting Chord Events to MIDI	922	Available Channels for Export
831	Controlling MIDI or Audio Playback Using the Chord Track	923	File Location
834	Assigning Voices to Notes	926	File Format
834	Extracting Chord Events from MIDI	932	Audio Engine Output
835	Recording Chord Events with a MIDI Keyboard	933	Import Into Project
		934	Post Process
		935	Synchronization
		935	Background

936	Timecode (positional references)	1035	Transport
938	Clock sources (speed references)	1036	User Interface
939	The Project Synchronization Setup dialog	1037	VST
943	Synchronized operation	1040	VariAudio (Cubase Pro only)
944	Example Scenarios (Cubase Pro only)	1041	Video
945	Working with VST System Link	1042	Index
948	Activating VST System Link		
956	Video		
956	Video File Compatibility		
957	Frame Rates		
957	Video Output Devices		
958	Preparations for Creating Video Projects		
960	Preparations for Video Playback		
962	Editing Video		
964	Exchanging Files with Other Applications		
964	OMF Files (Cubase Pro only)		
968	ReWire		
968	Introduction		
968	Enabling ReWire Applications		
969	Launching and quitting		
970	Activating ReWire channels		
970	Using the transport and tempo controls		
971	How the ReWire channels are handled		
971	Routing MIDI via ReWire		
972	Considerations and limitations		
973	Key Commands		
973	Adding Key Commands		
974	Searching for Key Commands		
974	Removing Key Commands		
974	Setting Up Macros		
975	Saving Key Commands Presets		
975	Loading Key Command Presets		
976	Importing Key Command Settings		
976	Resetting Key Commands		
977	The Default Key Commands		
988	Setting Up Tool Modifier Keys		
990	Customizing		
990	Workspaces		
994	Using the Setup Options		
995	Customizing the Meter Colors		
996	Customizing the User Interface Colors		
997	Color Selector Pane		
998	Coloring Tracks, Parts, or Events Manually		
998	Auto Track Color Mode		
999	Colorizing Track Controls		
1000	Project Colors Dialog		
1001	Profiles (Cubase Pro only)		
1005	Where are the Settings Stored?		
1007	Optimizing		
1007	Optimizing Audio Performance		
1011	Preferences		
1011	Preferences Dialog		
1013	Editing		
1020	Editors		
1021	Event Display		
1024	General		
1025	MIDI		
1030	MediaBay		
1030	Metering		
1031	Record		
1033	Scores (Cubase Pro only)		

Introduction

The documentation covers the following Steinberg products: Cubase Pro and Cubase Artist.

Functions that are only available in Cubase Pro and not in Cubase Artist are clearly indicated. The screenshots are taken from Cubase Pro.

Platform-Independent Documentation

The documentation applies to the operating systems Windows and macOS.

Features and settings that are specific to one of these platforms are clearly indicated. In all other cases, the descriptions and procedures in the documentation are valid for Windows and macOS.

Some points to consider:

- The screenshots are taken from Windows.
- Some functions that are available on the **File** menu on Windows can be found in the program name menu on macOS.

About the Documentation

The documentation consists of several documents. You can read them online or download them from **steinberg.help**. To visit **steinberg.help**, do one of the following:

- Enter www.steinberg.help in the address bar of your web browser.
- In the program, select **Help > Cubase Help**.

Quick Start Guide

Covers the following areas without going into details:

- System requirements, installation procedure, and license activation.
- Setting up your system for audio and MIDI work.

Operation Manual

The main Cubase reference documentation, with detailed descriptions of operations, parameters, functions, and techniques.

Score Layout and Printing (Cubase Pro only)

Describes the professional music notation, score editing, and printing features included in the **Score Editor**.

Remote Control Devices

Lists the supported MIDI remote control devices.

Plug-in Reference

Describes the features and parameters of the included VST plug-ins, VST instruments, and MIDI effects.

HALion Sonic SE

Describes the features and parameters of the included VST instrument HALion Sonic SE.

Groove Agent SE

Describes the features and parameters of the included VST instrument Groove Agent SE.

Retrologue

Describes the features and parameters of the included VST instrument Retrologue.

MIDI Devices

Describes how to manage MIDI Devices and device panels.

VST Connect SE (Cubase Pro only)

Describes how to work with the VST Connect SE features.

Conventions

In our documentation, we use typographical and markup elements to structure information.

Typographical Elements

The following typographical elements mark the following purposes.

PREREQUISITE

Requires you to complete an action or to fulfill a condition before starting a procedure.

PROCEDURE

Lists the steps that you must take to achieve a specific result.

IMPORTANT

Informs you about issues that might affect the system, the connected hardware, or that might bring a risk of data loss.

NOTE

Informs you about issues that you should consider.

EXAMPLE

Provides you with an example.

RESULT

Shows the result of the procedure.

AFTER COMPLETING THIS TASK

Informs you about actions or tasks that you can perform after completing the procedure.

RELATED LINKS

Lists related topics that you can find in this documentation.

Markup

Bold text indicates the name of a menu, option, function, dialog, window, etc.

EXAMPLE

To open the **Functions** menu, click **Functions Menu** in the top right corner of the **MixConsole**.

If bold text is separated by a greater-than symbol, this indicates a sequence of different menus to open.

EXAMPLE

Select **Project > Add Track**.

Key Commands

Many of the default key commands, also known as keyboard shortcuts, use modifier keys, some of which are different depending on the operating system.

When key commands with modifier keys are described in this manual, they are shown with the Windows modifier key first followed by the macOS and the key:

- Windows modifier key/macOS modifier key-Z
-

EXAMPLE

Ctrl/Cmd-Z means: press **Ctrl** on Windows or **Cmd** on macOS, then press **Z**.

Setting Up Your System

To use Cubase, you must set up your audio, and if required, your MIDI system.


Setting Up Audio

IMPORTANT

Make sure that all equipment is turned off before making any connections.

Simple Stereo Input and Output Setup

If you only use a stereo input and output from Cubase, you can connect your audio hardware, for example, the inputs of your audio card or your audio interface, directly to the input source and the outputs to a power amplifier and speaker.



Audio Connections

Your system setup depends on many different factors, for example, on the kind of project that you want to create, on the external equipment that you want to use, or on the computer hardware that is available to you. Therefore, the following sections can only serve as examples.

How to connect your equipment, that is, whether to use digital or analog connections also depends on your setup.

About Recording Levels and Inputs

When you connect your equipment, make sure that the impedance and levels of the audio sources and inputs are matched. Using the correct type of input is important to avoid distortion or noisy recordings. For example, different inputs can be used, such as consumer line level (-10 dBV) or professional line level (+4 dBu).

Sometimes, you can adjust input characteristics on the audio interface or on its control panel. For details, refer to the documentation that came with the audio hardware.

IMPORTANT

Cubase does not provide any input level adjustments for the signals that are coming into your audio hardware, since these are handled differently for each card. Adjusting input levels is either done in a special application that is included with the hardware or its control panel.

Word Clock Connections

If you are using a digital audio connection, you may also need a word clock connection between the audio hardware and external devices. For details, refer to the documentation that came with the audio hardware.

IMPORTANT

Set up word clock synchronization correctly, or you may experience clicks and crackles in your recordings.

Selecting an Audio Driver

By selecting an audio driver, you allow Cubase to communicate with the audio hardware. Normally, when you start Cubase, a dialog opens that prompts you to select a driver, but you can also select your audio hardware driver as described below.

NOTE

On Windows operating systems, we recommend that you access your hardware via an ASIO driver developed specifically for the hardware. If no ASIO driver is installed, contact the manufacturer of your audio hardware for information on available ASIO drivers. If no specific ASIO driver is available, you can use the Generic Low Latency ASIO driver.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **VST Audio System**.
 3. Open the **ASIO Driver** pop-up menu and select your audio hardware driver.
 4. Click **OK**.
-

Setting Up Audio Hardware

PREREQUISITE

You have selected a driver for your audio hardware.

PROCEDURE

1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select your audio hardware driver.

3. Do one of the following to open the control panel for your audio hardware:
 - On Windows, click **Control Panel**.
 - On macOS, click **Open Config App**.
This button is available only for some hardware products. If it is not available in your setup, refer to the documentation of your audio hardware.

NOTE


The control panel is provided by the manufacturer of your audio hardware and is different for each audio interface brand and model. However, control panels for the Generic Low Latency ASIO Driver (Windows only) are provided by Steinberg.

4. Set up your audio hardware as recommended by the manufacturer.
-

VST Audio System

In the **VST Audio System** section you can select an ASIO driver for your audio hardware.

- To open the **VST Audio System** section, select **Studio > Studio Setup** and select **VST Audio System** in the **Devices** list.



The following options are available:

ASIO Driver

Allows you to select a driver.

Release Driver when Application is in Background

Releases the driver and allows other applications to play back via your audio hardware even though Cubase is running.

Input Latency

Shows the input latency of the audio hardware.

Output Latency

Shows the output latency of the audio hardware.

ASIO-Guard Latency

Shows the ASIO-Guard latency.

HW Sample Rate

Shows the sample rate of your audio hardware.

HW Pull Up/Down

Shows the pull up/down status of the audio hardware.

Set to Defaults

Allows you to restore the default settings.

Processing Precision

Allows you to set the audio processing precision to 32 bit float or 64 bit float. Depending on this setting, all channels are processed and mixed in 32-bit floating-point or 64-bit floating-point format.

NOTE

A processing precision of 64 bit float can increase CPU load and memory consumption.

To show all plug-ins that support 64-bit float processing, open the **VST Plug-in Manager** and activate **Show Plug-ins That Support 64-Bit Processing** in the **Display Options** pop-up menu.

NOTE

VST2 plug-ins and instruments are always processed with 32-bit precision.

Activate Multi Processing

Allows you to distribute the processing load evenly to all available CPUs. This way, Cubase can make full use of the combined power of multiple processors.

Activate ASIO-Guard

Activates the ASIO-Guard. This is only available if **Activate Multi Processing** is activated too.

ASIO-Guard Level

Allows you to set the ASIO-Guard level. The higher the level, the higher the processing stability and audio processing performance. However, higher levels also lead to an increased ASIO-Guard latency and memory usage.

Audio Priority (Windows only)

This setting should be set to **Normal** if you work with audio and MIDI. If you do not use MIDI at all, you can set this to **Boost**.

Activate Steinberg Audio Power Scheme

If this option is activated, all power safe modes that have an impact on realtime processing are deactivated. Note that this is only effective for very low latencies, and that it increases the power consumption.

Disk Preload

Allows you to specify how many seconds of audio are preloaded into RAM prior to starting playback. This allows for smooth playback.

Adjust for Record Latency

If this is activated, the plug-in latencies are taken to account during recording.

Record Shift

Allows you to shift the recordings by the specified value.


RELATED LINKS

[VST Plug-In Manager Window](#) on page 641

ASIO Driver Setup

This section allows you to set up your ASIO driver.

- To open the section where you can set up the ASIO driver, select **Studio > Studio Setup** and select the audio driver in the **Devices** list.



The following options are available:

Control Panel

Opens the control panel for the audio hardware.

Input Latency

Shows the input latency of the audio driver.

Output Latency

Shows the output latency of the audio driver.

Clock Source

Allows you to select a clock source.

Externally Clocked

Activate this option if you use an external clock source.

Direct Monitoring

Activate this option to monitor via your audio hardware and to control it from Cubase.

Ports Reset

Allows you to reset all port names and visibilities.

I/O

The port input/output status.

Port System Name

The system name of the port.

Show As

Allows you to rename the port. This name is used in the **Input Routing** and **Output Routing** pop-up menus.

Visible

Allows you to activate/deactivate audio ports.

State

The state of the audio port.

Using External Clock Sources

If you are using an external clock source, Cubase must be notified that it receives external clock signals and derives its speed from that source.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select your audio hardware driver.
 3. Activate **Externally clocked**.
-

RESULT

Cubase now derives its speed from the external source.

NOTE

For proper audio playback and recording, you must set the sample rate of the project to the sample rate of the incoming clock signals.

When a sample rate mismatch occurs, the **Record Format** field on the status line is highlighted in a different color. Cubase accepts a sample rate mismatch, and playback is therefore faster or slower.

Using Several Audio Applications Simultaneously

You can allow other applications to play back via your audio hardware even though Cubase is running.

PREREQUISITE

Other audio applications accessing the audio hardware are set to release the audio driver.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **VST Audio System**.
 3. Activate **Release Driver when Application is in Background**.
-

RESULT

The application that has the focus gets access to the audio hardware.

Audio Hardware Configuration

Most audio cards provide one or more small applications that allow you to customize your hardware.

The settings are normally gathered on a control panel that can be opened from within Cubase or separately, when Cubase is not running. For details, refer to the audio hardware documentation.

Settings include:

- Selecting which inputs/outputs are active.
- Setting up word clock synchronization.
- Turning on/off monitoring via the hardware.
- Setting levels for each input.
- Setting levels for the outputs so that they match the equipment that you use for monitoring.
- Selecting digital input and output formats.
- Making settings for the audio buffers.

Setting Up Input and Output Ports

Once you have selected the driver for your audio hardware and have set it up, you must specify which inputs and outputs to use.

PREREQUISITE

You have selected a driver for your audio hardware.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select your audio hardware driver.
 3. Make your settings.
 4. Click **OK**.
-

RELATED LINKS

[ASIO Driver Setup](#) on page 15

Audio Bus Setup

Cubase uses a system of input and output busses to transfer audio between the program and the audio hardware.

- Input busses let you route audio from the inputs of your audio hardware into Cubase. This means that audio is always recorded through one or several input busses.
- Output busses let you route audio from Cubase to the outputs of your audio hardware. This means that audio is always played back through one or several output busses.

Once you have set up the internal input and output busses, you can connect your audio source, for example a microphone, to your audio interface and start recording, playing back, and mixing.

RELATED LINKS

[Audio Connections](#) on page 21

Monitoring

In Cubase, monitoring means listening to the input signal while recording.

The following ways of monitoring are available.

- Externally by listening to the signal before it reaches Cubase.
- Via Cubase.
- By using ASIO Direct Monitoring.
This is a combination of the other methods.

RELATED LINKS

[External Monitoring](#) on page 240

[Monitoring via Cubase](#) on page 240

[ASIO Direct Monitoring](#) on page 240

Setting Up MIDI

IMPORTANT

Turn off all equipment before making any connections.

PROCEDURE

1. Connect your MIDI equipment (keyboard, MIDI interface, etc.) to your computer.
 2. Install the drivers for your MIDI equipment.
-

RESULT

You can use your MIDI equipment in Cubase.

MIDI Connections

To play back and record MIDI data from your MIDI device, for example, a MIDI keyboard, you need to connect the MIDI ports.

Connect the MIDI output port of your MIDI device to the MIDI input port of your audio hardware. This way, the MIDI device sends MIDI data to be played back or recorded inside your computer.

Connect the MIDI input port of your MIDI device to the MIDI output port of your audio hardware. This way, you can send MIDI data from Cubase to the MIDI device. For example, you can record your own playing, edit the MIDI data in Cubase, and then play it back on the keyboard and record the audio that is coming out of the keyboard for a better edited performance.

Showing or Hiding MIDI Ports

You can specify if a MIDI port is listed on the MIDI pop-up menus in the program.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **MIDI Port Setup**.
 3. To hide a MIDI port, deactivate its **Visible** column.
 4. Click **OK**.
-

Setting Up All MIDI Inputs

When you record MIDI, you can specify which MIDI input each recording MIDI track should use. However, you can also record any MIDI data from any MIDI input. You can specify which inputs are included when you select **All MIDI Inputs** for a MIDI track.

PROCEDURE

1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select **MIDI Port Setup**.
3. Activate **In 'All MIDI Inputs'** for a port.

NOTE

If you have a MIDI remote control unit connected, make sure to deactivate the **In 'All MIDI Inputs'** option for that MIDI input. This avoids accidental recording of data from the remote control when **All MIDI Inputs** is selected as input for a MIDI track.

4. Click **OK**.


RESULT

When you select **All MIDI Inputs** on the **Input Routing** menu of a MIDI track in the Inspector, the MIDI track uses all MIDI inputs that you specified in the **MIDI Port Setup**.

MIDI Port Setup

The **MIDI Port Setup** page in the **Studio Setup** dialog displays the connected MIDI devices and allows you to set up their ports.

- To open the **MIDI Port Setup** page, select **Studio > Studio Setup** and activate **MIDI Port Setup** in the **Devices** list.



The following columns are displayed:

Device

The connected MIDI devices.

I/O

The port input/output status.

Port System Name

The system name of the port.

Show As

Allows you to rename the port. This name is used in the **Input Routing** and **Output Routing** pop-up menus.

Visible

Allows you to activate/deactivate MIDI ports.

State

The state of the MIDI port.

In 'All MIDI Inputs'

Allows you to record MIDI data from all MIDI inputs.

NOTE

Deactivate this option if you use remote control devices.

The following options are available:

Use System Timestamp for 'Windows MIDI' Inputs

Activate this option if you have persistent timing problems such as shifted notes. If this is activated, the system timestamp is used as a time reference.

Use Device 'DirectMusic'

If you do not use a device with a DirectMusic device driver, you can leave this option deactivated. This enhances the system performance.

Use System Timestamp for 'DirectMusic' Inputs

Activate this option if you have persistent timing problems such as shifted notes. If this is activated, the system timestamp is used as a time reference.

Plug and Play Support for USB MIDI Devices

Cubase supports plug and play of USB MIDI devices. These devices can be plugged in and switched on while the application is running.

Connecting a Synchronizer

When using Cubase with external tape transports, you most likely must add a synchronizer to your system.

IMPORTANT

Make sure that all equipment is turned off before making any connections.

For information on how to connect and set up your synchronizer, refer to the documentation of your synchronizer.

RELATED LINKS

[Synchronization](#) on page 935

Audio Connections

To play back and record in Cubase, you must set up input and output busses in the **Audio Connections** window. Here, you can also set up group and FX channels, external effects, external instruments, and the **Control Room** (Cubase Pro only).

The bus types that you need depend on your audio hardware, on your general audio setup, for example your surround speaker setup, and on the projects that you use.


Audio Connections Window

The **Audio Connections** window allows you to set up input and output busses, group and FX channels, external effects, and external instruments. Furthermore, you can use this window to access and configure the **Control Room** (Cubase Pro only).

- To open the **Audio Connections** window, select **Studio > Audio Connections**.

Inputs/Outputs Tab

The **Input** and **Output** tabs allow you to set up and configure input and output busses.



The following options are available above the bus list:

+ - All

Expands/Collapses all busses in the bus list.

Add Bus

Opens the **Add Input Bus** dialog, where you can create a new bus configuration.

Presets

Opens the **Presets** menu, where you can select bus configuration presets. **Store**  allows you to save a bus configuration as preset. **Delete**  deletes the selected preset.

The following columns are available for the bus list:

Bus Name

Lists the busses. Click the name of a bus to select or rename it.

Speakers

Indicates the speaker configuration (mono, stereo, surround formats (Cubase Pro only)) of each bus.

Audio Device

Shows the selected ASIO driver.

Device Port

Shows which physical inputs/outputs on your audio hardware are used by the bus. Expand the bus entry to show all speaker channels. If the bus entry is collapsed, only the first port that is used by this bus is visible.


The **Device Port** pop-up menu displays how many busses are connected to a given port. The busses are shown in square brackets next to the port name.

Up to 3 bus assignments can be displayed in this way. If more connections have been made, this is indicated by a number at the end of the port name.

For example, "Adat 1 [Stereo1] [Stereo2] [Stereo3] (+2)" means that the Adat1 port is already assigned to 3 stereo busses plus 2 additional busses.

Group/FX Tab (Cubase Pro only)

This tab allows you to create group and FX channels/tracks and to make output assignments for these.



The following options are available above the bus list:

+ - All

Expands/Collapses all busses in the bus list.

Add Group

Opens the **Add Group Channel Track** dialog, where you can create a new group channel track.

Add FX

Opens the **Add FX Channel Track** dialog, where you can create a new FX channel track.

The following columns are available for the bus list:

Bus Name

Lists the busses. Click the name of a bus to select or rename it.

Speakers

Indicates the speaker configuration (mono, stereo, surround formats (Cubase Pro only)) of each bus.

Output Routing

Lets you select the output routing for the corresponding bus.

External FX Tab (Cubase Pro only)

This tab allows you to create send effect or return busses. You can use these to connect external effects which can then be selected via the effect pop-up menus from inside the program.

Inputs		Outputs		Group/FX		External FX		External Instruments		Control Room	
All		Add External FX		Favorites							
Bus Name	Speakers	Audio Device	Device Port	Delay	Send Gain	Return Gain	MIDI Device	Used			
External Effect	Stereo/Stereo			0.00 ms (0)	0.00 dB	0.00 dB	No Link				
Send Bus 1	Stereo	Yamaha Steinberg USB ASIO									
Left			UR44 Mix 2 L								
Right			UR44 Mix 2 R								
Return Bus 1	Stereo	Yamaha Steinberg USB ASIO									
Left			UR44 Input 3								
Right			UR44 Input 4								

The following options are available above the bus list:

+ - All

Expands/Collapses all busses in the bus list.

Add External FX

Opens the **Add External FX** dialog, where you can configure a new external FX.

Favorites

Lets you store external effect configurations as favorites that you can recall.

The following columns are available for the bus list:

Bus Name

Lists the busses. Click the name of a bus to select or rename it.

Speakers

Indicates the speaker configuration (mono, stereo, surround formats (Cubase Pro only)) of each bus.

Audio Device

Shows the selected ASIO driver.

Device Port

Shows which physical inputs/outputs on your audio hardware are used by the bus. Expand the bus entry to show all speaker channels. If the bus entry is collapsed, only the first port that is used by this bus is visible.

The **Device Port** pop-up menu displays how many busses are connected to a given port. The busses are shown in square brackets next to the port name.

Up to 3 bus assignments can be displayed in this way. If more connections have been made, this is indicated by a number at the end of the port name.

For example, "Adat 1 [Stereo1] [Stereo2] [Stereo3] (+2)" means that the Adat1 port is already assigned to 3 stereo busses plus 2 additional busses.

Delay

Allows you to enter a value to compensate for an inherent delay (latency) of your hardware effect device during playback. You can right-click the **Delay** column for the effect and select **Check User Delay** to automatically determine the delay value.

NOTE

The latency of the audio hardware is handled automatically by Cubase.

Send Gain

Allows you to adjust the level of the signal that is sent to the external effect.

Return Gain

Allows you to adjust the level of the signal that the external effect sends.

NOTE

Excessive output levels from an external effect device can cause clipping in the audio hardware. You cannot use the **Return Gain** setting to compensate for this. You must lower the output level on the effect device instead.

MIDI Device

When you click in this column, a pop-up menu opens where you can disconnect the effect from the associated MIDI device, select a MIDI device, create a new device, or open the **MIDI Device Manager** to edit the MIDI device.

Used

Whenever you insert an external effect into an audio track, this column shows a checkmark (x) to indicate that the effect is being used.

External Instruments Tab (Cubase Pro only)

This tab allows you to create input/output busses that can be used to connect external instruments.

Bus Name	Speakers	Audio Device	Device Port	Delay	Return Gain	MIDI Device	Used
External Instrument	1 Return(s)			0.00 ms (0)	0.00 dB	No Link	
Return Bus 1	Stereo	Yamaha Steinberg USB ASIO					
Left			UR44 Input 5				
Right			UR44 Input 6				

The following options are available above the bus list:

+ - All

Expands/Collapses all busses in the bus list.

Add External Instrument

Opens the **Add External Instrument** dialog, where you can configure a new external instrument.

Favorites

Lets you store external instrument configurations as favorites that you can recall.

The following columns are available for the bus list:

Bus Name

Lists the busses. Click the name of a bus to select or rename it.

Speakers

Indicates the speaker configuration (mono, stereo, surround formats (Cubase Pro only)) of each bus.

Audio Device

Shows the selected ASIO driver.

Device Port

Shows which physical inputs/outputs on your audio hardware are used by the bus. Expand the bus entry to show all speaker channels. If the bus entry is collapsed, only the first port that is used by this bus is visible.

The **Device Port** pop-up menu displays how many busses are connected to a given port. The busses are shown in square brackets next to the port name.

Up to 3 bus assignments can be displayed in this way. If more connections have been made, this is indicated by a number at the end of the port name.

For example, "Adat 1 [Stereo1] [Stereo2] [Stereo3] (+2)" means that the Adat1 port is already assigned to 3 stereo busses plus 2 additional busses.

Delay

Allows you to enter a value to compensate for an inherent delay (latency) of your hardware effect device during playback. You can right-click the **Delay** column for the instrument and select **Check User Delay** to automatically determine the delay value that is used for delay compensation.

NOTE

The latency of the audio hardware is handled automatically by Cubase.

Return Gain

Allows you to adjust the level of the signal coming in from the external instrument.

NOTE

Excessive output levels from an external effect device can cause clipping in the audio hardware. The **Return Gain** setting cannot be used to compensate for this. You must lower the output level on the effect device instead.

MIDI Device


When you click in this column, a pop-up menu opens where you can disconnect the instrument from the associated MIDI device, select a MIDI device, create a new device, or open the **MIDI Device Manager** to edit the MIDI device.

Used

Whenever you insert the external instrument into a VST instrument slot, this column shows a checkmark (x) to indicate that the instrument is being used.

Control Room Tab (Cubase Pro only)

This tab allows you to enable and configure the **Control Room**.



The following options are available above the bus list:

+ - All

Expands/Collapses all busses in the bus list.

Add Channel

Opens a menu where you can select the type of channel that you want to add. You can add the following channels:

- External Input
- Talkback
- Cue
- Headphone
- Monitor

Presets

Opens the **Presets** menu, where you can select bus configuration presets. **Store**  allows you to save a bus configuration as preset. **Delete**  deletes the selected preset.

Enable/Disable Control Room

Enables/Disables the **Control Room**.

Open Control Room

Opens the **Control Room** window.

Configuration

Displays the selected channel configuration.

The following columns are available for the bus list:

Bus Name

Lists the busses. Click the name of a bus to select or rename it.

Speakers

Indicates the speaker configuration (mono, stereo, surround formats (Cubase Pro only)) of each bus.

Audio Device

Shows the selected ASIO driver.

Device Port

Shows which physical inputs/outputs on your audio hardware are used by the bus. Expand the bus entry to show all speaker channels. If the bus entry is collapsed, only the first port that is used by this bus is visible.

The **Device Port** pop-up menu displays how many busses are connected to a given port. The busses are shown in square brackets next to the port name.

Up to 3 bus assignments can be displayed in this way. If more connections have been made, this is indicated by a number at the end of the port name.

For example, "Adat 1 [Stereo1] [Stereo2] [Stereo3] (+2)" means that the Adat1 port is already assigned to 3 stereo busses plus 2 additional busses.

RELATED LINKS

[Control Room \(Cubase Pro only\)](#) on page 372

Renaming the Hardware Inputs and Outputs

Before you set up busses, you should rename the default inputs and outputs of your audio hardware. This allows transferring projects between different computers and setups.

For example, if you move your project to another studio, the audio hardware may be of a different model. But if you and the other studio owner have agreed on identical names for your inputs and outputs, Cubase corrects inputs and outputs for your busses.

NOTE

If you open a project that was created on another computer and the port names do not match or the port configuration is not the same, the **Missing Ports** dialog appears. This allows you to manually re-route ports that are used in the project to ports that are available on your computer.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **VST Audio System**.
 3. Open the **ASIO Driver** pop-up menu and select your audio hardware driver.
 4. In the **Devices** list, select your audio hardware driver.
 5. In the **Show As** column, click on a port name and enter a new name.
 6. Repeat the previous step until you have renamed all required ports.
 7. Click **OK**.
-

RELATED LINKS

[Re-Routing Missing Ports](#) on page 91

Hiding Ports

You can hide ports that you are not using. Hidden ports are not displayed in the **Audio Connections** window.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select your audio hardware driver.
 3. In the **Visible** column, deactivate the ports that you want to hide.
 4. Click **OK**.
-

Activating and Deactivating Ports (macOS only)

On macOS you can specify which input and output ports are active. This allows you to use the microphone input instead of the line input or to deactivate the audio card input or output.

NOTE

This function is only available for built-in audio, standard USB audio devices, and a certain number of other audio cards.

PROCEDURE

1. Select **Studio > Studio Setup**.

2. In the **Devices** list, select your audio hardware driver.
 3. Click **Control Panel**.
 4. Activate/Deactivate ports.
 5. Click **OK**.
-

Adding Input and Output Busses

PROCEDURE

1. In the **Audio Connections** dialog, click the **Inputs** or **Outputs** tab.
 2. Click **Add Bus**.
 3. In the **Add Input Bus** dialog, configure the bus.
 4. Optional: Enter a name for the bus.
If you do not specify a name, the bus is named according to the channel configuration.
 5. Click **Add Bus**.
The new bus is added to the bus list.
 6. For each of the speaker channels in the bus, click in the **Device Port** column and select a port of your audio hardware.
-

Setting the Default Output Bus (Main Mix)

The **Main Mix** is the default output bus to which each new audio, group, or FX channel is automatically routed. If only one bus is available, this bus is automatically used as the default output bus.

PREREQUISITE

Add an output bus.

PROCEDURE

1. In the **Audio Connections** dialog, right-click the output bus that you want to use as default output bus.
 2. Select **Set <bus name> as Main Mix**.
-

RESULT

The selected bus is used as default bus. The **Main Mix** is indicated by a speaker icon next to its name.

RELATED LINKS

[Inputs/Outputs Tab](#) on page 21

Adding Child Busses (Cubase Pro only)

Child busses allow you to route tracks to particular channels within a bus.

For example, you can route a stereo track to a stereo channel pair within a surround bus. Or you can record a stereo channel pair in the surround bus to a separate stereo track.

PROCEDURE

1. On the **Inputs** tab, **Outputs** tab, or **Group/FX** tab, right-click a surround bus.

2. Click **Add Child Bus** and select a channel configuration.
-

RESULT

The child bus is created and can be used for routing.

Presets for Input and Output Busses

For input and output bus configurations, you can use different kinds of presets.

- A number of standard bus configurations.
- Automatically created presets tailored to your specific hardware configuration.
On startup, Cubase analyzes the physical inputs and outputs that are provided by your audio hardware and creates a number of hardware-dependent presets.
- Your own presets.

NOTE

You can create default presets for input and output bus configurations. If you create a new empty project, these default presets are applied. To create default presets, save your preferred input and output bus configurations under the name **Default**. If you have not defined default presets, the last used input and output bus configuration is applied when creating a new empty project.

Saving a Bus Configuration Preset

You can save your own input and output bus configuration and the studio configuration as presets.

PROCEDURE

1. Select **Studio > Audio Connections**.
 2. Set up your bus configuration.
 3. Click **Store** .
 4. In the **Type in Preset Name** dialog, enter a name.
 5. Click **OK**.
-

RESULT

The preset is available in the **Presets** menu.

Deleting a Bus Configuration Preset

PROCEDURE

1. Select **Studio > Audio Connections**.
 2. From the **Presets** menu, select the preset that you want to delete.
 3. Click **Delete** .
-

RESULT

The preset is deleted.

Adding Group and FX Channels (Cubase Pro only)

Group channels and FX channels allow you to group bus configurations.

Adding group and FX channels in the **Audio Connections** window is identical to creating group channel tracks or FX channel tracks in the **Project** window.

PROCEDURE

1. In the **Audio Connections** dialog, click the **Group/FX** tab.
 2. Do one of the following:
 - To create a group channel, click **Add Group**.
 - To create an FX channel, click **Add FX**.
 3. Configure the channel.
 4. Optional: Enter a name for the group channel track.
 5. Click **Add Track**.
The group channel or FX channel is added to the bus list.
 6. For each of the speaker channels in the bus, click in the **Output Routing** column and select a port of your audio hardware.
-

RELATED LINKS

[Audio Effects](#) on page 391

About Monitoring

In the **Audio Connections** window, you can set up the busses that are used for monitoring, activate/deactivate and open the **Control Room**.

When the **Control Room** is disabled on the **Control Room** tab of the **Audio Connections** window, the **Main Mix** bus is used for monitoring. In this case, you can adjust the monitoring level in the **MixConsole**.

In Cubase Artist, the **Main Mix** bus is always used for monitoring.

RELATED LINKS

[Control Room \(Cubase Pro only\)](#) on page 372

[MixConsole](#) on page 317

External Instruments and Effects (Cubase Pro only)

You can integrate external effect devices and external instruments, for example, hardware synthesizers, into the sequencer signal flow.

Requirements

- To use external effects, you need audio hardware with multiple inputs and outputs. An external effect requires at least one input and one output or input/output pairs for stereo effects in addition to the input/output ports that you use for recording and monitoring.
- To use external instruments, a MIDI interface must be connected to your computer.
- Audio hardware with low-latency drivers.
Cubase compensates for the input/output latency and ensures that the audio that is processed through external effects is not shifted in time.

Connecting an External Instrument/Effect

PREREQUISITE

The hardware device has stereo inputs and outputs.

PROCEDURE

1. Connect an unused output pair on your audio hardware to the input pair on your external hardware device.
2. Connect an unused input pair on your audio hardware to the output pair on your hardware device.

IMPORTANT

If you select input/output ports for external instruments/effects that are already used, the existing port assignment breaks without warning.


AFTER COMPLETING THIS TASK

Once the external device is connected to the audio hardware of your computer, you must set up the input/output busses in Cubase.

Setting Up External Effects

PROCEDURE

1. In the **Audio Connections** window, click the **External FX** tab.
2. Click **Add External FX**.
3. In the **Add External FX** dialog, enter a name for the external effect and specify the send and return configurations.
Depending on the type of effect, you can specify mono, stereo, or surround configurations.
4. Click **Associate MIDI Device** and select a MIDI device.



You can also select **MIDI Devices > Create Device** and create a new MIDI device association.

NOTE

Delay compensation is only applied for the effect when you use MIDI devices.

5. Click **OK**.
This adds a new external FX bus.
6. Click in the **Device Port** column for the left and right ports of the send bus and select the outputs of your audio hardware that you want to use.
7. Click in the **Device Port** column for the left and right ports of the return bus and select the inputs of your audio hardware that you want to use.

8. Make additional settings for the bus.
You can also adjust the settings while using the external effect. This allows you to hear the result.
-

RELATED LINKS

[Using MIDI devices](#) on page 679

[Delay Compensation](#) on page 636

Adding External Effects


You can use the external FX bus as an insert effect or as a send effect, which is an insert effect on an FX channel track.

PREREQUISITE


Set up your external effects in the **Audio Connections** window.

PROCEDURE

1. In the **Inspector**, open the **Inserts** panel.
2. Open the **Select Insert** menu.



3. Select an external effect from the **External Plug-ins** submenu.
External effects are indicated by an **x** icon in the list next to their names in the **Select Insert** pop-up menu.



RESULT

The external FX bus is loaded into the effect slot.

A parameter window opens, showing the Delay, Send Gain, and Return Gain settings for the external FX bus. You can adjust these settings while playing back.

The audio signal from the channel is sent to the outputs on the audio hardware, through your external effect device, and back to the program via the inputs on the audio hardware.


RELATED LINKS

[Setting Up External Effects](#) on page 31

External Effect Parameter Window

This window allows you to make delay and gain settings for the selected external effect.

When you select an external effect from the **Select Insert** menu in the **Inspector**, the **External Effect Parameter** window opens.



Activate Effect



Activates/Deactivates the external effect.

Bypass Effect



Allows you to bypass the external effect.

Measure Effect's Loop Delay for Delay Compensation



If this option is activated, Cubase automatically determines the delay value that is used for delay compensation. This is the same function as the **Check User Delay** option in the **Audio Connections** window.

When you have defined a MIDI device for the effect, the corresponding device window opens.

Delay

Allows you to adjust the delay for the external effect.

Send Gain

Allows you to adjust the send gain for the external effect.

Return Gain

Allows you to adjust the return gain for the external effect.

Setting Up External Instruments

PROCEDURE

1. In the **Audio Connections** window, click the **External Instruments** tab.
2. Click **Add External Instrument**.
3. In the **Add External Instrument** dialog, enter a name for the external instrument and specify the number of required mono and/or stereo returns.
Depending on the type of instrument, a specific number of mono and/or stereo return channels is required.
4. Click **Associate MIDI Device** and select a MIDI device.
5. Click **OK**.
This adds a new external instrument bus.
6. Click in the **Device Port** column for the left and right ports of the return bus and select the inputs of your audio hardware to which you connected the external instrument.
7. Make additional settings for the bus.
You can also adjust the settings while using the external instrument. This allows you to hear the result.

RELATED LINKS

[Using MIDI devices](#) on page 679


Adding External Instruments

PREREQUISITE

Set up your external instruments in the **Audio Connections** window.

PROCEDURE

1. Select **Studio > VST Instruments**.
The **VST Instruments** window opens.
2. Click **Add Track Instrument** .
The **Add Instrument Track** window opens.
3. Select an external instrument from the **Instrument** pop-up menu.
External instruments are indicated by an **x** icon in the list next to their names in the **Instrument** pop-up menu.



4. Click **Add Track**.
-

RESULT


The external instrument is added to the VST instruments list.

A parameter window for the external instrument opens. This can either be the device window that allows you to create a generic device panel, an OPT editor window, or a default editor.

External Instruments Parameter Window

This window allows you to make delay and gain settings for the selected external instrument.

When you select an external instrument in the **VST Instruments** window, the **External Instrument Parameter Window** opens.



Activate External Instrument



Activates/Deactivates the external instrument.

Bypass External Instrument



Allows you to bypass the external instrument.

Delay

Allows you to adjust the delay for the external instrument.

Return Gain

Allows you to adjust the return gain for the external instrument.

Sending MIDI Notes to External Instruments

PREREQUISITE

Set up your external instruments in the **Audio Connections** window and add a MIDI track.

PROCEDURE

1. In the **Inspector**, open the **Output Routing** pop-up menu for the corresponding MIDI track.
 2. Select the MIDI device to which the external instrument is connected.
-

RESULT

The instrument plays any MIDI notes that it receives from the track and returns them to Cubase through the return channels that you have set up. Delay compensation is used. The external instrument behaves like any other VST instrument in Cubase.

RELATED LINKS

[Delay Compensation](#) on page 636

Saving External Instrument and Effect Configurations as Favorites

You can save external instruments and external effects as favorites. Favorites are device configurations that you can recall. They also allow you to save different configurations for the same device, for example, a multi-effect board or an effect that provides both a mono and a stereo mode.

You can save and restore the favorites in the **External Instruments** and **External FX** tabs of the **Audio Connections** window.

- To save an external instrument or effect configuration as a favorite, select the **Bus Name**, click **Favorites**, and select **Add Selected Effect <effect name> to Favorites**.
- To recall a favorite, click **Favorites** and select the configuration that you want to recall.

Freezing External Instruments/Effects


You can freeze external instruments and effects to save processing power.

NOTE

You must perform the freeze function in realtime. Otherwise external effects are not taken into account.

When freezing external instruments or effects, you can adjust the corresponding **Tail Size** value in the **Freeze Channel Options** dialog.

When the **Tail Size** is set to 0 s, freezing only takes into account the data within the part boundaries.



RELATED LINKS

[VST Instruments](#) on page 628
[Audio Effects](#) on page 391
[Freezing Instruments](#) on page 634
[Freezing Insert Effects](#) on page 397

Missing Plug-ins

The "Plug-in could not be found" message appears in the following situations:

- When you remove an external device from the **Audio Connections** window although it is used in a saved project.
- When you transfer a project to another computer on which the external device is not defined.
- When you open a project that is created with an earlier version of Cubase.

In the **Audio Connections** window, the broken connection to the external device is indicated by an icon in the **Bus Name** column.

- To reestablish the broken connection to the external device, right-click the entry for the device in the **Bus Name** column and select **Connect External Effect**.

NOTE

Busses that are set up for external instruments or external effects are saved globally, that is, for your particular computer setup.

Editing the Bus Configurations

After you have set up all the required busses for a project you can edit the names and change port assignments. The bus configuration is saved with the project.

Removing Busses

PROCEDURE

- In the **Audio Connections** window, right-click a bus in the list and select **Remove Bus**. You can also select the bus and press **Backspace**.
-

Changing Port Assignments

You can change the port assignment of busses in the **Audio Connections** window.

- To change a port assignment, click in the **Device Port** column of a bus and select a new port.
- To assign different ports to the selected busses, open the **Device Port** pop-up menu for the first selected entry, press **Shift**, and select a device port. All subsequent busses are automatically connected to the next available port.

NOTE

Cubase Pro only: Exclusive ports, for example, ports that are already assigned to **Control Room** channels, are skipped.

- To assign the same port to all selected busses, open the **Device Port** pop-up menu for the first selected entry, press **Shift-Alt**, and select a device port.

Renaming Multiple Busses

You can rename all the selected busses at once using incrementing numbers or letters.

- To use incrementing numbers, select the busses that you want to rename and enter a new name for one of the busses, followed by a number. For example, if you have 8 inputs that you want to be named "In 1, In 2, ..., In 8", you select all the busses and enter the name **In 1** for the first bus. All other busses are then renamed automatically.

- To use letters from the alphabet, select the busses that you want to rename and enter a new name for one of the busses, followed by a space and a capital letter.
For example, if you have 3 FX channels that you want to be named "FX A, FX B, and FX C", you select all the channels and enter the name FX A for the first. All other channels are renamed automatically. The last letter that can be used is Z. If you have more selected entries than there are letters available, the remaining entries are skipped.

NOTE

You can begin renaming from any position in the list. The renaming starts from the bus where you edit the name, goes down the list to the bottom, and then continues from the top until all selected busses have been renamed.

Identifying Exclusive Port Assignments

For certain channel types, the port assignment is exclusive.

Once a port has been assigned to such a bus or channel, it must not be assigned to another bus, otherwise the connection to the first bus will be broken.


The corresponding ports are marked in the **Audio Connections** window on the **Device Port** pop-up menu.

Project Window

The **Project** window provides an overview of the project, and allows you to navigate and perform large scale editing.

Each project has one **Project** window. The **Project** window is displayed whenever you open or create a new project.

- To open a project, select **File > Open**.
- To create a new project, select **File > New Project**.



The **Project** window is divided into several zones:

1 Left Zone

The left zone shows the **Track Inspector** for the selected track or the **Editor Inspector** for the editor in the lower zone.

The **Visibility Inspector** allows you to show or hide individual tracks from the track list.

2 Project Zone

The project zone shows the toolbar, the track list with the tracks, the event display with the parts and events of the project, and the **Project** window ruler.

On the toolbar, you can activate/deactivate the status line, the info line, the overview line, and the transport.

3 Lower Zone

The lower zone shows the **Chord Pads**, the **Editor**, the **Sampler Control**, and the **MixConsole**.

4 Right Zone

The right zone shows the **VSTi** rack, the **Media** rack, the **Control Room** rack (Cubase Pro only), and the **Meter** rack (Cubase Pro only).

RELATED LINKS

[Project Zone](#) on page 39

[Left Zone](#) on page 51

[Lower Zone](#) on page 61

[Right Zone](#) on page 67

[Toolbar](#) on page 40

Showing/Hiding Zones

You can show/hide the zones in the **Project** window according to your needs.

PROCEDURE

- Do one of the following:
 - To show/hide the left zone, click **Show/Hide Left Zone**  on the **Project** window toolbar.
 - To show/hide the lower zone, click **Show/Hide Lower Zone**  on the **Project** window toolbar.
 - To show/hide the right zone, click **Show/Hide Right Zone**  on the **Project** window toolbar.


NOTE

The project zone is always shown.

Project Zone

The project zone is the heart of the **Project** window and cannot be hidden.

The project zone features the track list and the event display with the ruler. Furthermore, you can activate/deactivate the status line, the info line, the overview line, and the transport for the project zone.



RELATED LINKS

- [Track List](#) on page 44
- [Event Display](#) on page 45
- [Global Track Controls](#) on page 45
- [Ruler](#) on page 46
- [Status Line](#) on page 48
- [Info Line](#) on page 48
- [Overview Line](#) on page 49
- [Transport](#) on page 49

Toolbar

The toolbar contains tools and shortcuts for opening other windows and various project settings and functions.

- To show/hide tools, open the toolbar context menu by right-clicking in an empty area of the toolbar and activate the tools that you want to display. To show all tools, select **Show All**.

NOTE

The number of elements that are shown also depends on the size of the **Project** window and the screen resolution.

The following options are available:

Activate Project



NOTE

This button is only available if more than one project is open.

Allows you to activate a project.

Project History




Allows you to undo/redo actions in the **Project** window.

Constrain Delay Compensation



Allows you to minimize the latency effects of the delay compensation.

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

Media & MixConsole Windows




These buttons allow you to open or close the **MediaBay**, the **Pool**, the **MixConsole**, the **Control Room** (Cubase Pro only), and the **Direct Offline Processing** (Cubase Pro only).

Track Visibility Configurations




Allows you to create configurations that are useful for switching between different visibility setups.

State Buttons



These buttons show the mute, solo, listen, and automation states.

Automation Mode (Cubase Pro only)




Shows the automation mode and allows you to open the **Automation Panel**. Activate **Automation Follows Events** if you want your automation events to follow automatically when you move an event or part on a track.

Auto-Scroll



Allows you to keep the project cursor visible during playback.

Locators



Allows you to go to the left or right locator position, and to set the left and right locator position numerically.

Shows the left and right locator positions.

Transport Buttons



Shows the main transport controls.

External Sync State



Allows you to activate/deactivate external synchronization and to open the **Project Synchronization Setup** dialog.

Arranger Controls



Shows the controls for the arranger track.

Time Display



Shows the position of the project cursor in the selected time format.

Markers



Allows you to set and locate marker positions.

Tool Buttons



Shows the buttons for editing in the project zone.

Color Menu



Allows you to define the project colors.

Nudge Palette



Allows you to nudge or trim events or parts.

Project Root Key



Allows you to change the root key of the project.

Snap to Zero Crossing



If this option is activated, it finds zero crossings when you split and size audio events.

Snap On/Off



Allows you to activate/deactivate snap to restrict horizontal movement and positioning to certain positions.

Snap Type



Allows you to specify to what positions you want events to snap.

Grid Type



Allows you to specify a grid type for the snap function. This setting only has effect if **Snap Type** is set to one of the grid options.

Quantize



Allows you to move recorded audio or MIDI to musical relevant positions.

System Performance Meter



Shows the meters for ASIO time usage and hard disk transfer load.

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls



Allows you to show or hide the left zone, the lower zone, and the right zone of the **Project** window. The **Setup Window Layout** pop-up menu allows you to show or hide the status line, the info line, the overview line, and the **Transport**.

Set Up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.

RELATED LINKS

[Left/Right Toolbar Divider](#) on page 43

[Snap Types](#) on page 79

[Arranger Track](#) on page 290

[Markers](#) on page 307

[Automation](#) on page 606

[Synchronization](#) on page 935

Left/Right Toolbar Divider

The left and right toolbar dividers allow you to lock the position of specific tools at the left or at the right side of the toolbar, so that they are always shown.

All other items are shown in the center of the toolbar. When you reduce the width of the **Project** window, these toolbar items are hidden successively. When you increase the width, they are shown again.

Toolbox

The toolbox makes the editing tools from the toolbar available at the mouse pointer position. It can be opened instead of the standard context menus in the event display and editors.



- To activate the toolbox function, activate **Pop-up Toolbox on Right-Click** in the **Preferences** dialog (**Editing—Tools** page).
- To open the toolbox, right-click in the event display or editor.
If **Pop-up Toolbox on Right-Click** is deactivated, the context menu opens.
- To open the context menu instead of the toolbox, press any modifier key and right-click in the event display or editor.
If **Pop-up Toolbox on Right-Click** is deactivated, press any modifier key to open the toolbox instead of the context menu.
- To change the number of rows in which the tools are arranged on the toolbox, keep the right mouse button pressed on the toolbox until the mouse pointer changes to a double arrow, and drag to the bottom or right.



Track List

The track list shows the tracks that are used in the project. When a track is added and selected, it contains name fields and settings for this track.



- To decide which controls are visible for each track type, right-click the track list and open the **Track Controls Settings** dialog.

RELATED LINKS

[Track Control Settings](#) on page 96

Dividing the Track List

You can divide the track list into an upper track list and a lower track list. These track lists can have independent zoom and scroll controls.

Dividing the track list is useful if you are working with a video track and multi-track audio, for example. It allows you to place the video track in the upper track list and to scroll the audio tracks separately in the lower track list, so that they can be arranged with the video.

- To divide the track list, select **Project > Divide Track List**.
You can also click **Divide Track List** in the top right corner of the **Project** window below the ruler.




Video, marker, or arranger tracks are automatically moved to the upper track list. All other track types are moved to the lower track list.

- To move any type of track from the lower track list to the upper and vice versa, right-click it in the track list and select **Toggle Track List** from the context menu.
- To resize the upper part of the track list, click and drag the divider between the track list sections.
- To revert to a single track list, click **Divide Track List** again.

Event Display

The event display shows the parts and events that are used in the project. They are positioned along the timeline.



Global Track Controls

The global track controls above the track list allows you to manage the tracks in the track list.



1 Filter Track Types

Allows you to determine which track types are shown in the track list.

2 Number of Visible Tracks

Displays how many tracks are hidden. Click this, to show all tracks that are filtered out with the **Track Visibility**.

NOTE

If the track was outside the view or hidden, it is now shown. Tracks that are hidden using **Filter Track Types** are not shown.

3 Add Track

Allows you to add tracks to the track list.

4 Find Tracks

Allows you to find and select a specific track in the track list.


RELATED LINKS

[Opening the Track Visibility](#) on page 58

Filtering Track Types

PROCEDURE

1. Click **Filter Track Types** above the track list.
This opens the track types filter.



2. Uncheck a track type to hide it.
-

RESULT

Tracks of the filtered type are removed from the track list and the color of the **Filter Track Types** button changes to indicate that a track type is hidden.

Finding Tracks

The **Find Tracks** function allows you to find specific tracks. This is useful if you have a large project with many tracks or if you have hidden tracks using the track visibility features.

PROCEDURE

1. Click **Find Tracks** above the track list, to open a selector that lists all tracks.
 2. In the search field, enter the name of the track.
As you type, the selector updates automatically.
 3. In the selector, select the track and press **Return**.
-

RESULT

The selector closes and the track is selected in the track list.

NOTE

If the track was outside the view or hidden, it is now shown. Tracks that are hidden using **Filter Track Types** are not shown.

Ruler

The ruler shows the timeline and the display format of the project.



Initially, the **Project** window ruler uses the display format that is specified in the **Project Setup** dialog.

- To select an independent display format for the ruler, click the arrow button to the right of the ruler and select an option from the pop-up menu.
- To set the display format globally for all windows, use the primary display format pop-up on the Transport panel, or hold down **Ctrl/Cmd** and select a display format in any ruler.


RELATED LINKS

[Project Setup Dialog](#) on page 87

Ruler Display Formats

You can select a display format for the ruler.

- To select a new display format for the ruler, click the arrow button to the right of the ruler and select an option from the pop-up menu.



The selection that you make affects the time display formats in the following areas:

- Ruler
- Info line
- Tooltip position values

The following options are available:

Bars+Beats

Bars, beats, sixteenth notes, and ticks. By default, there are 120 ticks per sixteenth note. To change this, adjust the **MIDI Display Resolution** setting in the **Preferences** dialog (**MIDI** page).

Seconds

Hours, minutes, seconds, and milliseconds.

Timecode

Hours, minutes, seconds, and frames. The number of frames per second (fps) is set in the **Project Setup** dialog with the **Frame Rate** pop-up menu. To display subframes, activate **Show Timecode Subframes** in the **Preferences** dialog (**Transport** page).

Samples

Samples.

fps (User)

Hours, minutes, seconds, and frames, with a user-definable number of frames per second. To display subframes, activate **Show Timecode Subframes** in the **Preferences** dialog (**Transport** page). You can also set the number of fps.

Time Linear

Sets the ruler linear to time.

Bars+Beats Linear

Sets the ruler linear to bars and beats.


Status Line

The status line shows the most important project settings.

To activate the status line, click **Set up Window Layout** on the toolbar and activate **Status Line**.



The following information is shown on the status line:



Audio Inputs/Audio Outputs

These fields are shown if the audio device ports are not connected. Click to open the **Audio Connections** dialog and connect the ports.

Max. Record Time

Displays the remaining time for recording, depending on your project settings and the available hard disk space. Click in this field to display the remaining record time in a separate window.

Record Format

Displays the sample rate and the bit depth used for recording. Click in this field to open the **Project Setup** dialog.

Project Frame Rate

Displays the frame rate used in the project. Click in this field to open the **Project Setup** dialog.

Project Pan Law

Displays the current pan law setting. Click in this field to open the **Project Setup** dialog.

Info Line

The info line shows information about the event or part that you selected in the project zone.

Name	Start	End	Length	Offset
MIDI 01	1. 1. 1. 0	2. 2. 1. 0	1. 1. 0. 0	0. 0. 0. 0

Mute	Lock	Transpose	Global Transpose	Velocity	Root Key
-	-	0	Follow	0	-

To activate the info line, click **Set up Window Layout** on the toolbar and activate **Info Line**.



Editing on the Info Line

You can edit almost all event or part data on the info line using regular value editing.

If you select several events or parts, the info line is shown in another color and only the information about the first item in the selection is displayed. The following rules apply:

- Value changes are applied to all selected elements, relatively to the current values. For example, you have selected two audio events. The first event has a length of 1 bar, the second of 2 bars. If you change the info line value to 3, the first event is resized to 3 bars and the second event to 4 bars.

- Value changes are applied absolutely to the current values if you press **Ctrl/Cmd** while modifying the value on the info line.


In the example above, both events are resized to 3 bars.

NOTE

To change the modifier, select a new modifier in the **Info Line** category of the **Preferences** dialog (**Editing—Tool Modifiers** page).

Overview Line

The overview line allows you to zoom and navigate to other sections in the project.



To activate the overview line, click **Set up Window Layout** on the toolbar and activate **Overview Line**.



In the overview line, events and parts are displayed as boxes. A rectangle indicates the section of the project that is displayed in the event display.

- To zoom the event display in or out horizontally, resize the rectangle by dragging the edges.
- To navigate to another section of the event display, drag the rectangle to the left or right, or click in the upper part of the overview.

Transport

The **Transport** allows display the transport functions in an integrated and fixed zone of the **Project** window.



- To activate the **Transport**, click **Set up Window Layout** on the **Project** window toolbar and activate **Transport**.



- To show/hide tools, open the **Transport** context menu by right-clicking in an empty area of the **Transport** and activate the tools that you want to display. To show all tools, select **Show All**.

The following options are available:

Constrain Delay Compensation




Allows you to minimize the latency effects of the delay compensation.

Common Record Modes




Allow you to determine what happens if you click **Record** during an audio or MIDI recording.

Audio Record Modes




Allow you to select what happens when you record over existing audio events.

MIDI Record Modes



Allow you to select what happens when you record over existing MIDI parts.

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

System Performance Meter



Shows the meters for ASIO time usage and hard disk transfer load.

Locators



Allows you to go to the left or right locator position, and to set the left and right locator position numerically.

Punch Points



Allows you to activate/deactivate **Punch In** and **Punch Out**. These points determine the record start and stop positions.


The section to the right of the punch buttons allows you to set up the punch positions numerically. For this to work, **Lock Punch Points to Locators** must be deactivated. You can hide/show that section by clicking the points on the divider.

Main Transport



Shows the main transport controls.

Time Displays




Shows the time display options.

Pre-roll & Post-roll



Allows you to activate/deactivate pre-roll and post-roll, and to set the values numerically.

Tempo & Time Signature



Allows you to activate/deactivate the tempo track, and to set the tempo value and the first time signature value numerically.

External Sync State



Allows you to activate/deactivate external synchronization and to open the **Project Synchronization Setup** dialog.

Click & Count-In & Click Pattern



Allows you to activate/deactivate the metronome click, the metronome click in count-in, and the click pattern.

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Input/Output Activity



Allows you to monitor the MIDI input/output signals, the audio input/output signals, and allows you to control the output level.

RELATED LINKS

[Common Record Modes](#) on page 239

[Audio Record Modes](#) on page 244

[MIDI Record Modes](#) on page 250

[Left/Right Toolbar Divider](#) on page 43

Left Zone

The left zone of the **Project** window allows you to display the **Inspector** and the **Visibility**.

To show/hide the left zone, click **Show/Hide Left Zone** on the **Project** window toolbar.



The top of the left zone features two tabs: **Inspector** and **Visibility**.



RELATED LINKS

[Inspector](#) on page 52


[Visibility](#) on page 58

Inspector

The **Inspector** allows you to show controls and parameters for either the selected track in the track list or the event or part that is shown in the editor in the lower zone.

If the **Inspector** tab is activated at the top of the left zone, the bottom of the left zone features two tabs: **Track** and **Editor**.

- Click the **Track** tab to open the **Track Inspector** for the selected track.
- Click the **Editor** tab to open the **Editor Inspector** for the event or part that is shown in the editor in the lower zone.



RELATED LINKS

[Opening the Track Inspector](#) on page 53

[Opening the Editor Inspector](#) on page 54

[Opening the Editor in the Lower Zone](#) on page 64

Opening the Track Inspector

The **Track Inspector** shows controls and parameters for the selected track in the track list.

PROCEDURE

1. Click **Show/Hide Left Zone**  on the **Project** window toolbar to activate the **Left Zone**.
2. At the bottom of the left zone, click the **Track** tab.



RESULT

The **Track Inspector** for the selected track in the track list is opened. If more than one track is selected, the controls and parameters for the topmost selected track are shown.

Opening the Editor Inspector


The **Editor Inspector** shows controls and parameters for the event or part that is shown in the editor in the lower zone.

PREREQUISITE

The **Sample Editor**, the **Key Editor**, the **Drum Editor** or the **Score Editor** is shown in the lower zone.

PROCEDURE

1. Click **Show/Hide Left Zone**  on the **Project** window toolbar to activate the **Left Zone**.
2. At the bottom of the left zone, click the **Editor** tab.



RESULT

The **Editor Inspector** for the event or part that is shown in the editor in the lower zone is opened.

NOTE

The **Editor Inspector** only contains information if the lower zone shows an editor. Otherwise, it is empty.

RELATED LINKS

[Opening the Editor in the Lower Zone](#) on page 64

Selecting a different Inspector for the Score Editor (Cubase Pro only)


The **Score Editor Inspector** allows you to select the following tabs: **Inspector** and **Symbols**.

PREREQUISITE

The **Score Editor** is shown in the lower zone.

PROCEDURE

1. At the bottom of the left zone, click the **Editor** tab.
2. Select an option from the **Switch Score Editor Inspector Content** pop-up menu.



RESULT

The selected **Inspector** is shown.

RELATED LINKS

[Key Editor Inspector](#) on page 717

Inspector Sections

The **Track Inspector** and the **Editor Inspector** are divided into a number of sections that each contain different controls for the track, event or part.

Not all **Inspector** sections are shown by default. The available sections depend on the type of the selected track, event, or part, and on the settings in the setup dialog for the **Track Inspector/Editor Inspector**.

- To open/close sections, click their names.
Opening one section closes the other sections.
- To open a section without closing the other sections, **Ctrl/Cmd**-click the section name.


RELATED LINKS

[Inspector Settings Dialog](#) on page 56
[Audio Track Inspector](#) on page 98
[Instrument Track Inspector](#) on page 105
[MIDI Track Inspector](#) on page 112
[Sampler Track Inspector](#) on page 119
[Arranger Track Inspector](#) on page 124
[Marker Track Inspector](#) on page 141
[Signature Track Inspector](#) on page 143
[Tempo Track Inspector](#) on page 144
[Transpose Track Inspector](#) on page 145
[VCA Fader Track Inspector](#) on page 147
[Video Track Inspector](#) on page 149
[Key Editor Inspector](#) on page 717
[Drum Editor Inspector](#) on page 759
[Sample Editor Inspector](#) on page 452

Inspector Settings Dialog

The **Inspector** settings dialogs allow you to set up the sections that are available in the **Track Inspector** and the **Editor Inspector**.


- To open the **Setup** dialog for the **Track Inspector** settings, click **Setup Inspector**  in the **Track Inspector**, and from the pop-up menu select **Setup**.



- To open the **Setup** dialog for the **Editor Inspector** settings, click **Setup Inspector**  in the **Editor Inspector**, and from the pop-up menu select **Setup**.

NOTE

This is only available for the **Key Editor**, the **Drum Editor** and the **Score Editor**.



Hidden Items

Displays sections that are hidden in the **Inspector**.

Visible Items

Displays sections that are visible in the **Inspector**.

Pin

If you activate **Pin** by clicking the column for a section the open/close status of the selected **Inspector** section is pinned.

Add

Allows you to move an item selected in the hidden sections list to the list of visible sections.

Remove

Allows you to move an item selected in the visible sections list to the list of hidden sections.

Move Up/Move Down

Allows you to change the order of an item in the list of visible sections.

Presets

Allows you to save **Inspector** section settings as presets.

Reset All


Allows you to restore the default **Inspector** section settings.

Visibility

The **Visibility Inspector** allows you to show or hide individual tracks from the track list and to determine the position of certain **MixConsole** channels in the lower zone.

If the **Visibility** tab is activated at the top of the left zone, the bottom of the left zone features two tabs: **Track** and **Zones**.

- Activate the **Track** tab to open the **Track Visibility** that allows you to show or hide individual tracks from the track list.
- Activate the **Zones** tab to open the **Zones Visibility** that allows you to determine and lock the position of certain **MixConsole** channels in the lower zone.



RELATED LINKS


[Opening MixConsole in the Lower Zone](#) on page 63

Opening the Track Visibility

The **Track Visibility** allows you to show or hide individual tracks from the track list.

PROCEDURE

1. Click **Show/Hide Left Zone** on the **Project** window toolbar to activate the **Left Zone**.
2. At the top of the left zone, click the **Visibility** tab.
3. At the bottom of the left zone, click the **Track** tab.



RESULT


The **Track Visibility** for your project is shown.

RELATED LINKS

[Showing/Hiding Individual Tracks](#) on page 59

Showing/Hiding Individual Tracks

The **Track Visibility** shows a list of all tracks of your project. This list allows you to show and hide individual tracks.



- To show/hide a track in the track list, check/uncheck it by clicking to the left of the track name.
- To activate/deactivate several tracks at the same time, select them and press **Return**.
- To show a hidden track exclusively, check it by **Shift**-clicking to the left of the track name.
- To expand or collapse a folder, click the triangle to the left of a folder track.

NOTE

- The channels of the **MixConsole** in the lower zone are updated accordingly. This means that if you hide a track with the **Track Visibility**, the channel corresponding to that track is also hidden in the **MixConsole** in the lower zone.
- If you want to synchronize the track and the channel visibility in a separate **MixConsole** window, you must use the **Sync Track/Channel Visibility** function.

RELATED LINKS


[Synchronizing Track and Channel Visibility](#) on page 60

Synchronizing Track and Channel Visibility

You can synchronize the track visibility in the **Project** window with the channel visibility in a separate **MixConsole** window.

PROCEDURE

1. At the top of the left zone, open the **Visibility** tab.
2. At the bottom of the left zone, open the **Track** tab.
3. Click the equals sign to open the **Sync Visibility of Project and MixConsole: On/Off** menu.



4. Select **Sync Project and MixConsole** to synchronize the track visibility with the channel visibility.
-

RESULT

The track and channel visibility are synchronized.

NOTE

- You can only synchronize the track visibility in the **Project** window with the channel visibility of one **MixConsole**. If you enable **Sync Visibility of Project and MixConsole: On/Off** for a second **MixConsole**, the first link is lost.
 - If you divide the track list, the top part of the list is not affected. Likewise, channels in the left or right zones of the **MixConsole** are not synchronized.
-

RELATED LINKS


[Synchronizing Channel and Track Visibility](#) on page 323

Opening the Zones Visibility

The **Zones Visibility** allows to determine and lock the position of certain **MixConsole** channels in the lower zone.

PROCEDURE

1. At the top of the left zone, click the **Visibility** tab.
2. At the bottom of the left zone, click the **Zones** tab.



RESULT

The **MixConsole** is opened in the lower zone, and the **Zones Visibility** for the **MixConsole** in the lower zone is shown in the left zone.


RELATED LINKS

[Opening MixConsole in the Lower Zone](#) on page 63


Lower Zone

The lower zone of the **Project** window allows you to display specific windows and editors in an integrated and fixed zone of the **Project** window. This is useful if you work on single screen systems and notebooks, for example.


To show/hide the lower zone, click **Show/Hide Lower Zone** on the **Project** window toolbar.



The lower zone features the following tabs: **Chord Pads**, **MixConsole**, **Sampler Control**, and **Editor**.



To close the lower zone, click **Close Lower Zone** to the left of the tabs.



RELATED LINKS


- [Opening Chord Pads on page 62](#)
- [Opening MixConsole in the Lower Zone on page 63](#)
- [Opening Sampler Control on page 64](#)
- [Opening the Editor in the Lower Zone on page 64](#)

Setting up the Lower Zone

In the lower zone, the tabs **MixConsole**, **Editor**, **Sampler Control**, and **Chord Pads** are shown. You can change the order of these tabs, and you can hide tabs that you do not need.

PROCEDURE

1. Click **Set up Lower Zone** in the bottom right of the lower zone.



2. Do one of the following:
 - Activate/Deactivate the options in the pop-up menu to show/hide tabs from the lower zone.
 - Select **Setup** to open a dialog where you can activate/deactivate the tabs and change their position.

NOTE

In the **Presets** section of this dialog you can also save a preset of your tab configuration.

RESULT

The tabs in the lower zone are shown according to your configuration.

Opening Chord Pads


Chord Pads allow you to play with chords, and to change their voicings and tensions.

PREREQUISITE

The **Chord Pads** tab is activated in the **Lower Zone Setup**.

PROCEDURE

1. Click **Show/Hide Lower Zone**  on the **Project** window toolbar to activate the lower zone.
2. At the bottom of the lower zone, click the **Chord Pads** tab.



RESULT

The **Chord Pads** are opened.

RELATED LINKS

[Chord Pads](#) on page 837


[Setting up the Lower Zone](#) on page 62

Opening MixConsole in the Lower Zone

The **MixConsole** in the lower zone allows you to perform all basic mixing procedures from within the lower zone of the **Project** window, and at the same time to see the context of your tracks and events.

PROCEDURE

1. Click **Show/Hide Lower Zone**  on the **Project** window toolbar to activate the lower zone.
2. At the bottom of the lower zone, click the **MixConsole** tab.



RESULT

The **MixConsole** is opened in the lower zone.

RELATED LINKS

[MixConsole in Lower Zone](#) on page 317

Opening Sampler Control

Sampler Control allows you display and edit the waveform of an audio sample on a sampler track.

PROCEDURE

1. Click **Show/Hide Lower Zone**  on the **Project** window toolbar to activate the lower zone.
2. At the bottom of the lower zone, click the **Sampler Control** tab.



RESULT

Sampler Control is opened.

RELATED LINKS

[Controlling Sample Playback with Sampler Tracks](#) on page 514

Opening the Editor in the Lower Zone

The **Editor** in the lower zone allows you to perform event editing procedures from within the lower zone of the **Project** window, and at the same time to see the context of your tracks and events.

NOTE

By default, double-clicking an audio event/part or a MIDI part in the event display or selecting it and pressing **Return** opens the corresponding editor in the lower zone of the **Project** window. Using a menu command opens a separate editor window. You can change this in the **Preferences** dialog (**Editors** page).

PROCEDURE

1. Click **Show/Hide Lower Zone**  on the **Project** window toolbar to activate the lower zone.
2. At the bottom of the lower zone, click the **Editor** tab.
3. In the event display, do one of the following:
 - Select a MIDI part.
 - Select an audio event.
 - Select an audio part.



RESULT

Depending on your event or part selection the lower zone shows either the **Audio Part Editor**, the **Sample Editor** or one of the MIDI Editors.

NOTE

To change the default MIDI editor, select **MIDI > Set up Editor Preferences**, and select an option from the **Default MIDI Editor** pop-up menu.

NOTE

If you open the editor and no event or part is selected, the editor in the lower zone is empty.

RELATED LINKS

[Selecting a different MIDI Editor](#) on page 65

Selecting a different MIDI Editor

You can display the MIDI part that is opened in the editor in the lower zone in a different MIDI editor. To do this, you do not necessarily need to change the default MIDI editor.

PROCEDURE

1. On the **Editor** tab in the editor in the lower zone, click **Select MIDI Editor**.
2. Select an editor from the pop-up menu.



RESULT

The MIDI part is displayed in the selected editor.

NOTE


This selection is temporary. Next time you open the MIDI part, the default MIDI editor is used.

Link Project and Lower Zone Editor Cursors

You can link cursors and zoom factors of the project zone and the **Key Editor**, **Drum Editor**, and the **Audio Part Editor** in the lower zone.

NOTE

The ruler display format setting is not affected by this function. You can still select different ruler display formats for the project zone and the editor in the lower zone.



If you activate **Link Project and Lower Zone Editor Cursors**, the cursors and zoom factors are linked in the event displays of the project zone and the lower zone. This is useful if you edit in both zones and you want to keep the same position in view.

NOTE

In the **Key Commands** dialog in the **Edit** category, you can assign a key command for this.

RELATED LINKS

[Ruler](#) on page 46


[Ruler Display Formats](#) on page 47

[Zooming in the Project Window](#) on page 74


Right Zone

The right zone of the **Project** window allows you to display the **VSTi** rack, the **Media** rack, the **Control Room** rack (Cubase Pro only), and the **Meter** rack (Cubase Pro only).

To show/hide the right zone, click **Show/Hide Right Zone** on the **Project** window toolbar.



The top of the right zone features the following tabs: **VSTi**, **Media**, **CR** (Cubase Pro only), and **Meter** (Cubase Pro only).



NOTE

You can show/hide specific tabs from the right zone by right-clicking a tab header and activating/deactivating the options in the context menu.

RELATED LINKS

[VSTi Rack in the Right Zone](#) on page 69

[Media Rack in the Right Zone](#) on page 71

Opening the VSTi Rack in the Right Zone

You can show the **VSTi** rack in the right zone of the **Project** window. This allows you to add and edit VST instruments, and at the same time to see the context of your tracks and events.

PROCEDURE

1. Click **Show/Hide Right Zone**  on the **Project** window toolbar to activate the **Right Zone**.
2. At the top of the right zone, click the **VSTi** tab.



RESULT

The **VSTi** rack is opened in the right zone of the **Project** window.

RELATED LINKS

[VSTi Rack in the Right Zone](#) on page 69

[VST Instruments](#) on page 628

VSTi Rack in the Right Zone

The **VSTi** rack in the right zone of the **Project** window allow you to add and edit VST instruments in the context of the **Project** window.

The following sections are available:



- **Track**
Shows the associated VST instrument for an instrument track.
- **Rack**
Shows a VST instrument.

The following controls are available:



- 1 **Add Track Instrument**
Opens the **Add Instrument Track** dialog that allows you to select an instrument and add an instrument track that is associated to this instrument.
- 2 **Find Instruments**
Opens a selector that allows you to find a loaded instrument.
- 3 **Set Remote-Control Focus for VST Quick Controls to Previous/Next Instrument**
Allows you to set the remote-control focus to the next/previous instrument.
- 4 **Show/Hide all VST Quick Controls**
Shows/Hides the default quick controls for all loaded instruments.
- 5 **Settings**
Opens the **Settings** menu where you can activate/deactivate the following modes:
 - **Show VST Quick Controls for One Slot Only** shows the VST Quick Controls exclusively for the selected instrument.
 - **MIDI Channel follows track selection** ensures that the **Channel** selector follows the MIDI track selection in the **Project** window. Use this mode if you work with multitimbral instruments.
 - **Remote-Control Focus for VST Quick Controls follows track selection** ensures that the VST Quick Control remote-control focus follows the track selection.

RELATED LINKS


[VST Instruments Window](#) on page 630

Opening the Media Rack in the Right Zone

You can show the **Media** rack in the right zone of the **Project** window. This allows you to see the context of your tracks and events when you drag audio events, MIDI parts, presets, or instruments into the **Project** window.

PROCEDURE

1. Click **Show/Hide Right Zone**  on the **Project** window toolbar to activate the **Right Zone**.
2. At the top of the right zone, click the **Media** tab.



RESULT


The **Media** rack is opened in the right zone of the **Project** window.

RELATED LINKS

- [Media Rack in the Right Zone](#) on page 71
- [MediaBay](#) on page 546

Media Rack in the Right Zone

The **Media** rack in the right zone of the **Project** window allows you to drag audio events, MIDI parts, or instrument presets into the event display. It lists Steinberg factory content and any installed Steinberg content sets.



The **Media** rack **Home** page  shows the following tiles:

Instruments

Shows all included VST instruments.

Loops & Samples

Shows audio loops, MIDI loops, or instrument sounds ordered by content set.

Presets

Shows track presets, strip presets, pattern banks, FX chain presets, and VST FX presets.

User Presets

Shows track presets, strip presets, pattern banks, FX chain presets, VST FX presets, and instrument presets that are listed in the **User Content** folder.

Favorites

Shows your favorite folders and allows you to add new favorites. The folder content is automatically added to the **MediaBay** database.

File Browser

Shows your file system and the pre-defined folders **Favorites**, **This Computer**, **VST Sound**, **Factory Content**, and **User Content** where you can search for media files and access them immediately.

RELATED LINKS

[Favorites Section](#) on page 556

[Media Rack in Right Zone](#) on page 546

[MediaBay](#) on page 546

Opening the Control Room in the Right Zone (Cubase Pro only)

You can show the **Control Room** in the right zone of the **Project** window.

PROCEDURE

1. Click **Show/Hide Right Zone**  on the **Project** window toolbar to activate the **Right Zone**.
2. At the top of the right zone, click the **CR** tab.



RESULT

The **Control Room** is opened in the right zone of the **Project** window. It has exactly the same features as the **Control Room** that you open from the **Studio** menu as a separate window.

RELATED LINKS


[Control Room \(Cubase Pro only\)](#) on page 372

Opening the Meter in the Right Zone (Cubase Pro only)

You can show the **Meter** in the right zone of the **Project** window.

PROCEDURE

1. Click **Show/Hide Right Zone**  on the **Project** window toolbar to activate the **Right Zone**.
2. At the top of the right zone, click the **Meter** tab.



RESULT

The **Meter** is opened in the right zone of the **Project** window. It has exactly the same features as the **Meter** that you open in the right zone of the **MixConsole**.

RELATED LINKS

[Metering and Loudness \(Cubase Pro only\)](#) on page 385

Keyboard Focus in the Project Window

The different zones in the **Project** window can be controlled by using key commands. To make sure that a key command has effect on a specific zone, you must make sure that this zone has the keyboard focus.

The following **Project** window zones can have the keyboard focus:

- Project zone
- Left zone
- Lower zone
- Right zone

If a zone has the keyboard focus, the border that surrounds it is highlighted in a specific color.

NOTE

You can change the focus color in the **Preferences** dialog (**User Interface—Custom Colors** page).

RELATED LINKS

[Project Zone](#) on page 39

[Left Zone](#) on page 51

[Lower Zone](#) on page 61
[Right Zone](#) on page 67
[Project Window](#) on page 38

Activating Keyboard Focus for a Zone

You can activate the keyboard focus for a zone by clicking with the mouse and by using key commands.

PROCEDURE

- Do one of the following:
 - To activate any zone, click in it.
 - To activate the next zone, press **Tab**. This allows you to cycle forward through the zones.
 - To activate the previous zone, press **Shift-Tab**.

NOTE

The editor in the lower zone automatically gets the keyboard focus if you double-click an event or part in the event display, if you select an event or part and press **Return**, or if you use key commands to open the zone.

RESULT

The keyboard focus is activated for this zone and the border of the zone is highlighted.

NOTE

The project zone and the lower zone have separate toolbars and info lines. If you use the toolbar or the info line for one of these zones, the corresponding zone automatically gets the focus.

RELATED LINKS

[Customizing the User Interface Colors](#) on page 996

Zooming in the Project Window

You can zoom in the **Project** window according to the standard zoom techniques.

NOTE

If screen redraws are slow on your system, consider activating **Quick Zoom** in the **Preferences** dialog (**Editing** page).

Zooming Horizontally

- Select the **Zoom** tool and click in the event display to zoom in. To zoom out, hold down **Alt** and click.
- Use the horizontal zoom sliders to zoom in and out.
- Click the lower half of the ruler and drag down to zoom in horizontally. Click the lower half of the ruler and drag up to zoom out horizontally.
- Click **H** to zoom in horizontally. Click **G** to zoom out horizontally.

NOTE

If the **Grid Type** in the **Project** window toolbar is set to **Adapt to Zoom**, the horizontal zoom level affects the grid and snap resolution in the event display.

Zooming Vertically

- Select the **Zoom** tool, click in the event display, and drag a selection rectangle to zoom in vertically and horizontally.

NOTE

For this to work, you must deactivate the **Zoom Tool Standard Mode: Horizontal Zooming Only** option in the **Preferences** dialog (**Editing—Tools** page).

- Use the vertical zoom sliders to zoom in and out. If you have made any individual track height adjustments, the relative height differences are maintained.
- Click **Shift-H** to zoom in vertically. Click **Shift-G** to zoom out vertically.

RELATED LINKS

[Zoom Submenu](#) on page 75

[Zoom Presets](#) on page 76

[Zooming In On Cycle Markers](#) on page 77

[Zoom History](#) on page 78

[Link Project and Lower Zone Editor Cursors](#) on page 66


[Grid Types](#) on page 80

Zooming in on Audio Contents

You can zoom in vertically on the contents of audio parts and events. This is useful when viewing quiet audio passages.

PROCEDURE

- Click the waveform zoom slider in the top right corner of the event display and drag up.



RESULT

The contents of audio parts and events in your project are zoomed in vertically.

AFTER COMPLETING THIS TASK

To get an approximate reading on the level of the audio events by viewing the waveforms, zoom out by dragging the slider is all the way down again. Otherwise, zoomed waveforms may be mistaken for clipped audio.

Zoom Submenu

The **Zoom** submenu contains options for zooming in the **Project** window.

- To open the **Zoom** submenu, select **Edit > Zoom**.

The following options are available:

Zoom In/Out

Zooms in/out one step, centering on the project cursor.

Zoom Full

Zooms out so that the whole project is visible. The whole project means the timeline from the project start to the length set in the **Project Setup** dialog.

Zoom to Selection

Zooms in horizontally and vertically so that the current selection fills the screen.

Zoom to Selection (Horiz.)

Zooms in horizontally so that the current selection fills the screen.

Zoom to Event

This option is available in the **Sample Editor** and in some MIDI editors.

Zoom In/Out Vertically

Zooms in/out one step vertically.

Zoom In/Out Tracks

Zooms the selected tracks in/out one step vertically.

Zoom Selected Tracks

This zooms in vertically on the selected tracks and minimizes the height of all other tracks.

Undo/Redo Zoom

These options allow you to undo/redo the last zoom operation.


RELATED LINKS

[Zoom Submenu](#) on page 456


Zoom Presets

You can create zoom presets that allow you to set up different zoom settings. For example, one where the whole project is displayed in the **Project** window and another with a high zoom factor for detailed editing. The **Zoom Presets** pop-up menu allows you to select, create, and organize zoom presets.

- To open the **Zoom Presets** pop-up menu, click the button to the left of the horizontal zoom control.



The upper part of the menu lists the zoom presets.



- To save the current zoom setting as a preset, open the **Zoom Presets** pop-up menu and select **Add**. In the **Type In Preset Name** dialog that opens, type in a name for the preset and click **OK**.
- To select and apply a preset, select it from the **Zoom Presets** pop-up menu.
- To zoom out so that the whole project is visible, open the **Zoom Presets** pop-up menu and select **Zoom Full**.
This displays the project from the project start to the length that is set in the **Project Setup** dialog.
- To delete a preset, open the **Zoom Presets** pop-up menu and select **Organize**. In the dialog that opens, select the preset in the list and click **Delete**.
- To rename a preset, open the **Zoom Presets** pop-up menu and select **Organize**. In the dialog that opens, select a preset in the list and click **Rename**. In the dialog that opens, type in a new name for the preset. Click **OK** to close the dialogs.


IMPORTANT

Zoom presets are global for all projects. They are available in all projects that you open or create.

Zooming In On Cycle Markers

You can zoom in on the area between cycle markers in the project.

- To zoom in on a cycle marker, click the button to the left of the horizontal zoom control to open the **Zoom Presets** pop-up menu and select a cycle marker.



The middle part of the **Zoom Presets** pop-up menu lists any cycle markers that you have added to the project.

NOTE

Only the cycle markers that you create in the current project are available on the menu.

If you select a cycle marker, the event display is zoomed in to encompass the marker area.

You cannot edit the cycle markers in the **Zoom Presets** pop-up menu.

RELATED LINKS

[Markers Window](#) on page 308

Zoom History

You can undo and redo zoom operations. This way you can zoom in several steps and then easily go back to the zoom stage at which you started.

You can undo and redo zoom operations in the following ways:

- To undo zoom, select **Edit > Zoom > Undo Zoom** or double-click with the zoom tool.
- To redo zoom, select **Edit > Zoom > Redo Zoom** or press **Alt** and double-click with the zoom tool.

Snap Function

The **Snap** function helps you to find exact positions when editing in the **Project** window. It does this by restricting horizontal movement and positioning to certain positions. Operations affected by **Snap** include moving, copying, drawing, sizing, splitting, range selection, etc.

- To activate/deactivate **Snap**, activate/deactivate the **Snap** icon on the toolbar.



Setting the Snap Point

You can set the snap point at any position of the audio event.

PROCEDURE

1. Select an event.
2. Place the project cursor at a position within the selected audio event.
3. Select **Audio > Snap Point To Cursor**.

RESULT

The snap point is set at the cursor position. The snap point for an event is displayed as a vertical line in the **Project** window.



NOTE

You can also set the snap point in the **Sample Editor**.

RELATED LINKS

[Adjusting the Snap Point](#) on page 464

Snap to Zero Crossing


When splitting and sizing audio events, sudden amplitude changes can cause pops and clicks. To avoid this, you can activate **Snap to Zero Crossing** to snap to points where the amplitude is zero.

- To activate **Snap to Zero Crossing**, activate **Snap to Zero Crossing**  on the toolbar.

Snap Types

You can select between different snap types to determine the snap point.

- To select a snap type, open the **Snap Type** pop-up menu.




The following snap types are available:


Grid

If this option is activated, the snap points are set with the **Grid Type** pop-up menu. The options depend on the display format that is selected for the ruler.

If you select **Seconds** as ruler format, time-based grid options are available.



If you select **Bars+Beats** as a ruler format, musical grid options are available.



Grid Relative

If this option is activated, events and parts are not magnetic to the grid. Rather, the grid determines the step size for moving the events. This means that a moved event keeps its original position relative to the grid.

For example, if an event starts at the position 3.04.01, snap is set to **Grid Relative** and the **Grid Type** pop-up menu is set to **Bar**, you can move the event in steps of one bar to the positions 4.04.01, 5.04.01, and so on.

NOTE

This only applies when dragging existing events or parts. When you create new events or parts this snap type works like **Grid**.


Events

If this option is activated, the start and end positions of other events and parts become magnetic. This means that if you drag an event to a position near the start or end of another event, it is automatically aligned with the start or end of the other event.

For audio events, the position of the snap point is also magnetic. This includes marker events on the marker track.

Shuffle

Shuffle is useful when you want to change the order of adjacent events. If you have two adjacent events and drag the first one to the right, past the second event, the two events will change places.



The same principle works when changing the order of more than two events.

Magnetic Cursor

This grid type lets the project cursor become magnetic. Dragging an event near the cursor causes the event to be aligned with the cursor position.

Grid + Cursor

This is a combination of **Grid** and **Magnetic Cursor**.

Events + Cursor

This is a combination of **Events** and **Magnetic Cursor**.

Events + Grid + Cursor

This is a combination of **Events**, **Grid**, and **Magnetic Cursor**.


Grid Types

Allows you to specify a grid type that determines the grid and snap resolution in the event display.

NOTE

This setting only has an effect if **Snap Type** is set to one of the grid options.

- To select a grid type, open the **Grid Type** pop-up menu.



If you select **Bars+Beats** as a ruler format, the following grid types are available:

Bar

Sets the grid and snap resolution to bars.

Beat

Sets the grid and snap resolution to beats.

Use Quantize

Sets the grid and snap resolution to the value that is activated in the **Quantize Preset** pop-up menu.

Adapt to Zoom

Sets the grid and snap resolution to the horizontal zoom level. The more you zoom in on the event display, the finer the resolution. High zoom levels allow you to snap to 64th notes, low zoom levels allow you to snap to bars.

NOTE

Adapt to Zoom is only available if **Bars+Beats** is set as a ruler display format.

If you activate **Time Linear** in the ruler context menu, the distances between the grid lines are still constant but based on musical values such as bars and beats.

If you select **Seconds** as ruler format, the following grid types are available:

1 ms

Sets the grid and snap resolution to 1 ms.

10 ms

Sets the grid and snap resolution to 10 ms.

100 ms

Sets the grid and snap resolution to 100 ms.

1000 ms

Sets the grid and snap resolution to 1000 ms.

RELATED LINKS

[Snap Types](#) on page 79

[Zooming in the Project Window](#) on page 74

[Ruler Display Formats](#) on page 47

Cross-Hair Cursor

The cross-hair cursor is displayed when working in the **Project** window and in the editors, facilitating navigation and editing, especially when arranging large projects.

- You can set up the cross-hair cursor in the **Preferences** dialog (**Editing—Tools** page). You can set up the colors for the line and the mask of the cross-hair cursor, and define its width.

The cross-hair cursor works as follows:

- When the **Object Selection** tool or one of its subtools is selected, the cross-hair cursor appears when you start moving/copying a part/event, or when using the event trim handles.



Cross-hair cursor when moving an event.

- When the **Object Selection** tool, the **Cut** tool, or any other tool that makes use of this function is selected, the cross-hair cursor appears as soon as you move the mouse over the event display.
- The cross-hair cursor is only available for tools where such a function is of any use. The **Mute** tool, for example, does not use a cross-hair cursor, as you have to click directly on an event to mute it.


NOTE

If the **Key Editor**, **Drum Editor** or the **Audio Part Editor** is open in the lower zone of the **Project** window and **Link Project and Lower Zone Cursors** is activated, the cross-hair cursor is shown in the editor in the lower zone and in the **Project** window.

Edit History Dialog

The **Edit History** dialog contains a list of all your edits. This allows you to undo all actions in the **Project** window as well as in the editors.

- To open the **Edit History** dialog, select **Edit > History**.



#	Action	Time	State	Details
1	Move Selected Tracks	9:23:10 AM	Executed	Track: Lead
2	Add Track	9:23:35 AM	Executed	Track: MIDI 01
3	Add Track	9:23:51 AM	Executed	Track: HALion Sonic SE 01
4	Move Selected Tracks	9:23:59 AM	Executed	Track: MIDI 01, Track: HALi
5	Set Track Name	9:24:09 AM	Executed	Track: Lead
6	Create Event	9:24:09 AM	Executed	Track: MIDI 01 - MIDI 01
7	Change Track Color	9:24:47 AM	Executed	Track: MIDI 01
8	Change Track Color	9:24:53 AM	Executed	Track: HALion Sonic SE 01
9	Move Selected Tracks	9:56:18 AM	Executed	Track: Claps1
10	Lock Events	10:17:57 AM	Executed	Track: Lead - Lead
11	Unlock Events	10:18:02 AM	Executed	Track: Lead - Lead
12	Split	10:18:43 AM	Undone	Track: Claps1 - Claps1 - Cl
13	Split	10:18:48 AM	Undone	Claps1 - Claps1 - Claps1
14	Move	10:18:58 AM	Undone	Claps1 - Claps1

The **Action** column displays the name of the action while the **Time** column tells you when this action was performed. In the **Details** column further details are shown. Here you can enter new text by double-clicking in the column.

- To undo your actions, move the horizontal, colored line upwards to the desired position. You can only undo your actions in reverse order, for example, the last performed action is the first action to be undone.
- To redo an action that was undone previously, move the line down the list again.

NOTE

- You can also undo applied plug-in effects (Cubase Pro only) or audio processes. However, we recommend to modify or delete these using the **Direct Offline Processing** window.
- All offline processing that you have applied permanently to the audio using the **Make Direct Offline Processing Permanent** function cannot be undone. Therefore, it is not shown in the **Edit History** dialog.

RELATED LINKS

[Direct Offline Processing](#) on page 416

[Applying Offline Processing Permanently](#) on page 424

Setting the Number of Maximum Undo Steps

You can limit the number of maximum undo steps. This is useful if you run out of memory, for example.

PROCEDURE

1. In the **Preferences** dialog, select **General**.
2. Set the number in the **Maximum Undo Steps** field.

Project Handling

In Cubase, projects are the central documents. You must create and set up a project to work with the program.

Creating New Projects

You can create empty projects or projects that are based on a template.

PROCEDURE

1. Select **File > New Project**.
Depending on your settings, either the **Hub** or the **Project Assistant** dialog opens.
2. In the location options section, select where to store the new project.
 - To use the default location, select **Use default location**.
 - To choose another location, select **Prompt for project location**.
3. Do one of the following:
 - To create an empty new project, click **Create Empty**.
 - To create a new project from a template, select a template and click **Create**.

RESULT

A new, untitled project is created. If you selected a template, the new project is based on this template and includes the corresponding tracks, events, and settings.

NOTE

If you create an empty project, your default presets for the input and output bus configurations are applied. If you have not defined default presets, the last used configurations are applied.

RELATED LINKS

[Presets for Input and Output Busses](#) on page 29

Hub

When you start Cubase or create new projects using the **File** menu, the **Hub** opens. The **Hub** keeps you up to date with the latest information and assists you with organizing your projects. It consists of the **News and Tutorials** section and the **Projects** section.



News and Tutorials section

The **News and Tutorials** section displays Steinberg news, tutorial videos as well as links to the user forum, downloads, and the Help Center.

NOTE

Ensure that you have an active Internet connection to access this material.

Projects section

The **Projects** section lets you create new projects, which can either be empty or based on a template. It lets you specify where to save the projects. It also allows you to access recently opened projects or projects that are stored in other locations. This section offers the same functionality as the **Project Assistant** dialog.

Category bar

In this section, the available factory templates are sorted into the predefined categories **Recording**, **Scoring**, **Production**, and **Mastering**.

The **Recent** category contains a list of the recently opened projects.

The **More** category contains the default project template and all templates that are not assigned to any of the other categories.

Template list

When you click on one of the category items, the list below the category bar shows the available templates for this category. Any new templates that you create are added at the top of the corresponding list.

Location options

This section allows you to specify where the project is stored.

Open other

This button allows you to open any project file on your system. This is identical to using the **Open** command on the **File** menu.

RELATED LINKS

[Project Assistant](#) on page 85

Deactivating the Hub

To start Cubase or to create new projects without the **Hub**, you can deactivate it.

PROCEDURE

1. In the **Preferences** dialog, select **General**.
2. Deactivate **Use Hub**.

RESULT

Cubase starts without opening a project and opens the **Project Assistant** dialog when you create a new project using the **File** menu. However, you can still open the **Hub** through the **Hub** menu.

Project Assistant

When you deactivate the **Hub** and create new projects, the **Project Assistant** dialog opens. This dialog offers the same functions as the **Projects** section in the **Hub**.

Category bar

In this section, the available factory templates are sorted into the predefined categories **Recording**, **Production**, **Scoring**, and **Mastering**.

The **Recent** category contains a list of the recently opened projects.

The **More** category contains the default project template and all templates that are not assigned to any of the other categories.

Template list

When you click on one of the category items, the list below the category bar shows the available factory templates for this category. Any new templates that you create are added at the top of the corresponding list.

Location options

This section allows you to specify where the project is stored.

Open other

This button allows you to open any project file on your system. This is identical to using the **Open** command from the **File** menu.

About Project Files

A project file (extension *.cpr) is the central document in Cubase. A project file contains references to media data that can be saved in the project folder.

NOTE

We recommend to save files only in the project folder, even though you can save them in any other location to which you have access.

The project folder contains the project file and the following folders that Cubase automatically creates when necessary:

- Audio
- Edits
- Images

- Track Pictures

About Template Files

Templates can be a good starting point for new projects. Templates are projects where you can save all settings that you regularly use, such as bus configurations, sample rates, record formats, basic track layouts, VSTi setups, drum map setups, etc.

The following template types are available from within the **Hub**:

- Factory templates for specific scenarios. These are listed in the **Recording, Scoring, Production, or Mastering** categories.
- The default template. This is listed in the **More** category.
- Any new user templates that you create and save. These are listed in the **More** category.

Template projects are not saved in project folders and therefore contain no subfolders and no media files.

- To open the location of a specific template, right-click a template in the template list and select **Show in Explorer** (Windows only) or **Reveal in Finder** (macOS only).

Saving a Project Template File


You can save the current project as a template. When you create a new project, you can select this template as a starting point for your new project.

PREREQUISITE

Remove all clips from the Pool before you save the project as a template. This ensures that references to media data from the original project folder are deleted.

PROCEDURE

1. Set up a project.
2. Select **File > Save as Template**.
3. In the **New Preset** section of the **Save as Template** dialog, enter a name for the new project template.



4. In the **Attribute Inspector** section, double-click the **Value** field of the **Content Summary** attribute to enter a description for the template.

5. Click the **Value** field of the **Template Category** attribute and select a template category from the pop-up menu.
If you do not select a category, the new template will be listed in the **Hub** in the **More** category.
 6. Click **OK** to save the template.
-

Renaming Templates

PROCEDURE

1. In the **Hub** or the **Project Assistant**, right-click a template and select **Rename**.
 2. In the **Rename** dialog, enter a new name and click **OK**.
-

Project Setup Dialog

You can perform general settings for your project in the **Project Setup** dialog.

- To open the **Project Setup** dialog, select **Project > Project Setup**.
- To open the **Project Setup** dialog automatically when you create a new project, activate the **Run Setup on Create New Project** option in the **Preferences** dialog (**General** page).

The screenshot shows the Project Setup dialog with the following settings:

- Author: [Redacted]
- Company: [Redacted]
- Start: 00:00:00:00
- Length: 00:10:00:00
- Frame Rate: 30 fps (with Get From Video button)
- Display Format: Bars+Beats
- Display Offset: 00:00:00:00
- Bar Offset: 0
- Sample Rate: 48.000 kHz
- Bit Depth: 32 bit float
- Record File Type: Wave File
- Stereo Pan Law: Equal Power
- Volume Max: +6 dB
- HMT Type: Classic (pure 3/5 equa)
- HMT Depth: 100

IMPORTANT

While most **Project Setup** settings can be changed at any time, you must set the sample rate directly after creating a new project. If you change the sample rate at a later stage, you must convert all audio files in the project to the new sample rate to make them play back properly.

The following options are available:

Author

Allows you to specify a project author that is written into the file, when you export audio files and activate the **Insert iXML chunk** option. You can specify a default

author in the **Default Author Name** field in the **Preferences** dialog (**General—Personalization** page).

Company

Allows you to specify a company name that is written into the file, when you export audio files and activate the **Insert iXML chunk** option. You can specify a default company in the **Default Company Name** field in the **Preferences** dialog (**General—Personalization** page).

Start

Allows you to specify the start time of the project in timecode format. This also determines the sync start position when synchronizing to external devices.

Length

Allows you to specify the length of the project.

Frame Rate

Allows you to specify the timecode standard and frame rate for the project. When synchronizing to an external device, this setting must correspond to the frame rate of any incoming timecode.

Get From Video

Allows you to set the project frame rate to the frame rate of an imported video file.

Display Format

Allows you to specify the global display format that is used for all rulers and position displays in the program, except the ruler tracks. However, you can make independent display format selections for the individual rulers and displays.

Display Offset

Allows you to specify an offset for the time positions that are displayed in the rulers and position displays to compensate for the Start position setting.

Bar Offset

This setting is only used, when you select the Bars+Beats display format. Allows you to specify an offset for the time positions that are displayed in the rulers and position displays to compensate for the Start position setting.

Sample Rate

Allows you to specify the sample rate at which records and plays back audio.

- If your audio hardware generates the sample rate internally and you select a non-supported sample rate, this is indicated by a different color. In this case, you must set a different sample rate to make your audio files play back properly.
- If you select a sample rate that your audio hardware supports, but that differs from its current sample rate setting, it is automatically changed to the project sample rate.
- If your audio hardware is externally clocked and receives external clock signals, sample rate mismatches are accepted.

Bit Depth

Allows you to specify the bit depth of the audio files that you record in Cubase. Select the record format according to the bit depth that is delivered by your audio hardware. The available options are 16 bit, 24 bit, 32 bit, 32 bit float, and 64 bit float.

NOTE

- If your audio interface supports a bit depth of 32 bit, and you want to maintain this precision in your recordings, you must select a **Processing Precision** of 64 bit float in the **Studio Setup** dialog.
- When you record with effects, consider setting the bit depth to 32 bit float or 64 bit float. This prevents clipping (digital distortion) in the recorded files and keeps the audio quality very high. Effect processing and level or EQ changes in the input channel are done in 32-bit float or 64-bit float format, depending on the **Processing Precision** setting in the **Studio Setup** dialog. If you record at 16 bit or 24 bit, the audio will be converted to this lower bit depth when it is written to a file. As a result, the signal may degrade. This is independent of the actual bit depth of your audio hardware. Even if the signal from the audio hardware has a bit depth of 16 bit, the signal will be 32 bit float or 64 bit float after the effects are added to the input channel.
- The higher the bit depth value, the larger the files and the more strain is put on the disk system. If this is an issue, you can lower the record format setting.

Record File Type

Allows you to specify the file type of the audio files that you record in Cubase. The following file types are available:

- **Wave File**
This is the most common file format on the PC platform. Wave files have the extension **.wav**.
- **Wave 64 File**
This is a proprietary format developed by Sonic Foundry Inc. Wave 64 files offer the same quality as Wave files, but they can be considerably larger than standard Wave files. They are especially suited for long recordings with file sizes over 2 GB. The files have the extension **.w64**.
- **Broadcast Wave Files**
This format is, in terms of audio content, identical with regular Wave files. Broadcast Wave files can contain embedded text strings. The files have the extension **.wav**.
- **AIFF Files**
This is an audio file format standard defined by Apple Inc. AIFF files are used on most computer platforms. The files can contain embedded text strings. AIFF files have the extension **.aif**.
- **FLAC File**
This is an open source format that reduces the size of audio files by 50 to 60 % compared to regular Wave files. The files have the extension **.flac**.

NOTE

- For wave file recordings larger than 4 GB, the EBU RIFF standard is used. If a FAT 32 disk is used (not recommended), audio files are split automatically. In the **Preferences** dialog, you can specify what happens, when your recorded Wave file is larger than 4 GB.
- You can set up embedded strings in the **Preferences** dialog.

Stereo Pan Law

If you pan a channel left or right, the sum of the left and right side is higher (louder), than if this channel is panned center. These modes allow you to attenuate signals panned center. **0 dB** turns off constant-power panning. **Equal Power** means that the power of the signal remains the same regardless of the pan setting.

Volume Max

Allows you to specify the maximum fader level. By default, this is set to +12 dB. If you load projects that were created with Cubase versions older than 5.5, this value is set to the old default value of +6 dB.

HMT Type (MIDI only)

Allows you to specify a mode for Hermode tuning of MIDI notes.

HMT Depth (MIDI only)

Allows you to specify the overall degree of retuning.

RELATED LINKS

[VST Audio System](#) on page 13

[Record - Audio](#) on page 1031

Opening Project Files

You can open one or several saved project files at the same time.

IMPORTANT

If you open a project saved with a different program version that contains data for functions that are not available in your version, this data may be lost when you save the project with your version.

NOTE

- If you open an external project, the last used view that was saved on your computer is used. You can change this setting in the **Preferences** dialog (**General** page).
- External projects are automatically connected to the input and output busses. If you open a project that was created on a computer with an ASIO port configuration different from the configuration of your computer, this can result in unwanted audio connections. You can deactivate the automatic connection of input and output busses in the **Preferences** dialog (**VST** page).

PROCEDURE

1. Select **File > Open**.
2. In the file dialog that opens, select the project that you want to open and click **Open**.
3. If there already is an open project, you are asked if you want to activate the new project. Do one of the following:
 - To activate the project, click **Activate**.
 - To open the project without activating it, click **No**.
This reduces load times for projects.

RELATED LINKS

[Workspaces for External Projects](#) on page 991

[Do not Connect Input/Output Busses When Loading External Projects](#) on page 1038

Activating Projects

If you have several projects opened at the same time in Cubase, only one project can be active. The active project is indicated by the lit **Activate Project** button in the upper left corner of the **Project** window. If you want to work on another project, you have to activate the other project.

PROCEDURE

- To activate a project, click **Activate Project** .
-

Opening Recent Projects

To open a recently opened project, do one of the following:

- In the category bar of the **Hub** or the **Project Assistant** dialog, click **Recent**, select a project from the projects list, and click **Open**.
- Select **File** > **Recent Projects** and select a recently opened project.

Re-Routing Missing Ports

If you open a Cubase project that was created on a different system with other audio hardware, Cubase tries to find matching audio inputs and outputs for the input/output busses. If Cubase cannot resolve all audio/MIDI inputs and outputs that are used in the project, the **Missing Ports** dialog opens.

This allows you to manually re-route any ports specified in the project to ports that are available in your system.

NOTE

To improve the search for matching audio inputs and outputs for the input/output busses, you should use descriptive, generic names for your input and output ports.

RELATED LINKS

[Renaming the Hardware Inputs and Outputs](#) on page 27

Saving Project Files

You can save the active project as a project file. To keep your projects as manageable as possible, make sure that you save project files and all related files in the respective project folders.

- To save the project and specify a file name and location, open the **File** menu and select **Save As**.
- To save the project with its current name and location, open the **File** menu and select **Save**.

About the Auto Save Option

Cubase can automatically save backup copies of all open project files with unsaved changes.

NOTE

Only the project files are backed up. If you want to include the files from the Pool and save your project in a different location, you must use the **Back up Project** function.

Cubase can automatically save backup copies of all open projects with unsaved changes. To set this up, activate the **Auto Save** option in the **Preferences** dialog (**General** page). The backup

copies are named “<project name>-xx.bak” where xx is an incremental number. Unsaved projects are backed up in a similar way as “UntitledX-xx.bak”, with X being the incremental number for unsaved projects. All backup files are saved in the project folder.

- To specify the time intervals in which a backup copy is created, use the **Auto Save Interval** setting.
- To specify how many backup files are created with the **Auto Save** function, use the **Maximum Backup Files** option. When the maximum number of backup files is reached, the existing files are overwritten, starting with the oldest file.

Saving Project Files As a New Version

You can create and activate a new version of an active project file. This is useful if you are experimenting with edits and arrangements and want to be able to go back to a previous version at any time.

To save a new version of the active project, do one of the following:

- Select **File > Save New Version**.
- Press **Ctrl/Cmd-Alt-S**.

The new file is saved with the same name as the original project and an attached incremental number. For example, if your project is called “My Project,” new versions are called “My Project-01”, “My Project-02”, and so on.

Reverting to the Last Saved Version


You can return to the last saved version and discard all changes that have been introduced.

PROCEDURE

1. Select **File > Revert**.
 2. In the warning message, click **Revert**.
If you have recorded or created new audio files since the last version was saved, you are prompted to delete or keep the files.
-

Choosing a Project Location

In the **Hub** and in the **Project Assistant**, you can specify where to save a project.



- To create a project in the default project location, select **Use default location**.
In the **Project folder** field, you can specify a name for the project folder. If you do not specify a project folder here, the project is saved in a folder named **Untitled**.
- To change the default project location, click in the path field.
A file dialog opens that allows you to specify a new default location.
- To create the project in a different location, select **Prompt for project location**.
In the dialog that opens, specify a location and a project folder.

Creating Self-Contained Projects

If you want to share your work or transfer it to another computer, your project must be self-contained.

The following functions facilitate this task:

- Select **Media > Prepare Archive** to verify that every clip that is referenced in the project is located in the project folder, and to take actions if that is not the case.
- Select **File > Back up Project** to create a new project folder where you can save the project file and the necessary work data. The original project remains unchanged.

Preparing Archives

The Prepare Archive function allows you to gather all files that are referenced by your project to ensure that these are in the project folder. This is useful if you want to move or archive your project.

PROCEDURE

1. Select **Media > Prepare Archive**.
If your project references external files, you are prompted if you want to copy them to your working directory. If any processing has been applied, you must decide if you want to flatten edits.
2. Click **Proceed**.

RESULT

Your project is ready to be archived. You can move or copy the project folder to another location.

AFTER COMPLETING THIS TASK

You must copy audio files that reside within the project folder to the Audio folder or save them separately. You must also move your video clips manually, as videos are only referenced and not saved in the project folder.

Backing Up Projects

You can create a backup copy of your project. Backups only contain the necessary work data. All media files except the files from VST Sound archives are included as a copy.

PROCEDURE

1. Select **File > Back up Project**.
2. Select an empty folder or create a new one.
3. Make your settings in the **Back up Project Options** dialog and click **OK**.

RESULT

A copy of the project is saved in the new folder. The original project remains unaffected.

NOTE

VST Sound content provided by Steinberg is copy-protected and will not be included in the backup project. If you want to use a backup copy that uses VST Sound content on a different computer, make sure that the corresponding content is also available on that computer.

Back up Project Options Dialog

This dialog allows you to create a backup copy of your project.

- To open the **Back up Project Options** dialog, select **File > Back up Project**.

Project Name

Allows you to change the name of the backed up project.

Keep Current Project Active

Allows you to keep the current project active after clicking **OK**.

Minimize Audio Files

Allows you to include only the audio file portions that are actually used in the project. This can significantly reduce the size of the project folder if you are using small sections of large files. It also means that you cannot use other parts of the audio files if you continue working with the project in its new folder.

Freeze Direct Offline Processing

Allows you to flatten all edits and make all processing and applied effects permanent to each clip in the Pool.

Remove Unused Files

Allows you to remove unused files and to back up only the files that are actually used.


Do Not Back up Video

Allows you to exclude video clips on the video track or in the Pool of the current project.

Tracks

Tracks are the building blocks of your project. They allow you to import, add, record, and edit data (parts and events). Tracks are listed from top to bottom in the Track list and extend horizontally across the **Project** window. Each track is assigned to a particular channel strip in the MixConsole.

If you select a track in the **Project** window, the controls, settings, and parameters displayed in the Inspector and the track list allow you to control the track.




Track Inspector Settings

For each track type you can configure which **Inspector** sections are shown. You can also specify the order of the sections.

- To open the **Track Inspector Settings** dialog, click **Setup Inspector**, and select **Setup** from the pop-up menu.





Hidden Items

Displays sections that are hidden in the **Inspector**.

Visible Items

Displays sections that are visible in the **Inspector**.

Pin

If you activate **Pin** by clicking the column for a section the open/close status of the selected **Inspector** section is pinned.

Add

Allows you to move an item selected in the hidden sections list to the list of visible sections.

Remove

Allows you to move an item selected in the visible sections list to the list of hidden sections.

Move Up/Move Down

Allows you to change the order of an item in the list of visible sections.

Presets

Allows you to save **Inspector** section settings as presets.


Reset All


Allows you to restore the default **Inspector** section settings.

Track Control Settings

For each track type you can configure which track controls are shown in the track list. You can also specify the order of controls and group controls so that they are always shown adjacent to each other.

- To open the **Track Controls Settings** dialog, right-click a track in the track list and select **Track Controls Settings** from the context menu, or click **Open Track Controls Settings Dialog** in the bottom right corner of the track list.





Track Type

Allows you to select the track type to which your settings are applied.

Hidden Controls

Displays controls that are hidden in the track list.

Visible Controls

Displays controls that are visible in the track list.

Width

If you click in this column, you can set the maximum length for the track name.

Group

Displays the group number.

Add

Allows you to move an item selected in the hidden controls list to the list of visible controls.

Remove

Allows you to move an item selected in the visible controls list to the list of hidden controls. All controls can be removed except **Mute** and **Solo**.

Move Up/Move Down

Allows you to change the order of an item in the list of visible controls.

Group

Allows you to group two or more controls selected in the visible controls list that are adjacent to each other. This ensures that they are always positioned side by side in the track list.

Ungroup

Allows you to ungroup grouped controls in the visible controls list. To remove an entire group, select the first (topmost) element belonging to this group and click **Ungroup**.

Reset

Allows you to restore all default track controls settings for the selected track type.

Controls Area Preview

Shows a preview of the customized track controls.

Controls Area Width

Allows you to determine the width of the track control area for the selected track type. In the **Controls Area Preview**, this area is shown with a frame.

Presets

Allows you to save track controls settings as presets. To recall a preset, click **Switch Presets** in the bottom right corner of the track list. The name of the selected preset is shown in the left corner.

Track Name Width (global)

Allows you to determine the global name width for all track types.

Apply

Applies your settings.

Reset All

Allows you to restore all default track controls settings for all track types.

Audio Tracks

You can use audio tracks for recording and playing back audio events and audio parts. Each audio track has a corresponding audio channel in the MixConsole. An audio track can have any number of automation tracks for automating channel parameters, effect settings, etc.

- To add an audio track to your project, select **Project > Add Track > Audio**.

RELATED LINKS

[Adding Tracks](#) on page 151


Audio Track Inspector

The **Inspector** for audio tracks contains controls and parameters that allow you to edit your audio track.



The top section of the audio track **Inspector** contains the following basic track settings:

Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Open Device Panels (Cubase Pro only)



Allows you to create a device panel for the plug-in and device parameters of your track.

Auto Fades Settings



Opens a dialog where you can make separate audio fade settings for the track.

Record enable



Activates the track for recording.

Monitor



Routes incoming signals to the selected output.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Show Lanes



Divides the tracks in lanes.

Freeze Audio Channel



Allows you to freeze the audio channel.

Volume



Allows you to adjust the level for the track.

Pan



Allows you to adjust the panning of the track.

Delay



Allows you to adjust the playback timing of the track.

Load/Save/Reload Track Preset



Loads or saves a track preset or reverts the default presets.

Input Routing



Allows you to specify the input bus for the track.

Output Routing




Allows you to specify the output bus for the track.

Audio Track Inspector sections

Apart from the basic track settings that are always shown, audio tracks provide other Inspector sections. These are described in the following sections.

TrackVersions




Allows you to create and edit **TrackVersions**.

Chords



Allows you to specify how the track follows the chord track.

Inserts




Allows you to add insert effects to the track.

Strip



Allows you to set up the channel strip modules.

Equalizers



Allows you to adjust the EQs for the track. You can have up to four bands of EQ for each track.

Sends



Allows you to route the track to one or several FX channels.

Cue Sends (Cubase Pro only)



Allows you to route cue mixes to **Control Room** cues.

Direct Routing



Allows you to set up direct routing.

Surround Pan (Cubase Pro only)



Shows the panner for a track.

Fader




Shows a duplicate of the corresponding **MixConsole** channel.

Notepad



Allows you to enter notes about the track.

Device Panel (Cubase Pro only)



Allows you to display and use device panels.


Quick Controls



Allows you to configure quick controls to use remote devices, for example.

Audio Track Controls

The Track List for audio tracks contains controls and parameters that allow you to edit your audio track.



Track name

 Audio 01

Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Record enable



Activates the track for recording.

Monitor



Routes incoming signals to the selected output.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Show Lanes



Divides the tracks in lanes.

Bypass Inserts



Bypasses the inserts for the track.

Bypass EQs



Bypasses the equalizers for the track.

Bypass Sends



Bypasses the sends for the track.

Channel Configuration



Shows the channel configuration of the track.

Listen



The listen indicator is lit if the track is in listen mode.

Freeze Channel



Opens the **Freeze Channel Options** dialog that allows you to set the **Tail Size** time in seconds.

Instrument Tracks

You can use instrument tracks for dedicated VST instruments. Each instrument track has a corresponding instrument channel in the **MixConsole**. An instrument track can have any number of automation tracks.

- To add an instrument track to your project, select **Project > Add Track > Instrument**.

Instrument Track Inspector

The Inspector for instrument tracks contains controls and parameters that allow you to control your instrument track. It shows some of the sections from VST instrument channels and MIDI tracks.



The top section of the instrument track Inspector contains the following basic track settings:

Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Open Device Panels



Allows you to open the instrument panel.

Input Transformer



Opens the **Input Transformer** dialog that allows you to transform incoming MIDI events in realtime.

Record enable



Activates the track for recording.

Monitor



Routes incoming MIDI to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Freeze Instrument Channel



Allows you to freeze the instrument.

Volume



Allows you to adjust the level of the track.

Pan



Allows you to adjust the panning of the track.

Delay



Allows you to adjust the playback timing of the track.

Show Lanes



Divides the tracks in lanes.

Load/Save/Reload Track Preset



Loads or saves a track preset or reverts the default presets.

Input Routing



Allows you to specify the input bus for the track.

Activate Outputs



This control is only available if the instrument provides more than one output. It allows you to activate one or more outputs for the instrument.

Edit Instrument



Allows you to open the instrument panel.

Programs



Allows you to select a program.

Drum Map




Allows you to select a drum map for the track.

Instrument Track Inspector Sections


Apart from the basic track settings that are always shown, instrument tracks provide other Inspector sections. These are described in the following sections.

TrackVersions



Allows you to create and edit **TrackVersions**.

Chords



Allows you to specify how the track follows the chord track.

Expression Map



Allows you to use the **Expression Map** features.

Note Expression



Allows you to work with the **Note Expression** features.

MIDI Modifiers



Allows you to transpose or adjust the velocity of the MIDI track events in realtime during playback.

MIDI Inserts




Allows you to add MIDI insert effects.

Instrument Section




Shows the audio-related controls for the instrument.

Notepad



Allows you to enter notes about the track.

Device Panel (Cubase Pro only)



Allows you to display and use device panels.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

Instrument Track Controls

The Track List for instrument tracks contains controls and parameters that allow you to edit your instrument track.



Mute




Mutes the track.

Solo



Solos the track.

Track name



Double-click to rename the track.

Record enable



Activates the track for recording.

Monitor



Allows you to route incoming MIDI signals to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Edit



Opens the **Channel Settings** window for the track.

Edit Instrument



Allows you to open the instrument panel.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Show Lanes




Divides the tracks in lanes.

ASIO Latency Compensation



Moves all recorded events on the track by the current latency.

Programs



Allows you to select a program.

Bypass Inserts



Bypasses the inserts for the track.

Bypass EQs



Bypasses the equalizers for the track.

Bypass Sends



Bypasses the sends for the track.

Instrument



Allows you to select an instrument.

Listen



The listen indicator is lit if the track is in listen mode.

Edit In-Place



Allows you to edit MIDI events and parts on the track in the **Project** window.

Lock



Disables all editing of all events on the track.

Channel Configuration



Shows the channel configuration of the track.

Drum Map



Allows you to select a drum map for the track.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Freeze Channel



Opens the **Freeze Channel Options** dialog that allows you to set the **Tail Size** time in seconds.

Load available update



This button lights up when other users have made changes to a track and committed them over the network to indicate that you can load the changes and update the project.


MIDI Tracks

You can use MIDI tracks for recording and playing back MIDI parts. Each MIDI track has a corresponding MIDI channel in the **MixConsole**. A MIDI track can have any number of automation tracks.

- To add a MIDI track to your project, select **Project > Add Track > MIDI**.


MIDI Track Inspector

The Inspector for MIDI tracks contains controls and parameters that allow you to control your MIDI track. These affect MIDI events in realtime, on playback, for example.



The top section of the MIDI track Inspector contains the following basic track settings:

Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Open Device Panels



Allows you to open the instrument panel.

Input Transformer



Opens the **Input Transformer** dialog that allows you to transform incoming MIDI events in realtime.

Record enable



Activates the track for recording.

Monitor



Routes incoming MIDI to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Show Lanes



Divides the tracks in lanes.

MIDI Volume



Allows you to adjust the MIDI volume for the track.

MIDI Pan



Allows you to adjust the MIDI pan for the track.

Delay



Allows you to adjust the playback timing of the track.

Load/Save/Reload Track Preset



Loads or saves a track preset or reverts the default presets.

Input Routing



Allows you to specify the input bus for the track.

Output Routing



Allows you to specify the output bus for the track.

Channel



Allows you to specify the MIDI channel.

Edit Instrument



Allows you to open the instrument panel.

Bank Selector



Allows you to set a bank select message that is sent to your MIDI device.

Program Selector



Allows you to set a program change message that is sent to your MIDI device.

Drum Map



Allows you to select a drum map for the track.

MIDI Track Inspector Sections


Apart from the basic track settings that are always shown, MIDI tracks provide other Inspector sections. These are described in the following sections.

TrackVersions



Allows you to create and edit **TrackVersions**.

Chords



Allows you to specify how the track follows the chord track.

Expression Map



Allows you to use the **Expression Map** features.

Note Expression



Allows you to work with the **Note Expression** features.

MIDI Modifiers



Allows you to transpose or adjust the velocity of the MIDI track events in realtime during playback.

MIDI Inserts




Allows you to add MIDI insert effects.

MIDI Sends Section



Allows you to add MIDI send effects.

MIDI Fader Section




Shows a duplicate of the corresponding **MixConsole** channel.

Notepad



Allows you to enter notes about the track.

Device Panel (Cubase Pro only)



Allows you to display and use device panels.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

MIDI Track Controls

The Track List for MIDI tracks contains controls and parameters that allow you to edit your MIDI track.



The track list for MIDI tracks contains the following controls:

Mute



Mutes the track.

Solo



Solos the track.

Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Record enable



Activates the track for recording.

Monitor



Allows you to route incoming MIDI signals to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Channel



Allows you to specify the MIDI channel.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Show Lanes



Divides the tracks in lanes.

Output



Allows you to specify the output for the track.

Programs



Allows you to select a program.

Edit In-Place



Allows you to edit MIDI events and parts on the track in the **Project** window.

Bypass Inserts



Bypasses the inserts for the track.

Bypass Sends



Bypasses the sends for the track.

Lock



Disables all editing of all events on the track.

Edit



Opens the **Channel Settings** window for the track.

Drum Map



Allows you to select a drum map for the track.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Load available update



This button lights up when other users have made changes to a track and committed them over the network to indicate that you can load the changes and update the project.

ASIO Latency Compensation



Moves all recorded events on the track by the current latency.

Sampler Tracks

You can use sampler tracks for controlling the playback of audio samples via MIDI. Each sampler track has a corresponding channel in the **MixConsole**. A sampler track can have any number of automation tracks.

- To add a sampler track, select **Project > Add Track > Sampler**.

RELATED LINKS

[Creating Sampler Tracks](#) on page 515


Sampler Track Inspector

The **Inspector** for sampler tracks contains controls and parameters that allow you to edit your sampler track.



The top section of the sampler track Inspector contains the following basic track settings:

Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Input Transformer



Opens the **Input Transformer** dialog that allows you to transform incoming MIDI events in realtime.

Record enable



Activates the track for recording.

Monitor



Routes incoming MIDI to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Show Lanes



Divides the tracks in lanes.

Freeze Sampler Channel



Allows you to freeze the sampler track.

Volume



Allows you to adjust the level of the track.

Pan



Allows you to adjust the panning of the track.

Delay



Allows you to adjust the playback timing of the track.

Load/Save/Reload Track Preset



Loads or saves a track preset or reverts the default presets.

Input Routing



Allows you to specify the input bus for the track.

Sampler Track Inspector Sections


Apart from the basic track settings that are always shown, sampler tracks provide other Inspector sections. These are described in the following sections.

TrackVersions



Allows you to create and edit **TrackVersions**.

Chords




Allows you to specify how the track follows the chord track.

Expression Map



Allows you to use the **Expression Map** features.

Note Expression



Allows you to work with the **Note Expression** features.

MIDI Modifiers



Allows you to transpose or adjust the velocity of the MIDI track events in realtime during playback.

MIDI Inserts




Allows you to add MIDI insert effects.

Instrument Section




Shows the audio-related controls for the sampler track.

Notepad



Allows you to enter notes about the track.

Device Panel (Cubase Pro only)



Allows you to display and use device panels.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

Sampler Track Controls

The track list for sampler tracks contains controls and parameters that allow you to edit your sampler track.



Mute



Mutes the track.

Solo



Solos the track.

Track name



Double-click to rename the track.

Record enable



Activates the track for recording.

Monitor



Allows you to route incoming MIDI signals to the selected MIDI output. For this to work, activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

Edit



Opens the **Channel Settings** window for the track.

Open/Close Sampler

Opens/Closes the **Sampler Control** in the lower zone.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Show Lanes



Divides the tracks in lanes.

ASIO Latency Compensation



Moves all recorded events on the track by the current latency.

Bypass Inserts



Bypasses the inserts for the track.

Bypass EQs



Bypasses the equalizers for the track.

Bypass Sends



Bypasses the sends for the track.

Listen



The listen indicator is lit if the track is in listen mode.

Edit In-Place



Allows you to edit MIDI events and parts on the track in the **Project** window.

Lock



Disables all editing of all events on the track.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Freeze Channel



Opens the **Freeze Channel Options** dialog that allows you to set the **Tail Size** time in seconds.


Arranger Track

You can use the arranger track for arranging your project by marking out sections and determining in which order they are to be played back.

- To add the arranger track to your project, select **Project > Add Track > Arranger**.


Arranger Track Inspector

The arranger track Inspector displays the lists of available arranger chains and arranger events.



The arranger track Inspector contains the following settings:

Track Name




Double-click to rename the track.

Edit



Opens the **Arranger Editor**.

Select Active Arranger Chain + Function



Allows you to select the active arranger chain, to rename it, to create a new one, to duplicate or to flatten it.

Current Arranger Chain



Shows the active arranger chain.

Arranger Events




Lists all arranger events in your project. Click the arrow for an arranger event to play it back and start the live mode.

Stop



Allows you to stop the live mode.

Jump mode




Allows you to define how long the active arranger event is played before jumping to the next one.

Arranger Track Controls

The track list for the arranger track contains controls and parameters that allow you to edit the arranger track.



Select Active Arranger Chain



Allows you to select the active arranger chain.

Current Item/Current Repeat



Displays which arranger event and which repeat is active.

Activate Arranger Mode



Allows you to activate and deactivate the arranger mode.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Edit



Opens the **Arranger Editor** for the track.


Chord Track

You can use the chord track for adding chord and scale events to your project. These can transform the pitches of other events.

- To add the chord track to your project, select **Project > Add Track > Chord**.


Chord Track Inspector

The chord track Inspector contains a number of settings for the chord events.



The top section of the chord track Inspector contains the following settings:

Track name



Click to show/hide the basic track settings section.

Mute



Mutes the track.

Record enable



Activates the track for recording.

Acoustic Feedback



Allows you to audition the events on the chord track. For this to work, you need to select a track for auditioning in the track list.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Voicing library



Allows you to set up a voicing library for the track.

Voicing library subset

Rock/Easy Jazz ▾

Allows you to select a library subset.

Configure voicing parameters



Allows you to configure your own voicing parameters for a specific voicing scheme.

Adaptive Voicings

Adaptive Voicings

If this option is activated the voicings will be set automatically.

Automatic Scales

Automatic Scales

If this option is activated the program creates scale events automatically.

Mapping Offset


Mapping Offset 0 Ticks

Allows you to specify an offset value to make sure that chord events also affect the MIDI notes that have been triggered too early (enter a negative value) or too late (enter a positive value).

Chord Track Inspector Sections


Apart from the basic track settings that are always shown, the chord track provides other Inspector sections. These are described in the following sections.

TrackVersions



Allows you to create and edit **TrackVersions**.


Notepad



Allows you to enter notes about the track.

Chord Track Controls

The Track List for the chord track contains controls and parameters that allow you to edit the chord track.



The track list for chord tracks contains the following controls:

Mute



Mutes the track.

Select Track for Auditioning



Allows you to select a track for auditioning the chord events.

Record Enable



Allows you to record chord events.

Resolve Display Conflicts



Allows you to show all chord events on the track properly, even at low horizontal zoom levels.

Show Scales



Allows you to show the scale lane in the lower part of the chord track.

Lock



Disables all editing of all events on the track.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

FX Channel Tracks

You can use FX channel tracks for adding send effects. Each FX channel can contain up to eight effect processors. By routing sends from an audio channel to an FX channel, you send audio from the audio channel to the effects on the FX channel. You can place FX channel tracks in a special FX channel folder, or in the track list, outside a FX channel folder. Each FX channel has a corresponding channel in the MixConsole. An FX channel track can have any number of automation tracks.


- To add an FX channel track to your project, select **Project > Add Track > FX Channel**.

FX Channel Track Inspector

The Inspector for FX channel tracks shows the settings for the FX channel. When you select the folder track instead, the Inspector shows the folder and the FX channels it contains. You can click one of the FX channels shown in the folder to have the Inspector show the settings for that FX channel.



Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Volume



Allows you to adjust the level of the track.

Pan



Allows you to adjust the panning of the track.

Output Routing




Allows you to specify the output bus for the track.

FX Channel Track Inspector Sections

Apart from the basic track settings that are always shown, FX channel tracks provide other Inspector sections. These are described in the following sections.

Inserts




Allows you to add insert effects to the track.

Strip



Allows you to set up the channel strip modules.

Equalizers



Allows you to adjust the EQs for the track. You can have up to four bands of EQ for each track.

Sends



Allows you to route the track to one or several FX channels.

Cue Sends (Cubase Pro only)



Allows you to route cue mixes to **Control Room** cues.

Direct Routing



Allows you to set up direct routing.

Surround Pan (Cubase Pro only)




Shows the panner for a track.

Fader



Shows a duplicate of the corresponding **MixConsole** channel.

Notepad



Allows you to enter notes about the track.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

FX Channel Track Controls

The Track List for FX channel tracks contains controls and parameters that allow you to edit the settings for the effect.



Track name

FX 2-MonoDelay

Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation




Allows you to write track automation.

Mute Automation



Deactivates the automation read function for the selected parameter.

Automation parameter



Allows you to select a parameter for automation.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Bypass Inserts



Bypasses the inserts for the track.

Bypass EQs



Bypasses the equalizers for the track.

Bypass Sends



Bypasses the sends for the track.

Channel Configuration



Shows the channel configuration of the track.

RELATED LINKS

[Click Pattern Editor](#) on page 225

[Creating a Click Track](#) on page 232


Folder Tracks

Folder tracks function as containers for other tracks, making it easier to organize and manage the track structure. They also allow you to edit several tracks at the same time.

- To add a folder track to your project, select **Project > Add Track > Folder**.

Folder Track Inspector

The Inspector for folder tracks shows the folder and its underlying track, much like a folder structure in the File Explorer/macOS Finder. When you select the one of the tracks shown under the folder, the Inspector shows the settings for that track.



Track name



Double-click to rename the track.

Mute



Mutes the track.

Solo



Solos the track.

Record enable



Activates the track for recording.

Monitor



Routes incoming signals to the selected output.

Group Editing



Allows you to activate the group editing mode.

Lock



Disables all editing of all events on the track.

Folder Track Controls

The Track List for folder tracks contains controls and parameters that allow you to edit all tracks in the folder.



Expand/Collapse

Shows/hides the tracks in the folder. Hidden tracks are played back as usual.

Track name



Double-click to rename the track.

Mute



Mutes the track.

Solo



Solos the track.

Record enable



Activates the track for recording.

Monitor



Routes incoming signals to the selected output.

Group Editing



Allows you to activate the group editing mode.

Lock



Disables all editing of all events on the track.

Group Channel Tracks

You can use group channel tracks to create a submix of several audio channels and apply the same effects to them. A group channel track contains no events as such, but displays settings and automation for the corresponding group channel.

All group channel tracks are automatically placed in a special group track folder in the track list, for easy management. Each group channel track has a corresponding channel in the MixConsole. A group channel track can have any number of automation tracks.

- To add a group channel track to your project, select **Project > Add Track > Group Channel**.

Group Channel Track Inspector

The Inspector for group channel tracks shows the settings for the group channel.



Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute Automation



Deactivates the automation read function for the selected parameter.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Volume



Allows you to adjust the level for the track.

Pan



Allows you to adjust the panning of the track.

Output Routing



Allows you to specify the output bus for the track.

NOTE


When you select the group folder track instead, the Inspector shows the folder and the group channels it contains. You can click one of the group channels shown in the folder, to have the Inspector show the settings for that group channel.



Group Channel Track Inspector sections

Apart from the basic track settings that are always shown, group channel tracks provide other Inspector sections. These are described in the following sections.

Inserts




Allows you to add insert effects to the track.

Strip




Allows you to set up the channel strip modules.

Equalizers



Allows you to adjust the EQs for the track. You can have up to four bands of EQ for each track.

Sends



Allows you to route the track to one or several FX channels.

Cue Sends (Cubase Pro only)



Allows you to route cue mixes to **Control Room** cues.

Direct Routing



Allows you to set up direct routing.

Surround Pan (Cubase Pro only)



Shows the panner for a track.

Fader



Shows a duplicate of the corresponding **MixConsole** channel.

Notepad



Allows you to enter notes about the track.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

Group Channel Track Controls

The Track List for group channel tracks contains controls and parameters that allow you to edit the settings for the group.



Track name

Group 1

Double-click to rename the track.

Edit



Opens the **Channel Settings** window for the track.

Mute



Mutes the track.

Solo



Solos the track.

Read Automation



Allows you to read track automation.

Write Automation




Allows you to write track automation.

Mute Automation



Deactivates the automation read function for the selected parameter.

Automation parameter



Allows you to select a parameter for automation.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Bypass Inserts



Bypasses the inserts for the track.

Bypass EQs



Bypasses the equalizers for the track.

Bypass Sends



Bypasses the sends for the track.

Channel Configuration



Shows the channel configuration of the track.


Marker Track

Cubase Pro only: You can use marker tracks to add and edit markers that help you to locate certain positions quickly. Cubase Artist only: You can use the marker track to add and edit markers that help you to locate certain positions quickly.

- To add the marker track to your project, select **Project > Add Track > Marker**.
Cubase Pro only: You can add up to 10 marker tracks in a project.

Marker Track Inspector

The marker track Inspector displays the marker list.



ID	Position
[1]	1. 1. 1. 0
1	7. 1. 1. 0
2	8. 1. 1. 0
3	9. 1. 1. 0

Track name

Markers 01

Double-click to rename the track.

Edit



Opens the **Markers** window.


Marker attributes

ID Position

Shows the markers, their IDs, and time positions. Click in the leftmost column for a marker to move the project cursor to the marker position.

Marker Track Controls

The track list for the marker track contains controls and parameters that allow you to edit the marker track.



Track name

Markers

Double-click to rename the track.

Locate

Locate

Allows you to move the project cursor to the selected marker position.

Cycle

Cycle

Allows you to select a cycle marker.

Zoom

Zoom

Allows you to zoom in a cycle marker.

Add Marker



Allows you to add a position marker at the project cursor position.

Add Cycle Marker



Allows you to add a cycle marker at the project cursor position.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Ruler Track


You can use ruler tracks to show several rulers with different display formats for the timeline. This is completely independent from the main ruler, as well as rulers and position displays in other windows.

- To add a ruler track to your project, select **Project > Add Track > Ruler**.

Ruler Track Controls

In the track list for ruler tracks you can change the display format for the ruler.

Right-click the ruler to open the display format pop-up menu.



The following display formats are available:

Bars+Beats

Activates a display format of bars, beats, sixteenth notes, and ticks. By default there are 120 ticks per sixteenth note. To adjust this, set the **MIDI Display Resolution** in the **Preferences** dialog (**MIDI** page).

Seconds

Activates a display format of hours, minutes, seconds, and milliseconds.

Timecode

Activates a display format of hours, minutes, seconds, and frames. The number of frames per second (fps) is set in the **Project Setup** dialog with the **Frame Rate** pop-up menu. To display subframes, activate **Show Timecode Subframes** in the **Preferences** dialog (**Transport** page).

Samples

Activates a display format of samples.

fps (User)

Activates a display format of hours, minutes, seconds, and frames, with a user-definable number of frames per second. To display subframes, activate **Show Timecode Subframes** in the **Preferences** dialog (**Transport** page). On the **Transport** page, you can also set the frame rate.

NOTE

Ruler tracks are not affected by the display format setting in the **Project Setup** dialog.

Signature Track

You can use the signature track to add and edit signature events, and to set up click patterns for them. The signature track's background always shows bars. This is independent of the ruler display format setting.

- To add the signature track to your project, select **Project > Add Track > Signature**.

RELATED LINKS

[Time Signature Events](#) on page 908

[Click Patterns Page](#) on page 231

Signature Track Inspector

The signature track Inspector displays a list of all time signature events.



Bar	Sign.	Pattern
4/4	-	- - - -
17 3/4	-	- - - -
41 4/4	-	- - - -

Bar

Shows the number of the bar where the signature event is positioned. Double-click the field and enter a new value to change the position of the signature event.

NOTE

The first signature event is always positioned at bar 1. You cannot change this.

Sign.

Shows the value of the signature event. Double-click the field and enter a new value to change the time signature.

Pattern


Shows the click pattern that is used. Double-click the field to open the **Click Pattern Editor** where you can change the pattern.

RELATED LINKS

[Click Pattern Editor](#) on page 225

Signature Track Controls

The track list for the signature track contains controls and parameters that allow you to edit the signature track.



Lock



Disables all editing of all events on the track.

Signature Track Options

- **Copy Click Pattern to Clipboard**
Copies the click pattern of the selected signature event to the clipboard.
- **Paste Click Pattern to Selected Signatures**

Pastes the click pattern from the clipboard to selected signature events.

NOTE

This only works if the selected signature events are equal.

- **Apply Click Pattern to Equal Signatures**
Pastes the click pattern from the clipboard to signature events that are equal.

NOTE

For this you do not have to select the signature events first.

- **Reset Click Pattern to Default**
Sets the click pattern of the selected signature event to default. If no signature event is selected, the click patterns of all signature events are set to default.
- **Show Click Patterns**
Allows you to show/hide the click patterns for the signature events.
- **Render MIDI Click between Locators**
Adds a MIDI track to your project and creates a MIDI part containing the click pattern between the left and right locator.
- **Render Audio Click between Locators**
Adds an audio track to your project and creates an audio event containing the click pattern between the left and right locator.
- **Process Bars Dialog** (Cubase Pro only)
Opens the **Process Bars** dialog.

RELATED LINKS

[Click Patterns Page](#) on page 231

[Process Bars \(Cubase Pro only\)](#) on page 906


Tempo Track

You can use the tempo track to create tempo changes within a project.

- To add a tempo track to your project, select **Project > Add Track > Tempo**.

Tempo Track Inspector

The tempo track Inspector displays a list of all tempo events.



Position	Tempo
1. 1. 1. 0	85.000
1. 1. 2. 5	155.000
1. 1. 2.116	110.000
1. 2. 3. 58	165.000
2. 1. 1. 0	65.000
3. 1. 1. 0	150.000

Edit



Opens the Tempo Track Editor.

Tempo event list



Position	Tempo
----------	-------

Shows a list of all tempo events that allows you to edit tempo events and their positions.

Tempo Track Controls

The track list for the tempo track contains controls and parameters that allow you to edit the tempo track.



Activate Tempo Track



Allows you to activate the tempo track. In this mode, the tempo cannot be changed on the Transport panel.

Lock



Disables all editing of all events on the track.

Current Tempo




Allows you to change the tempo at the project cursor position.

Open Process Tempo Dialog



Allows you to open the **Process Tempo** dialog.

New Tempo Points Type



Allows you to specify whether the tempo should change gradually (Ramp) or instantly (Jump) from the previous curve point to the new one.

Visible Tempo Upper/Lower Limit



Allows you to specify the display range. This changes the display scale of the tempo track, but not the tempo setting.

Transpose Track

You can use the transpose track to set global key changes.

- To add the transpose track to your project, select **Project > Add Track > Transpose**.

Transpose Track Inspector

The transpose track Inspector contains a number of parameters to control the transpose track.



Keep Transpose in Octave Range



Allows you to keep the transposition in the octave range and ensures that nothing is transposed by more than seven semitones.

Toggle Time Base




Switches between musical (tempo related) and linear (time related) time base for the track.

Transpose Track Inspector sections

Apart from the basic track settings that are always shown, the transpose track provides other Inspector sections. These are described in the following sections.

Notepad



Allows you to enter notes about the track.

Transpose Track Controls

The track list for the transpose track contains parameters that allow you to control the transpose track.



Mute Transpose Events



Mutes the track.

Keep Transpose in Octave Range



Allows you to keep the transposition in the octave range and ensures that nothing is transposed by more than seven semitones.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

VCA Fader Track (Cubase Pro only)

You can use a VCA fader track to add VCA faders to your project.

- To add a VCA fader track to your project, select **Project > Add Track > VCA Fader**.

RELATED LINKS

[VCA Faders \(Cubase Pro only\)](#) on page 365

[VCA Fader Automation](#) on page 369

[Automation](#) on page 606

VCA Fader Track Inspector

The **Inspector** for VCA fader tracks shows the settings for the VCA faders.



Track name



Click once to show/hide the basic track settings section. Double-click to rename the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Lock



Disables all editing of all events on the track.

Volume




Allows you to adjust the level of the track.

Fader Section



Shows a duplicate of the corresponding **MixConsole** channel.

Notepad



Allows you to enter notes about the track.

Quick Controls



Allows you to configure quick controls to use remote devices, for example.

VCA Fader Track Controls

The track list for VCA fader tracks contains controls and parameters that allow you to edit the settings for the VCA fader.



Edit



Opens the **Channel Settings** window for the track.

Channel Configuration



Shows the channel configuration of the track.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Lock



Disables all editing of all events on the track.

Toggle Time Base



Switches between musical (tempo related) and linear (time related) time base for the track.

Video Track

You can use the video track to play back video events. Video files are displayed as events/clips on the video track, with thumbnails representing the frames in the film.

- To add a video track to your project, select **Project > Add Track > Video**.

Video Track Inspector

The video track Inspector contains a number of parameters to control the video track.



Reveal Video Window



Opens the **Video Player** window.

Mute Video Track



Mutes the track.

Lock



Disables all editing of all events on the track.

Show Frame Numbers



Allows you to show each thumbnail with the corresponding video frame number.

Show Thumbnails



Allows you to activate/deactivate the thumbnails of a video track.

Video Track Inspector Sections

Apart from the basic track settings that are always shown, the video track provides an other Inspector section. This is described in the following section.

Notepad



Allows you to enter notes about the track.

Video Track Controls

The track list for the video track contains a number of parameters to control the video track.



Mute Video Track



Mutes the track.

Lock



Disables all editing of all events on the track.

Show Thumbnails



Allows you to activate/deactivate the thumbnails of a video track.

Show Frame Numbers



Allows you to show each thumbnail with the corresponding video frame number.

Track Handling

Adding Tracks

You can add tracks via the **Project** menu, the context menu, or by dragging files from the **MediaBay**. Tracks can be added with or without track presets.

Add Track Dialog

The **Add Track** dialog opens when you add audio, MIDI, group/FX/VCA (Cubase Pro only) channels, or instrument tracks. The available options depend on the track type.

Browse

Expands the dialog and allows you to select a track preset for the track.

Count

Allows you to enter the number of tracks that you want to add.

Effect

Allows you to add a send effect to the track.

Configuration

Allows you to set the channel configuration. Audio-related tracks can be configured as mono, stereo, or surround tracks (Cubase Pro only).

Speakers

Shows the speaker names according to the track configuration.

Track Name

Allows you to specify a track name.

Output Routing

Allows you to set the output routing for audio, instrument, FX, and group tracks.

Channels Folder

Allows you to determine whether the track will be added inside or outside the dedicated FX, group, or VCA Fader (Cubase Pro only) channels folder. If you select **Create Outside Folder**, the new track will be added below the selected track.

Add Track

Adds the track and closes the dialog.

Adding Tracks via the Project Menu

PROCEDURE

1. Select **Project > Add Track**.

2. Select a track of a specific type.
 3. In the **Add Track** dialog, edit the add track options.
 4. Click **Add Track**.
-

RESULT

The new tracks are added to the project below the selected track.

RELATED LINKS

[Add Track Dialog](#) on page 151

Adding Tracks based on Track Presets

You can add tracks based on track presets. Track presets contain sound and channel settings.

PROCEDURE

1. Select **Project > Add Track**.
 2. Select **Using Track Preset**.
You can also right-click the track list and select **Add Track Using Track Preset**.
 3. In the **Choose Track Preset** dialog, select a track preset.
The number and type of the added tracks depend on the selected track preset.
 4. Click **Add Track**.
-

RESULT

The new tracks are added to the project below the selected track.

RELATED LINKS

[Add Track Dialog](#) on page 151

[Track Presets](#) on page 179

Adding Tracks by Dragging Files from the MediaBay

PREREQUISITE

One of the following prerequisites must apply:

- The **MediaBay** is open. To open the **MediaBay** press **F5**.
 - The **Media** rack in the right zone of the **Project** window is open. Click **Show/Hide Right Zone**  and click the **Media** tab to open it.
-

PROCEDURE

1. In the **MediaBay**, select the files that you want to add tracks for.
 2. Drag the files into the track list.
 - The indicator highlights the position at which the new tracks will be added.
 - If you drag multiple audio files into the track list, choose if you want to place all files on one track or on different tracks.
 - If you drag multiple audio files into the track list, the **Import Options** dialog opens that allows you to edit the import options.
-

RESULT

The new tracks are added at the position that was highlighted by the indicator in the track list. The audio files are inserted at the cursor position.


RELATED LINKS

[MediaBay](#) on page 546

[Media Rack in Right Zone](#) on page 546

[Import Options Dialog](#) on page 153

Import Options Dialog



Copy Files to Working Directory

Copies the audio file to the **Audio** folder of the project, and has the clip refer to the copy.

Deactivate this option to have the clip refer to the original file in the original location. In this case, it is marked as “external” in the **Pool**.

Convert and Copy to Project if Needed

Converts the imported file if the sample rate or the bit depth differ from the settings in the **Project Setup** dialog.

Split Channels/Split Multi Channel Files

Splits stereo or multi channel audio files into a corresponding number of mono files, one for each channel, and copies the imported files to the **Audio** folder of the project.

Inserts the split files into the project and into the **Pool** as separate mono tracks.

The **Split File Name Format** pop-up menu allows you to specify how the split files are named. This allows for compatibility with other products when exchanging audio files.

Please, don't ask again

Always imports files according to the settings, without opening the dialog again. You can reset this option in the **Preferences** dialog (**Editing—Audio** page).

Importing Tracks (Cubase Pro only)

You can import audio, instrument, sampler, MIDI, chord, marker, and video tracks from other Nuendo or Cubase projects.

Audio, instrument, MIDI, sampler tracks

A new track is created in your project and all events, channel settings, and TrackVersions are imported.

The following mixer settings are not imported: the channel visibility and zone settings, the record-enable status, the send destination, and the device panel settings. The routing settings are imported only if the active project contains the same routing sources and destinations as the imported track.

NOTE

You can also import a track as a new TrackVersion of an existing track. This new TrackVersion gets the name of the imported track and contains all its events. The

channel settings of the existing track remain unchanged. If the imported track contains more than one TrackVersion, only its active TrackVersion is imported.

Imported TrackVersions must be of the same type as the track in your active project.

Marker tracks

A new marker track is created. If your project already contains 10 marker tracks, you cannot import a marker track from another project. In this case, you must remove an existing marker track first.

NOTE

Projects from other Steinberg applications can contain more than 10 marker tracks. If you import marker tracks from these projects, only the first 10 selected marker tracks in the **Import Options** dialog are imported to your project.

Chord tracks

A chord track is created. If your project already contains a chord track, it is replaced by the imported chord track.

Video tracks

A video track is created. If your project already contains a video track, you cannot import a video track from another project. In this case, you must remove the existing video track first.

NOTE

Projects from other Steinberg applications can contain more than one video track. If you import video tracks from these projects, only the first selected video track in the **Import Options** dialog is imported to your project.

Importing Tracks from Project

You can import tracks from other Nuendo or Cubase projects.

PROCEDURE

1. Select **File > Import > Tracks from Project**.
 2. In the file dialog, select a the project file that contains the tracks that you want to import, and click **Open**.
 3. In the **Import** column of the **Import Options** dialog, select the tracks that you want to import or click **Select All**.
 4. Optional: In the **Destination** column, select a destination for the track.
 5. Click **OK**.
-

RESULT

The tracks are imported in your active project.

RELATED LINKS

[Import Options for Tracks](#) on page 155

[TrackVersions](#) on page 171

Importing Tracks from Track Archive

You can import tracks from track archives.

PREREQUISITE

You have created at least one track archive by exporting selected tracks from a project.

PROCEDURE

1. Select **File > Import > Track Archive**.
2. In the file dialog, select the .xml file of the track archive and click **Open**.
3. In the **Import** column of the **Import Options** dialog, select the tracks that you want to import or click **Select All**.
4. Optional: In the **Destination** column, select a destination for the track.
5. Click **OK**.

RESULT

The tracks are imported into your active project.


RELATED LINKS

[Import Options for Tracks](#) on page 155

[TrackVersions](#) on page 171

Import Options for Tracks

The **Import Options** dialog allows you to activate tracks for import, to specify a destination track, and to set up several import options.



Import

Allows you to select the tracks that you want to import into your project.

Type

Shows the track type.

Track Name

Shows the track name.

Destination

Opens a pop-up menu that allows you to select the destination track for the imported track.

Select All

Selects all tracks.

Select None

Deselects all tracks.

Project Settings

Shows the sample rate, the frame rate, and the project start time for both the imported tracks and your active project.

NOTE

Imported tracks may contain media files with a sample rate that differs from the sample rate of your destination project. Files with a sample rate different from the one that is used in the destination project play back at the wrong speed and pitch.

Copy to Active Project Folder

Copies the media files of the imported tracks to your active project folder. If this option is deactivated, the media file path of the original project is referenced.

Perform Sample Rate Conversion

Converts the sample rate of the imported tracks to the sample rate of your active project.

NOTE

This option is available only if the sample rates of the imported tracks and your active project differ and **Copy To Active Project Folder** is activated.

RELATED LINKS

[TrackVersions](#) on page 171

Exporting Tracks as Track Archive (Cubase Pro only)

Track archives contain information that is associated with the tracks such as channel settings, parts and events, and automation.

NOTE

Project-specific settings such as the tempo, are not exported to track archives.

Track archives are saved as .xml files.

When exporting audio and video tracks, you can either reference the media files or copy them to a separate folder.

RELATED LINKS

[Track Presets](#) on page 179

[Exporting Audio or Video Tracks as Track Archives](#) on page 157

Exporting Tracks as Track Archives

PROCEDURE

1. Select the tracks you want to export.
2. Select **File > Export > Selected Tracks**.
3. In the file dialog that opens, select or create a folder for saving the track archive as single .xml file.

4. Enter a file name and click **Save**.
-

RELATED LINKS

[Exporting Audio or Video Tracks as Track Archives](#) on page 157

Exporting Audio or Video Tracks as Track Archives

PROCEDURE

1. Select the audio or video tracks and any other tracks that you want to export.
 2. Select **File > Export > Selected Tracks**.
 3. In the dialog that opens, choose between the following options:
 - Click **Copy** to include copies of the media files in the export.
In the file dialog that opens, select an empty folder or create a new folder for saving the track archive as .xml file and its media subfolder.
Click **OK** to save the track archive.
 - Click **Reference** to include a reference to the files in the export.
In the file dialog that opens, select or create a folder for saving the track archive as single .xml file.
 4. Enter a name for the track archive and click **Save**.
-

Exporting MIDI Tracks as Standard MIDI File

You can export MIDI tracks as standard MIDI files. This allows you to transfer MIDI material to virtually any MIDI application on any platform.

PROCEDURE

1. Select **File > Export > MIDI File**.
 2. In the file dialog that opens, specify a location and name for the file.
 3. Click **Save**.
 4. In the **Export Options** dialog, activate the options for the settings that you want to export, and click **OK**.
-

RESULT

The MIDI file is exported. It includes the tempo and time signature events of the **Tempo Track Editor** or, if the tempo track is deactivated on the **Transport** panel, the current tempo and time signature.

NOTE

If you want to include other **Inspector** settings than those specified in the **Export Options**, use **Merge MIDI in Loop** to convert these settings to real MIDI events.


RELATED LINKS

[Export Options for MIDI Files](#) on page 158

[Merging MIDI Events into a New Part](#) on page 691

Export Options for MIDI Files

The **Export Options** for MIDI files allow you to specify what data is included in the exported MIDI files.



Export Inspector Patch

If this option is activated, the MIDI patch settings in the Inspector - Bank Select and Program Select (used for selecting sounds in the connected MIDI instrument) are included as MIDI Bank Select and Program Change events in the MIDI file.

Export Inspector Volume/Pan

If this option is activated, Volume and Pan settings made in the **Inspector** are included as MIDI Volume and Pan events in the MIDI file.

Export Automation

If this option is activated, the automation data (just as it is heard during playback) is converted to MIDI controller events and included in the MIDI file. This also includes automation recorded with the **MIDI Control** plug-in.

Note that if a continuous controller (CC7, for example) has been recorded but the Read button is deactivated for the automation track (that is the automation is effectively switched off for this parameter), only the part data for this controller will be exported.

If this option is deactivated and the Read Automation button is activated, no continuous controllers will be exported. If the Read button is deactivated, the controller data of the MIDI part are exported (these will now be handled like "regular" part data).

It is recommended to activate the "Export Automation" option.

Export Inserts

If this option is activated and you are using MIDI modifiers or any MIDI plug-ins as insert effects, the modifications to the original MIDI notes that occur as a result of the effects will be included in the MIDI file. A MIDI delay, for example, will produce a number of repeats to a MIDI note by actually adding additional, "echoing" notes at rhythmic intervals - these notes will be included in the MIDI file if the option is activated.

Export Sends

If this option is activated and you are using any MIDI plug-ins as send effects, the modifications to the original MIDI notes that occur as a result of the effects will be included in the MIDI file.

Export Markers

If this option is activated, any markers you have added will be included in the MIDI file as Standard MIDI File Marker events.

Export as Type 0

If this option is activated, the MIDI file will be of Type 0 (all data on a single track, but on different MIDI channels). If you do not check this option, the MIDI file will be of Type 1 (data on separate tracks). Which type to choose depends on what you want to do with the MIDI file (in which application or sequencer it is to be used).

Export Resolution

You can specify a MIDI resolution between 24 and 960 for the MIDI file. The resolution is the number of pulses, or ticks, per quarter note (PPQ) and determines the precision with which you will be able to view and edit the MIDI data. The higher the resolution, the higher the precision. The resolution should be chosen depending on the application or sequencer with which the MIDI file will be used though, because certain applications and sequencers may not be able to handle certain resolutions.

Export Locator Range

If this option is activated, only the range between the left and right locator will be exported.

Export includes Delay

If this option is activated, any delay settings you have made in the **Inspector** will be included in the MIDI file.

RELATED LINKS

[Automation](#) on page 606

[Markers](#) on page 307

[MIDI Track Parameters](#) on page 668

[Merging MIDI Events into a New Part](#) on page 691

[Export Options](#) on page 1027

Removing Tracks

You can remove selected or empty tracks from the track list.

- To remove selected tracks, select **Project > Remove Selected Tracks** or right-click the track that you want to remove, and from the context menu select **Remove Selected Tracks**.

NOTE

If you delete tracks that are not empty, a warning message is displayed. You can deactivate this message. To reactivate the message, activate **Display Warning before Deleting Non-Empty Tracks** in the **Preferences** dialog (**Editing** page).

- To remove empty tracks, select **Project > Remove Empty Tracks**.

Moving Tracks in the Track List

You can move tracks up or down in the track list.

PROCEDURE

- Select a track and drag it up or down in the track list.
-

Renaming Tracks

PROCEDURE

1. Double-click the track name and type in a new name for the track.
 2. Press **Return**.
If you want all events on the track to get the same name, hold down any modifier key and press **Return**.
-


AFTER COMPLETING THIS TASK

If the **Parts Get Track Names** option is activated in the **Preferences** dialog (**Editing** page), and you move an event from one track to another, the moved event will automatically be named according to its new track.

Coloring Tracks

All new tracks are automatically assigned a color according to the **Auto Track Color Mode** settings. However, you can change the track color manually.


- To change the color for the selected track, use the **Select Colors** pop-up menu on the toolbar.



- You can also use the Track Color Selector. In the **Inspector**, click the arrow to the right of the track name and select a color.



In the track list, **Ctrl/Cmd-click** in the left area and select a color.



- To control which colors are used for new tracks, edit the **Auto Track Color Mode** settings in the **Preferences** dialog (**Event Display—Tracks** page).

RELATED LINKS

[Auto Track Color Mode](#) on page 998

Showing Track Pictures

You can add pictures to tracks to recognize your tracks easily. Track pictures are available for audio, instrument, MIDI, FX channel and group channel tracks.

PREREQUISITE

Adjust the track height to at least 2 rows.

PROCEDURE

1. Right-click any track in the track list.
2. From the track list context menu, select **Show Track Pictures**.



If you move the mouse to the left on a track, a highlighted rectangle appears.

AFTER COMPLETING THIS TASK

Double-click the rectangle to open the **Track Pictures Browser** and set up a track picture.

RELATED LINKS

[Track Pictures Browser](#) on page 161

Track Pictures Browser

The **Track Pictures Browser** allows you to set up and select pictures that can be shown in the track list and in the MixConsole. Track pictures are useful to recognize tracks and channels easily. You can select pictures from the factory content or add new ones to the user library.

- To open the **Track Pictures Browser** for a track, double-click in the lower left side of the track list.



Factory

Shows the factory content in the pictures browser.

Pictures Browser

Shows the pictures that you can assign to the selected track/channel.

User

Shows your user content in the pictures browser.

Import

Opens a file dialog that allows you to select pictures in bmp, jpeg, or png format and add them to the user library.

Remove Selected Pictures from User Library

Removes the selected picture from the user library.

Reset Current Picture

Removes the picture from the selected track/channel.

Show/Hide Preview

Opens/Closes a section with further color and zoom settings.

Track Picture Preview

Shows the current track picture. When you zoom in the picture, you can drag it with the mouse to change its visible part.

Track Color

Opens the **Track Color Selector**. Click the rectangle to change the track color.

Intensity

Allows you to apply the track color to the track picture and set the color intensity.

Zoom

Allows you to change the size of the track picture.

Rotate

Allows you to rotate the track picture.

Setting the Track Height

You can enlarge the track height to show the events on the track in detail, or you can decrease the height of several tracks to get a better overview of your project.

- To change the height of an individual track, click its lower border in the track list and drag up or down.
- To change the height of all tracks simultaneously, hold down **Ctrl/Cmd**, click the lower border of one track, and drag up or down.
- To set the number of tracks to view in the **Project** window, use the track zoom menu.
- To set the track height automatically when you select a track, click **Edit > Enlarge Selected Track**.

RELATED LINKS


[Track Zoom Menu](#) on page 162

[Track Control Settings](#) on page 96

Track Zoom Menu

The track zoom menu allows you to set the number of tracks and the track height in the **Project** window.

- To open the track zoom menu in the lower right of the **Project** window, click the arrow button above the vertical zoom control.



The following options are available:

Zoom Tracks x Rows

Zooms all track heights to show the specified number of rows.

Zoom Tracks Full

Zooms all tracks to fit in the active **Project** window.

Zoom x Tracks

Zooms the specified number of tracks to fit in the active **Project** window.

Zoom N Tracks

Allows you to set the number of tracks to fit in the active **Project** window.

Zoom Tracks Minimal

Zooms all track heights to the minimum size.

Snap Track Heights

Changes the track height in fixed increments when you resize it.

Selecting Tracks

- To select a track, click on it in the track list.
- To select several tracks, **Ctrl/Cmd**-click several tracks.
- To select a continuous range of tracks, **Shift**-click the first and last track in a continuous range of tracks.

Selected tracks are highlighted in the track list.

RELATED LINKS

[Track Selection follows Event Selection](#) on page 1014

[Scroll to selected Track](#) on page 1018

[Select Channel/Track on Solo](#) on page 1018

[Select Channel/Track on Edit Settings](#) on page 1018

Selecting Tracks with Arrow Keys

You can select tracks and events with the **Up Arrow** key or the **Down Arrow** key on the computer keyboard. However, you can make the **Up Arrow** key and the **Down Arrow** key exclusively available for selecting tracks.

- To make the **Up Arrow** key and the **Down Arrow** key exclusively available for selecting tracks, activate **Use Up/Down Navigation Commands for selecting Tracks only** in the **Preferences** dialog (**Editing** page).

The following applies:

- If this option is deactivated and no event/part is selected in the **Project** window, the **Up Arrow** key and the **Down Arrow** key are used to step through the tracks in the track list.
- If this option is deactivated and an event/part is selected in the **Project** window, the **Up Arrow** key and the **Down Arrow** key still step through the tracks in the track list – but on the selected track, the first event/part will automatically be selected as well.
- If this option is activated, the **Up Arrow** key and the **Down Arrow** key are only used to change the track selection – the current event/part selection in the **Project** window will not be altered.

Duplicating Tracks

You can duplicate a track with all contents and channel settings.

PROCEDURE

- Select **Project > Duplicate Tracks**.

RESULT

The duplicated track appears below the original track.

Disabling Tracks

You can disable audio, instrument, MIDI, and sampler tracks that you do not want to play back or process at the moment. Disabling a track zeroes its output volume and shuts down all disk activity and processing for the track.

PROCEDURE

- Right-click in the track list and select **Disable Track** from the context menu.

RESULT

The track color changes and the corresponding channel in the **MixConsole** is hidden.

To enable a disabled track and restore all channel settings, right-click in the track list and select **Enable Track**.

Organizing Tracks in Folder Tracks

You can organize your tracks in folders by moving tracks into folder tracks. This allows you to perform editing on several tracks as one entity. Folder tracks can contain any type of track including other folder tracks.

- To create a folder track, open the **Project** menu and in the **Add Track** submenu select **Folder**.

- To create new folder track and move all selected tracks into it, open the **Project** menu and from the **Track folding** submenu select **Move Selected Tracks To New Folder**.
- To move tracks into a folder, select them and drag them into the folder track.
- To remove tracks from a folder, select them and drag them out of the folder.
- To hide/show tracks in a folder, click the **Expand/Collapse Folder** button of the folder track.
- To hide/show data on a folder track, open the context menu for the folder track and select an option from the **Show Data on Folder Tracks** submenu.
- To mute/solo all tracks in a folder track, click the **Mute** or **Solo** button for the folder track.

NOTE

Hidden tracks are played back as usual.

RELATED LINKS

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Moving Tracks to Folder Tracks

You can move your tracks to folder tracks to organize them and to perform editing on several tracks as one entity. You can move any type of track including other folder tracks to folder tracks.

PROCEDURE

- Select **Project > Track Folding > Move Selected Tracks to New Folder**.
-

RESULT

This creates a new folder and moves all selected tracks into it.

NOTE

You can also drag and drop tracks into or out of a folder track.

RELATED LINKS

[Folder Tracks](#) on page 134

[Folder Track Controls](#) on page 134

Handling Overlapping Audio

The basic rule for audio tracks is that each track can only play back a single audio event at a time. If two or more events overlap, you will only hear one of them: the one that is actually visible.

If you have a track with overlapping (stacked) events/regions, use one of the following methods to select the event/region that is played back:

- Open the context menu for the audio event in the event display and select the desired event or region from the **To Front** or **Set to Region** submenu.
The available options depend on whether you performed a linear or a cycle recording and the record mode you used. When recording audio in cycle mode, the recorded event is divided in regions, one for each take.
- Use the handle in the middle of a stacked event and select an entry from the pop-up menu that appears.
- Activate **Show Lanes** and click the desired take.

RELATED LINKS

[Working with Lanes](#) on page 167

Track Folding

You can show, hide, or invert tracks that are displayed in the **Project** window event display. This allows you to divide the project into several parts by creating several folder tracks for the different project elements and showing/hiding their contents by selecting a menu function or using a key command. You can also fold in automation tracks this way.

- To open the **Track Folding** menu, select **Project > Track Folding**.

The following options are available:

Toggle Selected Track

Reverses the fold state of the selected track.

Fold Tracks

Folds in all open folder tracks in the **Project** window.

NOTE

The behavior of this function depends on the **Deep Track Folding** setting in the **Preferences** dialog.

Unfold Tracks

Unfolds all folder tracks in the **Project** window.

NOTE

The behavior of this function depends on the **Deep Track Folding** setting in the **Preferences** dialog.

Flip Fold States

Flips the fold states of the tracks in the **Project** window. This means that all tracks that were folded in will be unfolded and all unfolded tracks will be folded in, respectively.

Move Selected Tracks to New Folder

Moves all selected tracks to the folder track. This menu option is available if at least one folder track is available.

NOTE

You can assign key commands for these menu options in the **Key Commands** dialog in the **Project** category.

The following option also affects the track folding behavior:

Deep Track Folding

You can activate this option in the **Preferences** dialog (**Editing—Project & MixConsole** page).

If this option is activated, any folding settings that you make on the **Track Folding** submenu of the **Project** menu also affect the subelements of the tracks. For example, if you fold in a folder track that contains 10 audio tracks, of which 5 have several open automation tracks, all these audio tracks within the folder track will also be folded in.

How Events are Displayed on Folder Tracks

Closed folder tracks can display data of the contained audio, MIDI, and instrument tracks as data blocks or as events.

When you close folder tracks, the contents of the contained tracks are displayed as data blocks or events. Depending on the folder track height, the display of the events can be more or less detailed.

Modifying Event Display on Folder Tracks

You can modify the event display on folder tracks.

PROCEDURE

1. Right-click the folder track.
2. On the context menu, select **Show Data on Folder Tracks**.

You have the following options:

- **Always Show Data**
If this option is activated, data blocks or event details are always displayed.
- **Never Show Data**
If this option is activated, nothing is displayed.
- **Hide Data When Expanded**
If this option is activated, the display of events is hidden when you open folder tracks.
- **Show Event Details**
If this option is activated, event details are displayed. If this option is deactivated, data blocks are displayed.

NOTE

You can change these settings in the **Preferences** dialog (**Event Display—Folders** page).

RELATED LINKS

[Event Display - Folders](#) on page 1023

Working with Lanes

The descriptions in the following paragraphs focus on cycle recordings with takes. However, you can also apply lane operations and comping methods on overlapping events or parts that you assemble on one track.

If you perform a cycle recording in the **Keep History** or **Cycle History + Replace** modes (audio) or in the **Stacked** or **Mix-Stacked** modes (MIDI), the recorded cycle laps are shown on the track with the last recorded take active and on top.



The **Show Lanes** mode gives you a good overview of all your takes. If you activate the **Show Lanes** button, the recorded takes are shown on separate lanes.



Show Lanes button

Lanes are handled differently, depending on whether you work with audio or MIDI:

Audio

As each audio track can only play back one single audio event at a time, you only hear the take that is activated for playback, for example, the last lap of a cycle recording.

MIDI

Overlapping MIDI takes (parts) can be played back simultaneously. If you recorded in **Mix-Stacked** mode, you hear all takes from all cycle laps.

Lanes can be reordered, sized, and zoomed like regular tracks.

To solo a lane, you can activate the **Solo** button for it. This allows you to hear the lane in the project context. If you want to hear the take without the project context, you also have to activate the main track's **Solo** button.

Assembling a Perfect Take

You can play back, cut, and activate takes to combine the best parts of your recording in a final take.

PROCEDURE

1. Select the **Comp** tool or the **Object Selection** tool.
2. Bring a take to front to select it for playback, and listen to it.
3. Audition different takes to compare them in more detail.
4. If necessary, cut your takes into smaller sections, create new ranges, and bring them to front.
5. Proceed until you are satisfied with the result.

AFTER COMPLETING THIS TASK

After assembling your perfect take, you can improve your take.

- To automatically resolve overlaps and remove empty lanes, right-click the track and select **Clean Up Lanes**.

For audio, proceed as follows:

- Apply auto fades and crossfades to the comped takes.
- To put all takes on a single lane, and remove all takes in the background, select all takes and select **Audio > Advanced > Delete Overlaps**.
- To create a new and continuous event of all selected takes, select **Audio > Bounce Selection**.

For MIDI, proceed as follows:

- Open your takes in a MIDI editor to perform fine adjustments like removing or editing notes.
- To create a new and continuous part of all selected takes that is placed on a single lane, select all takes and select **MIDI > Bounce MIDI**.
- To create a new part and place it on a new track, select **MIDI > Merge MIDI in Loop**.

Finally, clean up the lanes as follows:

- Right-click a track and select **Create Tracks from Lanes**.
The lane is converted into a new track.

Assembling Operations

Unless it is clearly stated, all operations can be performed in the **Project** window and in the **Audio Part Editor**. Snap is taken into account, and all operations can be undone.

To assemble a perfect take, you can use the **Comp** tool, the **Object Selection** tool, or the **Range Selection** tool.

- The **Comp** tool modifies all takes on all lanes simultaneously.
This is useful if the recorded takes have the same start and end positions.
- The **Object Selection** tool and the **Range Selection** tool affect single takes on individual lanes.
If this is not what you want, you can either perform your edits on the main track or use the **Comp** tool.

NOTE

If you assemble stacked events on an audio track, deactivate **Treat Muted Audio Events like Deleted** in the **Preferences** dialog (**Editing—Audio** page).

The following operations can be performed:

Assembling Operations

Operation	Comp tool	Object Selection/Range Selection tool
Select (Project window only)	Hold down Shift and click on a take.	Click on a take.
Bring to front	Click on a take. Click twice to toggle.	Position the mouse pointer over the middle of the lower border of a take until it changes to a Comp symbol, and click. Click twice to toggle. For MIDI this mutes/unmutes a take.
Comp (create a new range and bring it to front, Project window only)	Click and drag on a lane. All takes are cut at the range start and end. If the audio takes are adjacent without gaps or fades and the material itself matches, the takes are merged within the range.	-

Operation	Comp tool	Object Selection/Range Selection tool
Audition	Press Ctrl/Cmd to activate the Speaker tool and click at the position where you want playback to start.	See left.
Move	Click and drag on the main track.	Click and drag on any lane.
Resize	Drag the resize handles. All takes with the same start and end positions are affected. Resizing is constrained to the end or start of the adjacent takes. This ensures that you do not create overlaps accidentally.	Drag the resize handles.
Correct timing (Slip Event)	Select a take, hold down Alt-Shift (the tool modifier for Slip Event) and drag with the mouse.	See left.
Cut	Alt -click on a take. If you cut a MIDI part and the cut position intersects one or several MIDI notes, the result depends on the Split MIDI Events option in the Preferences dialog (Editing—MIDI page).	See left.
Adjust cuts	Position the mouse pointer over a cut and drag to the left or to the right.	See left.
Glueing cuts	Bring a new range to front.	Select a range spanning all the cuts that you want to glue, and double-click.

RELATED LINKS

[Splitting Events](#) on page 196

Defining the Track Time Base

The time base of a track determines if the events on a track are positioned to bars and beats (musical time base) or to the timeline (linear time base). Changing the playback tempo affects only the time position of events on tracks with a musical time base.

PROCEDURE

- In the track list, click **Toggle Timebase**  to change the time base.

RESULT

Musical time base is indicated by a note symbol:



Linear time base is indicated by a clock symbol:



NOTE

Switching between linear and musical time base results in a very small loss of positioning precision. Therefore you should avoid switching repeatedly between the two modes.

RELATED LINKS

[Editing Tempo and Time Signature](#) on page 892

Defining the Default Track Time Base (Cubase Pro only)

You can specify the default track time type for new tracks (audio, group/FX, MIDI, and marker tracks).

PROCEDURE

1. In the **Preferences** dialog, select **Editing**.
2. Open the **Default Track Time Type** pop-up menu and select a default track time type.



RESULT

If you selected **Follow Transport Main Display**, the primary time format setting on the Transport panel is used. When this is set to **Bars+Beats**, tracks with musical time base are added. When this is set to any of the other options (Seconds, Timecode, Samples, etc.), all new tracks use linear time base.

RELATED LINKS

[Default Track Time Type](#) on page 1013

TrackVersions

TrackVersions allow you to create and manage multiple versions of events and parts on the same track.

TrackVersions are available for audio, MIDI, and instrument tracks. You can also have TrackVersions of the chord track, the signature track, and the tempo track.

TrackVersions are useful for the following tasks:

- Starting new recordings from scratch.
- Comparing different takes and comps.
- Managing takes that were recorded in a multi-track recording.

NOTE

TrackVersions are not available for automation tracks.

TrackVersions are included in track archives and project backups.

The TrackVersion key commands can be found in the **TrackVersions** category of the **Key Commands** dialog.

TrackVersions Pop-Up Menu

The **TrackVersions** pop-up menu is available for all track types that support TrackVersions. It contains the most important functions for managing TrackVersions and a TrackVersions list.

To open the **TrackVersions** pop-up menu for a track, click the arrow to the right of the track name.



The following options are available:

TrackVersion List

Lists all TrackVersions of the track for which you opened the **TrackVersions** pop-up menu and allows you to activate a TrackVersion.

New Version

Creates a new, empty TrackVersion for the selected tracks.

Duplicate Version

Creates a copy of the active TrackVersion for the selected tracks.

Rename Version

Opens a dialog that allows you to change the TrackVersion name for the selected tracks.

Delete Version


Deletes the active TrackVersion for the selected tracks.

Select Tracks with Same Version ID

Selects all tracks that have a TrackVersion with the same ID.

TrackVersions Section

The **TrackVersions** section in the **Inspector** allows you to view and manage TrackVersions for a selected track. It is available for audio tracks, MIDI tracks, instrument tracks, and the chord track.



To open the **TrackVersions** section for a track, select the track, and in the **Inspector**, click the **TrackVersions** section.

1 Name column

Shows the version name. Double-click to change it. The name will be changed for all selected tracks.

2 ID column

Shows the TrackVersion ID.

3 Track Version Indicator

Indicates that more than one TrackVersion exists.

4 Track Version list

Lists all TrackVersions and allows you to activate one of them for all selected tracks.

5 New Version

Creates a new, empty TrackVersion for all selected tracks.

6 Duplicate Version

Creates a copy of the active TrackVersion for all selected tracks.

7 Delete Version

Deletes the active TrackVersion for all selected tracks. This function is only available if the track has more than one TrackVersion.

Creating New TrackVersions

You can create new, empty TrackVersions for selected tracks.

PROCEDURE

1. In the track list, select the tracks for which you want to create a new TrackVersion.
2. Select **Project > TrackVersions > New Version**.

NOTE

You can also use the **TrackVersions** section in the **Inspector** (only available for audio tracks, MIDI tracks, instrument tracks, and the chord track) or the **TrackVersions** pop-up menu in the track list to create a new TrackVersion.

RESULT

The event display shows a new, empty TrackVersion. Events of previous TrackVersions are hidden. The track list shows a default version name.

TrackVersion IDs

All TrackVersions are automatically assigned an ID. TrackVersions that are created together get the same TrackVersion ID and can be selected together.

In the **TrackVersions** section in the **Inspector**, the TrackVersion ID is shown in the **ID** column of the TrackVersion list.

In the track list, you can open the **TrackVersions** pop-up menu to see the TrackVersion ID.

Selecting Tracks by TrackVersion ID

You can simultaneously select all tracks that share the same TrackVersion ID.

PROCEDURE

1. Activate the TrackVersion.
2. Select **Project > TrackVersions > Select Tracks with same Version ID**.

RESULT

All tracks that have TrackVersions with the same ID are selected.

Assigning a Common ID

TrackVersions on different tracks that were not created together have different TrackVersion IDs. TrackVersions with different IDs cannot be activated together. To do this, you must assign a new version ID to these tracks.

PROCEDURE

1. Select the tracks and activate the TrackVersions to which you want to assign a common version ID.
2. Select **Project > TrackVersions > Assign Common Version ID**.

RESULT

A new ID is assigned to all active TrackVersions on the selected tracks. The tracks are now marked as belonging together. You can now activate them together.


Active TrackVersion

If you created more than one TrackVersion for a track, you can show the events of a specific TrackVersion in the event display. This process is referred to as activating TrackVersions.

Activating TrackVersions

PROCEDURE

1. Click the arrow to the right of the track name to open the **TrackVersions** pop-up menu.



2. Select the TrackVersion that you want to activate.
-

RESULT

The selected version is activated and its events are shown in the event display.

NOTE

If you work with audio tracks, MIDI tracks, instrument tracks, or the chord track, you can also use the **TrackVersions Inspector** to activate a TrackVersion.

Activating TrackVersions on Multiple Tracks

You can simultaneously activate TrackVersions on multiple tracks if these TrackVersions share the same ID.

PROCEDURE

1. Select all tracks for which you want to activate a specific TrackVersion.
 2. Click the arrow to the right of the track name to open the **TrackVersions** pop-up menu.
 3. Select the TrackVersion that you want to activate from the list.
-

RESULT

The selected TrackVersion is activated for all selected tracks, and the corresponding events are shown in the event display.

NOTE

If you work with audio tracks, MIDI tracks, instrument tracks, or the chord track, you can also use the **TrackVersions Inspector** to activate a TrackVersion.

Duplicating TrackVersions

You can duplicate a TrackVersion by creating a new TrackVersion that contains a copy of the active TrackVersion.

PROCEDURE

1. In the track list, select the tracks and activate the TrackVersion that you want to duplicate.
2. Select **Project > TrackVersions > Duplicate Version**.
In the event display, a duplicate TrackVersion is displayed. In the track list, a default version name for the duplicate is shown.

NOTE

You can also use the **TrackVersions Inspector** for audio tracks, MIDI tracks, instrument tracks, and chord tracks or the **TrackVersions** pop-up menu in the track list to duplicate a TrackVersion.

Deleting TrackVersions

PROCEDURE

1. Select the tracks and activate the TrackVersions that you want to delete.
2. Select **Project > TrackVersions > Delete Version**.

NOTE

You can also use the **TrackVersions Inspector** for audio tracks, MIDI tracks, instrument tracks, and chord tracks or the **TrackVersions** pop-up menu in the track list to delete the active TrackVersion for selected tracks.

Copying and Pasting Selection Ranges Between TrackVersions

You can copy and paste ranges between different TrackVersions, even across multiple tracks.

PREREQUISITE

You have at least 2 TrackVersions.

PROCEDURE

1. Select the **Range Selection** tool.
 2. Select a range of the TrackVersion that you want to copy.
 3. Select **Edit > Copy**.
 4. Activate the TrackVersion into which you want to insert the copied range.
 5. Select **Edit > Paste**.
-

RESULT

The copied range from the first TrackVersion is pasted to the second TrackVersion at the exact same position.

NOTE

If you want to perform more complicated comping tasks, we recommend to select **Project > TrackVersions > Create Lanes from Versions** and proceed with the **Comp** tool.

Copying and Pasting Selected Events between TrackVersions

You can copy and paste selected events between different TrackVersions, even across multiple tracks.

PREREQUISITE

You have at least 2 TrackVersions, and you have split the corresponding events with the **Cut** tool, for example.

PROCEDURE

1. Select the **Object Selection** tool.
2. Select the events that you want to copy.
3. Select **Edit > Copy**.
4. Activate the TrackVersion into which you want to insert the copied events.
5. Select **Edit > Functions > Paste at Origin**.

This ensures that the events are inserted at the exact same position.

RESULT

The copied events from the first TrackVersion are pasted to the second TrackVersion at the exact same position.

TrackVersion Names

Each TrackVersion has a default TrackVersion name.


If more than one version is available for the track, the TrackVersion name is shown in the track list and in the **TrackVersions** section in the **Inspector**. By default, TrackVersions are named v1, v2, etc. However, you can rename each TrackVersion to your liking.

Renaming a TrackVersion

PROCEDURE

- In the **TrackVersions** section in the **Inspector**, double-click the TrackVersion name and enter a new name.


The name is changed. If the available space in the track list is too small, the name is abbreviated automatically.



Renaming TrackVersions on Multiple Tracks

PROCEDURE

1. Activate all TrackVersions that you want to rename, and select the corresponding tracks.
2. Select **Project > TrackVersions > Rename Version**.
3. Enter a new TrackVersion name and click **OK**.



RESULT

In the track list, the new TrackVersion name is shown.



NOTE

If you want to assign the same ID to TrackVersions, select **Project > TrackVersions > Assign Common Version ID**.

TrackVersions vs. Lanes

TrackVersions and lanes are individual features that complement each other. Every TrackVersion can have its own set of lanes.

Creating Lanes from TrackVersions

If your project contains TrackVersions and you want to continue working with lanes, using the **Comp** tool, for example, you can create lanes from TrackVersions.

PROCEDURE

1. Select the tracks for which you want to create lanes.
 2. Select **Project > TrackVersions > Create Lanes from Versions**.
A new TrackVersion named **Lanes from Version** is added. This TrackVersion contains all TrackVersions on separate lanes. The original TrackVersions are kept. Lanes that you create from MIDI TrackVersions are muted.
 3. In the track list or in the **Inspector**, activate the **Show Lanes** button for the track.
 4. On the **Project** window toolbar, activate the **Comp** tool and continue as usual.
-

Creating TrackVersions from Lanes

If your project contains lanes and you want to continue working with the TrackVersion functions, you can create TrackVersions from lanes.

PROCEDURE

1. Select the tracks for which you want to create TrackVersions.
If you only want to convert specific lanes, select these lanes.
 2. Select **Project > TrackVersions > Create Versions from Lanes**.
-

RESULT

New TrackVersions are added, one for each separate lane. The original lanes are kept. Any crossfades that you have created between different lanes are discarded.

Track Presets

Track presets are templates that can be applied to newly created or existing tracks of the same type.

You can create them from virtually all track types (audio, MIDI, instrument, sampler, group, FX, VST instrument return, input, and output channels). They contain sound and channel settings, and allow you to quickly browse, preview, select, and change sounds, or reuse channel settings across projects.

Track presets are organized in the **MediaBay**. There, you can categorize them with attributes.

Audio Track Presets

Track presets for audio tracks, group tracks, FX tracks, VST instrument channels, input channels, and output channels include all settings that define the sound.

You can use the factory presets as a starting point for your own editing and save the audio settings that you optimized for an artist that you often work with as a preset for future recordings.

The following data is saved in audio track presets:

- Insert effects settings (including VST effect presets)
- EQ settings
- Volume and pan
- Input gain and phase

NOTE

To access the track presets functions for input and output channels, activate the **Write** buttons for input and output channels in the MixConsole. This creates input and output channel tracks in the track list.

Instrument Track Presets

Instrument track presets offer both MIDI and audio features and are the best choice when handling sounds of simple, mono-timbral VST instruments.

Use instrument track presets for auditioning your tracks or saving your preferred sound settings, for example. You can also extract sounds from instrument track presets for use in instrument tracks.

The following data is saved in instrument track presets:

- Audio insert effects
- Audio EQ
- Audio volume and pan
- Audio input gain and phase
- MIDI insert effects
- MIDI track parameters
- Input Transformer settings
- The VST instrument used for the track
- Staff settings
- Color settings
- Drum map settings

MIDI Track Presets

You can use MIDI track presets for multi-timbral VST instruments. You can also use them for external instruments.

When creating MIDI track presets you can either include the channel or the patch.

- To ensure that saved MIDI track presets for external instruments will work again with the same instrument, install the instrument as a MIDI device, see the separate document **MIDI Devices**.

The following data is saved in MIDI track presets:

- MIDI modifiers (Transpose, etc.)
- MIDI insert effects
- Output and Channel or Program Change
- Input Transformer settings
- Volume and pan
- Staff settings
- Color settings
- Drum map settings

Multi-Track Presets

You can use multi-track presets, for example, when recording setups that require several microphones (a drum set or a choir, where you always record under the same conditions) and you have to edit the resulting tracks in a similar way. Furthermore, they can be used when working with layered tracks, where you use several tracks to generate a certain sound instead of manipulating only one track.

If you select more than one track when creating a track preset, the settings of all selected tracks are saved as one multi-track preset. Multi-track presets can only be applied if the target tracks are of the same type, number, and sequence as the tracks in the track preset, therefore, they should be used in recurring situations with similar tracks and settings.

Sampler Track Presets

You can use sampler track presets to re-use created sounds in later projects or newly created sampler tracks.

The following data is saved in sampler track presets:

- Audio insert effects
- Audio EQ
- Audio volume and pan
- Audio input gain and phase
- MIDI insert effects
- MIDI track parameters
- Input Transformer settings
- Color settings

VST Presets

VST instrument presets behave like instrument track presets. You can extract sounds from VST presets for use in instrument tracks.

The following data is saved in VST instrument presets:

- VST instrument
- VST instrument settings

NOTE

Modifiers, inserts, and EQ settings are not saved.

VST effect plug-ins are available in VST 3 and VST 2 format.

NOTE

In this manual, VST presets stands for VST 3 instrument presets, unless stated otherwise.

Pattern Banks

Pattern banks are presets that are created for the Beat Designer MIDI effect.

They behave much like track presets.

RELATED LINKS

[Previewing Pattern Banks](#) on page 565

[Track Presets](#) on page 179

Creating a Track Preset

You can create a track preset from a single track or from a combination of tracks.

PROCEDURE

1. In the **Project** window, select one or more tracks.
2. In the track list, right-click one of the selected tracks and select **Save Track Preset**.
3. In the **New Preset** section, enter a name for the new preset.

NOTE

You can also define attributes for the preset.

4. Click **OK** to save the preset and exit the dialog.
-

RESULT

Track presets are saved within the application folder in the Track Presets folder. They are saved in default subfolders named according to their track type: audio, MIDI, instrument, and multi.

RELATED LINKS

[Attribute Inspector](#) on page 570

Creating a Sampler Track Preset

You can create a sampler track preset from a sampler track or you can use the **Sampler Control** toolbar.

PROCEDURE

1. In the **Sampler Control** toolbar, click **Preset Management** .
2. Click **Save Track Preset**.
3. In the **Save Track Preset** dialog, type in a name for the new preset.
4. Click **OK** to save the preset and exit the dialog.

RESULT

The new sampler track preset is saved. It is displayed in the **Preset Name** field on the info line. Sampler track presets are saved within the application folder in the sampler track presets folder.

RELATED LINKS

[Creating a Track Preset](#) on page 181

Applying Track Presets

When you apply a track preset, all the settings that are saved in the preset are applied.

Track presets can be applied to tracks of their own type only. The only exception are instrument tracks: for these, VST presets are also available.

NOTE

- Once a track preset is applied, you cannot undo the changes. It is not possible to remove an applied preset from a track and return to the previous state. If you are not satisfied with the track settings, you have to either edit the settings manually or apply another preset.
- Applying VST presets to instrument tracks leads to removal of modifiers, MIDI inserts, inserts, or EQs. These settings are not stored in VST presets.

Loading Track, VST, or Sampler Track Presets

PROCEDURE

1. In the **Project** window, select a track.
2. Do one of the following:
 - In the **Inspector**, click **Load Track Preset**.
 - In the track list, right-click the track and select **Load Track Preset**.
 - In the **Sampler Control** toolbar, click the preset management button next to the preset name field and select **Load Track Preset**.
3. In the preset browser, select a track, VST, or sampler track preset.
4. Double-click the preset to load it.

RESULT

The preset is applied.

NOTE

You can also drag and drop track presets from the **MediaBay**, the File Explorer/macOS Finder onto a track of the same type.

RELATED LINKS

[Filters Section](#) on page 566

Loading Multi-Track Presets

PROCEDURE

1. In the **Project** window, select several tracks.

NOTE

Multi-track presets can only be applied if track type, number, and sequence are identical for the selected tracks and the track preset.

2. In the track list, right-click the track and select **Load Track Preset**.
 3. In the preset browser, select a multi-track preset.
 4. Double-click the preset to load it.
-

RESULT

The preset is applied.

Loading Inserts and EQ from Track Presets

Instead of loading complete track presets, you can also apply insert or equalizer settings from track presets.

PROCEDURE

1. Select a track, open the **Inspector** or the **Channel Settings** window, and click the **VST Sound** button on the **Inserts** or **Equalizers** section.
 2. Select **From Track Preset**.
 3. In the preset browser, select a track preset.
 4. Double-click the preset to load the settings.
-

Extracting the Sound from an Instrument Track or VST Preset

For instrument tracks, you can extract the sound of an instrument track preset or VST preset.

PROCEDURE

1. Select the instrument track to which you want to apply a sound.
 2. In the **Inspector**, click **VST Sound**.
 3. In the preset browser, select an instrument track preset or VST preset.
 4. Double-click the preset to load the settings.
-

RESULT

The VST instrument and its settings (but no inserts, EQs, or modifiers) on the existing track are overwritten with the data of the track preset. The previous VST instrument for this instrument track is removed and the new VST instrument with its settings is set up for the instrument track.


Track Quick Control Presets

For audio, instrument, MIDI, FX, and group tracks, you can save and load your own Quick Control assignments as presets or use the factory presets.

Saving/Loading Track Quick Control Assignments as Presets

PROCEDURE

1. In the **Inspector** for your track, open the **Quick Controls** section.
For instrument tracks, the track quick controls are set to the 8 default VST quick controls of the loaded instrument by default.
2. Click **Preset Management** in the top right corner of the **Quick Controls** section and select one of the presets.



The Track Quick Control assignment changes and gives you access to the channel parameters.

NOTE

You can also make your own assignments and save them as presets and delete, rename, or reset the presets to the default assignments.

Parts and Events

Parts and events are the basic building blocks in Cubase.

Events

In Cubase, most event types can be viewed and edited on their specific tracks in the **Project** window.

Events can be added by importing or recording.

RELATED LINKS

[Audio Events](#) on page 185

[MIDI Events](#) on page 188

Audio Events

Audio events are created automatically when you record or import audio in the **Project** window.

You can view and edit audio events in the **Project** window and in the **Sample Editor**.

An audio event triggers the playback of the corresponding audio clip. By adjusting the **Offset** and the **Length** values of the event, you can determine which section of the audio clip is played back. The audio clip itself remains unchanged.

RELATED LINKS

[Project Window](#) on page 38

[Sample Editor](#) on page 445

[Audio Files and Audio Clips](#) on page 186

[Basic Recording Methods](#) on page 236

Creating Audio Events

PROCEDURE

- Do one of the following:
 - Record some audio.
 - Select **File > Import > Audio File** to import an audio file from your hard disk or any external storage device.
 - Select **File > Import > Audio CD** to import an audio file from an audio CD.
 - Select **File > Import > Audio from Video File** to import the audio from a video file on your hard disk or any external storage device.
 - Drag an audio file from the **MediaBay**, the **Audio Part Editor**, the **Sample Editor** or the **Find Media** window, and drop it in the event display.
 - Copy an event from a different Cubase project and paste it in the event display.
-

RELATED LINKS

- [Basic Recording Methods](#) on page 236
- [Importing Audio Files](#) on page 254
- [Importing Audio CD Tracks](#) on page 257
- [Importing Audio from Video Files](#) on page 259
- [MediaBay](#) on page 546
- [Audio Part Editor](#) on page 503
- [Sample Editor](#) on page 445
- [Find Media Window](#) on page 536

Creating New Files From Events

An audio event plays a section of an audio clip, which in turn refers to one or more audio files on the hard disk. However, you can create a new file that consists only of the section that is played by the event.

PROCEDURE

1. Select one or several audio events.
2. Set up fade in, fade out, and event volume.
These settings will be applied to the new file.
3. Select **Audio > Bounce Selection**.
You are asked whether you want to replace the selected event or not.
4. Do one of the following:
 - To create a new file that only contains the audio in the original event, click **Replace**.
 - To create a new file and add a clip for the new file to the **Pool**, click **No**.

RESULT

If you clicked **Replace**, a clip for the new file is added to the **Pool**, and the original event is replaced by a new event playing the new clip.

If you clicked **No**, the original event is not replaced.

NOTE

You can also apply the **Bounce Selection** function to audio parts. In that case, the audio from all events in the part is combined to a single audio file. If you select **Replace** when asked, the part is replaced with a single audio event playing a clip of the new file.

RELATED LINKS

- [Event-Based Fades](#) on page 278

Audio Files and Audio Clips

In Cubase, audio editing and processing are non-destructive.

When you edit or process audio in the **Project** window, the audio file on the hard disk remains untouched. Instead, your changes are saved to an audio clip that is automatically created on import or during recording, and that refers to the audio file. This allows you to undo changes or revert to the original version.

If you apply processing to a specific section of an audio clip, a new audio file that contains only this section is created. The processing is applied to the new audio file only and the audio clip is automatically adjusted, so that it refers both to the original file and to the new, processed file. During playback, the program will switch between the original file and the processed file at the correct positions. You will hear this as a single recording, with processing applied to one section only.

This allows you to undo processing at a later stage, and to apply different processing to different audio clips that refer to the same original file.

You can view and edit audio clips in the **Pool**.

RELATED LINKS

[Pool](#) on page 527

[Audio Regions](#) on page 187

[Replacing Clips in Events](#) on page 187

Replacing Clips in Events

You can replace the clips in audio events.

PROCEDURE

- Do one of the following:
 - Hold down **Shift**, drag an audio file from the File Explorer/macOS Finder, and drop it on the event.
 - Click a clip in the **Pool**, hold down **Shift**, and drop it on the event.
-

RESULT

The clip in the event is replaced. However, the event edits remain unchanged. If the new clip is shorter than the replaced clip, the length of the event is adapted. If the new clip is longer than the replaced clip, the length of the event stays the same.

RELATED LINKS

[Inserting Clips into a Project Via Drag and Drop](#) on page 532

Audio Regions

Cubase allows you to create audio regions within audio clips to mark important sections in the audio.

You can view audio regions in the **Pool**. You can create and edit them in the **Sample Editor**.

NOTE

If you want to use one audio file in different contexts, or if you want to create several loops from one audio file, convert the corresponding regions of the audio clip to events and bounce them into separate audio files. This is necessary since different events that refer to the same clip access the same clip information.

RELATED LINKS

[Pool](#) on page 527

[Audio Regions](#) on page 187

[Regions List](#) on page 461

Region Operations

Regions are sections within a clip.

Regions are best created and edited in the **Sample Editor**. However, to access the following options, select **Audio > Advanced**.

Event or Range as Region

This function is available when one or several audio events or selection ranges are selected. It creates a region in the corresponding clip, with the start and end position

of the region determined by the start and end position of the event or selection range within the clip.

Events from Regions

This function is available if you have selected an audio event whose clip contains regions within the boundaries of the event. The function will remove the original event and replace it with events positioned and sized according to the regions.

RELATED LINKS

[Creating Audio Events from Regions](#) on page 463

MIDI Events

MIDI events are created automatically when you record or import MIDI in the **Project** window.

The **In-Place Editor** allows you to view and edit MIDI events in the **Project** window. You can also view and edit MIDI events in the **Key Editor**, the **Drum Editor**, **List Editor**, or the **Score Editor**.

RELATED LINKS

[Project Window](#) on page 38

[In-Place Editor](#) on page 785

[Key Editor](#) on page 709

[Drum Editor](#) on page 750

[Basic Score Editor \(Cubase Artist only\)](#) on page 737

[Basic Recording Methods](#) on page 236

Creating MIDI Events

PROCEDURE

- Do one of the following:
 - Record MIDI.
 - Select **File > Import > MIDI File** to import a MIDI file from your hard disk.
 - Drag a MIDI file from the File Explorer/macOS Finder, from one of the MIDI editors, or from the **MediaBay**, and drop it in the event display.
 - Copy an event from a different Cubase project and paste it in the event display.
-

RELATED LINKS

[Basic Recording Methods](#) on page 236

[Importing MIDI Files](#) on page 262

[MIDI Editors](#) on page 702

[MediaBay](#) on page 546

Parts

Parts are containers for MIDI or audio events, and for tracks.

RELATED LINKS

[Audio Parts](#) on page 189

[MIDI Parts](#) on page 189

[Folder Parts](#) on page 189

Audio Parts

Audio parts are containers for audio events. If you want to treat several audio events as one unit in the **Project** window, you can convert them to a part.

You can create audio parts in the following ways:

- Select the **Draw** tool and draw on the audio track.
- Press **Alt**, select the **Object Selection** tool, and draw on the audio track.
- Select the **Object Selection** tool and double-click on the audio track, between the left and right locator.
- Select several audio events on an audio track and select **Audio > Events to Part**.

NOTE

To make the events appear as independent objects on the track again, select the part and select **Audio > Dissolve Part**.

RELATED LINKS

[Audio Part Editor](#) on page 503

MIDI Parts

A MIDI part is automatically created when you record. It contains the recorded events.

However, you can also create empty MIDI parts in the following ways:

- Select the **Draw** tool and draw on the MIDI track.
- Press **Alt**, select the **Object Selection** tool and draw on the MIDI track.
- Select the **Object Selection** tool, and double-click on the MIDI track, between the left and right locator.



Folder Parts

A folder part is a graphic representation of events and parts on the tracks in the folder.

Folder parts indicate the time position as well as the vertical track position. If part colors are used, these are also shown in the folder part.

Any editing that you perform to a folder part affects all the events and parts it contains. Tracks inside a folder can be edited as one entity.

NOTE

If you want to edit the individual tracks within the folder, you can double-click the folder part. This opens the editors for the events and parts that are present on the tracks.

RELATED LINKS

[Coloring Notes and Events](#) on page 703

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Editing Techniques for Parts and Events

This section describes techniques for editing in the **Project** window. If not explicitly stated, all descriptions apply to both events and parts, even though we use the term event for convenience.

In the **Project** window, you can edit events using the following techniques:

- By selecting and using one of the tools in the **Project** window toolbar.

NOTE

Some editing tools feature additional functions if you press modifier keys. You can customize the default modifier keys in the **Preferences** dialog (**Editing—Tool Modifiers** page).

- By opening the **Edit** menu and selecting one of the functions.
- By editing in the info line.
- By using a key command.

NOTE

Snap is taken into account.

RELATED LINKS

[Editing - Tool Modifiers](#) on page 1019

Auditioning Audio Parts and Events

You can audition audio parts and events in the **Project** window by using the **Play** tool.

PROCEDURE

1. Click **Play** .
 2. Click where you want playback to start, and keep the mouse button pressed.
-

RESULT

The track on which you click is played back, starting at the click position. Playback is stopped when you release the mouse button.

NOTE

When auditioning, audio will be routed directly to the **Control Room** (Cubase Pro only) if the **Control Room** is activated. If the **Control Room** is deactivated, the audio is routed to the default output bus, bypassing the audio channel's settings, effects and EQs. In Cubase Artist, the **Main Mix** bus is always used for monitoring.

Scrubbing

The **Scrub** tool allows you to locate positions in events by playing back, forwards or backwards.

PROCEDURE

1. Click **Play** .
2. Click **Play** again to open a pop-up menu.
3. Select **Scrub** .
4. Click the event and keep the mouse button pressed.

5. Drag to the left or right.
-

RESULT

The project cursor moves correspondingly and the event is played back. The speed and the pitch of the playback depend on how fast you move the mouse.

NOTE

Insert effects are bypassed when scrubbing with the mouse.

Scrub Tool

Scrubbing can be quite a burden on your system. If playback problems occur, open the **Preferences** dialog (**Transport—Scrub** page), and deactivate **Use High Quality Scrub Mode**. This lowers the resampling quality, but makes scrubbing less demanding on the processor, especially in large projects.

In the **Preferences** dialog (**Transport—Scrub** page), you can also adjust the **Scrub** volume.

Selecting with the Object Selection Tool

PROCEDURE

1. Click **Object Selection** .
2. In the event display, click the events that you want to select.

NOTE

You can also use the **Up Arrow**, **Down Arrow**, **Left Arrow**, **Right Arrow** keys on the computer keyboard to select the event on the upper or lower track or the previous or next event on the same track.

Select Submenu

If the **Object Selection** tool is selected, the **Select** submenu features specific options for selecting events in the **Project** window.

- To open the **Select** submenu, select **Edit > Select**.

All

Selects all events in the **Project** window.

None

Deselects all events.

Invert

Inverts the selection. All selected events are deselected and all events that were not selected are selected instead.

In Loop

Selects all events that are partly or wholly between the left and right locator.

From Start to Cursor

Selects all events that begin to the left of the project cursor.

From Cursor to End

Selects all events that end to the right of the project cursor.

Equal Pitch all Octaves/same Octave

These functions are available in the MIDI editors and the **Sample Editor**.

Select Controllers in Note Range

This function is available in the MIDI editors.

All on Selected Tracks

Selects all events on the selected track.

Events under Cursor

Automatically selects all events on the selected tracks that are touched by the project cursor.

Select Event

This function is available in the **Sample Editor**.

Left/Right Selection Side to Cursor

These functions are only used for range selection editing.

NOTE

When the **Range Selection** tool is selected, the **Select** submenu features different functions.

RELATED LINKS

[Selection Range Options](#) on page 204
[Range Editing](#) on page 457

Removing Events

PROCEDURE

- To remove an event from the **Project** window, do one of the following:
 - Select **Erase**  and click the event.
 - Select the events and select **Edit > Delete**.
 - Select the events and press **Backspace**.
-

Move Events

You can move events using any of the following methods:

- Use the **Object Selection** tool.
- Use **Nudge** tool.
- Select **Edit > Move to** and select one of the options.
- Select the event and edit the start position on the info line.

RELATED LINKS

[Moving with the Object Selection Tool](#) on page 193
[Moving with the Nudge Buttons](#) on page 193
[Move to Submenu](#) on page 193
[Moving via the Info Line](#) on page 193

Moving with the Object Selection Tool

PROCEDURE

1. Select **Object Selection** .
2. Click the events that you want to move and drag them to a new position.

NOTE

You can only drag events to tracks of the same type. If you hold down **Ctrl/Cmd** while dragging, you can restrict the movement either horizontally or vertically.

RESULT

The events are moved. If you moved several events, their relative positions are kept.

NOTE

To avoid accidentally moving events when you click them in the **Project** window, the response when you move an event by dragging is slightly delayed. You can adjust this delay with the **Drag Delay** setting in the **Preferences** dialog (**Editing** page).

Moving with the Nudge Buttons

PROCEDURE

1. Right-click the **Project** window toolbar and activate **Nudge Palette**.
The nudge buttons become available on the toolbar.

 2. Select the events that you want to move, and click **Move Left**  or **Move Right** .
- The selected events or parts are moved.
-

Move to Submenu

If the **Object Selection** tool is selected, the **Move to** submenu features options for moving events to specific positions in the **Project** window.

- To open the **Move to** submenu, select **Edit > Move to**.

The following options are available:

Cursor

Moves the selected event to the project cursor position. If you selected several events on the same track, the following events keep their relative position.

Origin

Moves the selected events to the positions at which they were originally recorded.

Front/Back

Moves the selected events to the front or back, respectively. This is useful if you have overlapping audio events and you want to play back an other event.

Moving via the Info Line

PROCEDURE

1. Select the event that you want to move.
2. On the info line, double-click the **Start** field and enter a new value for the event start.


RESULT

The event is moved by the set value.

Renaming Events

PROCEDURE

- Do one of the following:
 - Select the events and type in a new name in the **File** field on the info line.



- Change the track name, hold down a modifier key, and press **Return** to rename all events after the track.
-

Resize Events

You can resize events by moving their start or end positions individually.

To resize events, you can use the **Object Selection**, the **Trim**, or the **Scrub** tools.

IMPORTANT

When resizing events, automation data is not taken into account.

RELATED LINKS

- [Resizing Events with the Object Selection Tool - Normal Sizing](#) on page 194
- [Resizing Events with the Object Selection Tool - Sizing Moves Contents](#) on page 195
- [Resizing Events with the Object Selection Tool - Sizing Applies Time Stretch](#) on page 195
- [Resizing Events with the Trim Tool](#) on page 195
- [Resizing Events with the Scrub Tool](#) on page 196
- [Snap Function](#) on page 78

Resizing Events with the Object Selection Tool - Normal Sizing

You can move the start or end point of the event without changing the content of the event.

PROCEDURE

1. Select **Object Selection** .
2. Click the **Object Selection** tool again, and select **Normal Sizing** from the pop-up menu.
3. Click and drag the lower left or right corner of the event.



RESULT


The event is resized and according to where you dragged, more or less of the content is revealed. If several events are selected, they are all resized in the same way.

Resizing Events with the Object Selection Tool - Sizing Moves Contents

You can move the start or end point of the event and move the content.

PROCEDURE

1. Select **Object Selection** .
2. Click the **Object Selection** tool again, and select **Sizing Moves Contents** from the pop-up menu.
3. Click and drag the lower left or right corner of the event.



RESULT

The event is resized and the content follows. If several events are selected, they are all resized in the same way.

Resizing Events with the Object Selection Tool - Sizing Applies Time Stretch

You can move the start or end point of the event and time stretch the content to fit the new event length.

PROCEDURE

1. Select **Object Selection** .
2. Click the **Object Selection** tool again, and select **Sizing Applies Time Stretch** from the pop-up menu.
3. Click and drag the lower left or right corner of the event.

RESULT

The part is stretched or compressed to fit the new length.

- If you resize MIDI parts, the note events are stretched (moved and resized). Controller data and Note Expression data are stretched, too.
- If you resize audio parts, the events are moved, and the referenced audio files are time stretched to fit the new length.
If several events are selected, they are all resized in the same way.

RELATED LINKS

[Time Stretch](#) on page 431

Resizing Events with the Trim Tool

You can move the start or end point of the event by the amount set on the **Grid Type** pop-up menu.

PREREQUISITE

The **Object Selection** tool is set to **Normal Sizing** or to **Sizing Moves Contents**.

PROCEDURE

1. Right-click the **Project** window toolbar and activate **Nudge Palette**.
The nudge buttons become available on the toolbar.



2. Select the event.
 3. Do one of the following:
 - Click **Trim Start Left** .
 - Click **Trim Start Right** .
 - Click **Trim End Left** .
 - Click **Trim End Right** .
-

RESULT

The start or end position of the selected events are moved by the amount set on the **Grid Type** pop-up menu.

Resizing Events with the Scrub Tool

You can scrub the event when moving the start or end point of the event.

PROCEDURE

1. Click **Play** .
 2. Click **Play** again to open a pop-up menu.
 3. Select **Scrub** .
 4. Click and drag the lower left or right corner of the event.
-

RESULT

The event is resized and you get an acoustic feedback while dragging.

Splitting Events

PROCEDURE

- Do one of the following:
 - Select **Split**  and click the event that you want to split.
 - Select **Object Selection** , hold down **Alt** and click the event.
 - Move the project cursor to the position where you want to split the events, and select **Edit > Functions > Split at Cursor**.

NOTE

This splits the selected events at the position of the project cursor. If no events are selected, all events on all tracks that are intersected by the project cursor are split.

- Set up the left and right locators at the position where you want to split the events, and select **Edit > Functions > Split Loop**.

NOTE

This splits the selected events at the left and right locator positions. If no events are selected, all events on all tracks that are intersected by the locators are split.

RESULT

The events are split.

NOTE

If you split a MIDI part so that the split position intersects one or several MIDI notes and **Split MIDI Events** is activated in the **Preferences** dialog (**Editing—MIDI** page), the intersected notes are split and new notes are created at the beginning of the second part. If it is deactivated, the notes remain in the first part, but stick out after the end of the part.

RELATED LINKS

[Splitting Events Repeatedly](#) on page 197

Splitting Events Repeatedly

You can split events repeatedly into multiple equal-sized events.

PROCEDURE

- Select **Split** , hold down **Alt** and click the event where you want to split it first.
-

RESULT

The event is automatically split into as many equal events as the length of the original event allows.

Gluing Events

In the **Project** window, you can glue two or more events that are situated on the same track.

PROCEDURE

- Do one of the following:
 - Select **Glue**  and click the event that you want to glue to the next event.
 - Select **Glue** , hold down **Alt**, and click the event that you want to glue to all following events.
-

RESULT

The events are glued together.

NOTE

If you first split an audio event and then glue the parts together again, an event is created, in any other case, a part is created.

Pasting Events

You can paste events from the clipboard.

PROCEDURE

- Do one of the following:
 - Select the events and select **Edit > Functions > Paste at Origin** to paste the event at the same position from which you cut or copied it.
 - Select the events, select the track where you want to paste them, and select **Edit > Functions > Paste Relative to Cursor** to paste the event while keeping its relative position to the project cursor.
-

RESULT

If you paste an audio event, it is inserted on the selected track, positioned so that its snap point is aligned with the cursor position.

If the selected track is of the wrong type, the event is inserted on its original track.

Pasting Events To Matching Track Names

You can copy events in one project and paste them at the first track that matches the exact track name in another project.

PROCEDURE

1. Copy the events in one project.
2. Activate the project where you want to paste the events.
3. Select **Edit > Functions > Paste to Matching Track Name**.

RESULT

The events are inserted on the track with the name that exactly matches the original track name. For all events that have no matching track name, new tracks are created.

Duplicating Events

In the **Project** window, you can duplicate selected events.

PROCEDURE

- Select the event and do one of the following:
 - Select **Edit > Functions > Duplicate**.
 - Hold down **Alt** and drag the event to a new position.

NOTE

If you hold down **Ctrl/Cmd** as well, movement direction is restricted to either horizontal or vertical.

RESULT

A copy of the selected event is created and placed after the original. If several events are selected, all of these are copied as one unit, maintaining the relative distance between the events.

NOTE

If you duplicate audio events, the copies always refer to the same audio clip.

Repeating Events

PROCEDURE

- Do one of the following:
 - Select the events and select **Edit > Functions > Repeat** to open the **Repeat Events** dialog, that allows you to create a number of real or shared copies of the selected events.
 - Select the events, hold down **Alt**, click the handle in the lower right corner of the last selected event, and drag to the right to create a real copy.

- Move the mouse pointer over the middle of the right event border so that it becomes a pointing hand symbol, click and drag to the right to create a real copy.
- Select the events, hold down **Alt-Shift**, and drag to the right to create a shared copy.
- Move the mouse pointer over the middle of the right event border so that it becomes a pointing hand symbol, hold down **Shift**, click and drag to the right to create a shared copy.

NOTE

Repeating by dragging only works if the track has a height of at least 2 rows.


RELATED LINKS

- [Shared Copies](#) on page 199
- [Repeat Events Dialog](#) on page 199
- [Setting the Track Height](#) on page 162

Repeat Events Dialog

The **Repeat Events** dialog allows you to create a number of real or shared copies of the selected events.

- To open the **Repeat Events** dialog, select **Edit > Functions > Repeat**.



Count

Allows you to specify how many times you want the event to be repeated.

Shared Copies

Activate this to create a shared copy.

RELATED LINKS

- [Shared Copies](#) on page 199

Shared Copies

Shared copies are useful if you want to create copies that are automatically edited in the same way as the original event.

You can convert a shared copy to a real copy by selecting **Edit > Functions > Convert to Real Copy**. This creates a new version of the clip that you can edit independently. The new clip is automatically added to the **Pool**.

RELATED LINKS

- [Repeating Events](#) on page 198
- [Repeat Events Dialog](#) on page 199

Fill Loop

You can create a number of copies between the right and left locators.

- Select **Edit > Functions > Fill Loop** to create a number of copies starting at the left locator and ending at the right locator.

The last copy is automatically shortened to end at the right locator position.

Sliding the Contents of Events

You can move the contents of an event without changing its position in the **Project** window.

PROCEDURE

- Hold down **Alt-Shift**, click the event, and drag to the left or right.

RESULT

The content of the event is moved.

NOTE

You cannot slide an audio event past the start or end of the actual audio clip. If the event plays the whole clip, you cannot slide the audio at all.

Grouping Events

You can treat several events on the same or different tracks as one unit by grouping them.

PROCEDURE

- Select the events and select **Edit > Group**.

RESULT

The events are grouped. This is indicated by an icon.



Grouped Events

If you edit one of the grouped events in the **Project** window, all other events in the same group are affected too.

Group editing operations include:

- Selecting events.
- Moving and duplicating events.
- Resizing events.
- Adjusting fade-in and fade-out (audio events only).
- Splitting events.
- Locking events.
- Muting events.
- Deleting events.

RELATED LINKS

[Fades, Crossfades, and Envelopes](#) on page 278

Group Editing Mode (Cubase Pro only)

The **Group Editing** mode for folder tracks allows you to edit parts and events in a folder as a group.

If **Group Editing**  is activated and you select an event, a part or a range on a track inside the folder track, other events, parts, or ranges that have the same start and end time and the same playback priority, are also selected and temporarily grouped. This allows you to edit together different drum tracks for bass drum, snare, toms, for example.

Temporarily means that on every new selection with the **Object Selection** or the **Range Selection** tool, Cubase looks for corresponding events or parts inside the folder and groups them. If you edit the start or end point of a single event or part before activating the **Group Editing** mode, the event or part is excluded from the group.

Edit actions in **Group Editing** mode affect all grouped events, parts, or ranges. If you select another take by using the small **To Front** arrow at the right side of one event of an edit group, for example, all other tracks inside the edit group also switch to the corresponding take. This is useful for comparing takes of a multi-track recording.

NOTE

Group Editing overwrites any regular group settings in the edit group.

RELATED LINKS

[Muting Events](#) on page 202

[Organizing Tracks in Folder Tracks](#) on page 164

Group Editing (Cubase Pro only)

You can group events and parts on multiple tracks that have the same start and end time and the same playback priority to edit them together.

PREREQUISITE

PROCEDURE

1. Select **Project > Add Track > Folder** to add a folder track.
2. Move the tracks that contain the events that you want to edit as a group into the folder track.
3. In the track list for the folder track, click **Group Editing** .



RESULT

All events, parts, or ranges inside the folder that have the same start and end time and the same playback priority are temporarily grouped.

Locking Events

If you want to make sure that you do not edit or move an event by accident, you can lock it.

PROCEDURE

- Do one of the following:
 - Select the events and select **Edit > Lock** to lock the selected events.
 - Click the padlock symbol in the track list or in the Inspector to lock all events on a track.
-

RESULT

The events are locked. This is indicated by a padlock symbol.




To unlock an event, select the event and select **Edit > Unlock**.

Lock Event Attributes

The **Lock Event Attributes** dialog allows you to lock specific event attributes.

- To open the **Lock Event Attributes** dialog, select a locked event and select **Edit > Lock**.



- **Position Locked**
Activate this to prevent the event from being moved.
- **Size Locked**
Activate this to prevent the event from being resized.
- **Others Locked**
Activate this to prevent the event from being edited. This includes adjusting the fades and event volume, processing, etc.

NOTE

You can also set these attributes in the **Preferences** dialog (**Editing** page).

RELATED LINKS

[Lock Event Attributes](#) on page 1014

Muting Events

You can mute events in the **Project** window. Muted events can be edited as usual (with the exception of adjusting fades), but are not played back.

PROCEDURE

- Do one of the following:
 - Select **Mute**  and click the events or drag a selection rectangle around them.

- Select the events and select **Edit > Mute**.
-

RESULT

The events are muted and grayed out.




You can unmute events by selecting them and selecting **Edit > Unmute**. You can change the mute status of selected events by **Shift**-clicking them.

Range Editing

Editing in the **Project** window is not restricted to handling whole events and parts. You can also work with selection ranges, which are independent from the event/part and track boundaries.

Creating a Selection Range

- To make a selection range, drag with the **Range Selection** tool.



When the Range Selection tool is selected, you can select selection ranges options via **Edit > Select**.

- To create a selection range that encompasses an event, double-click on an event with the **Range Selection** tool.
- To create a selection range that encompasses several events, hold down **Shift** and double-click several events in a row.
- To open an encompassed event for editing in the **Sample Editor**, double-click it.

RELATED LINKS

[Selection Range Options](#) on page 204

Selection Range Options

If the **Range Selection** tool is selected, the **Select** submenu features specific options for selecting ranges in the **Project** window.

- To open the range selection options menu, select the **Range Selection** tool and select **Edit > Select**.

All

Makes a selection that covers all tracks, from the start of the project to the end. You can define the track length with the **Length** setting in the **Project Setup** dialog.

None

Removes the current selection range.

Invert

Inverts the selection. All selected events are deselected, and all events that were not selected are selected. Only used for event selection.

In Loop

Makes a selection between the left and right locator on all tracks.

From Start to Cursor

Makes a selection on all tracks, from the start of the project to the project cursor.

From Cursor to End

Makes a selection on all tracks, from the project cursor to the end of the project.

Equal Pitch - all Octaves

This function requires that a single note is selected. It selects all notes of this part that have the same pitch in any octave as the selected note.

Equal Pitch - same Octave

This function requires that a single note is selected. It selects all notes of this part that have the same pitch and the same octave as the selected note.

Select Controllers in Note Range

Selects the controllers within the note range.

All on Selected Tracks

Selects all events on the selected track. Only used for event selection.

Events under Cursor

Selects all events on the selected tracks that are touched by the project cursor.

Select Event

This is available in the **Sample Editor**.

Left Selection Side to Cursor

Moves the left side of the current selection range to the project cursor position.

Right Selection Side to Cursor

Moves the right side of the current selection range to the project cursor position.

RELATED LINKS

[Project Setup Dialog](#) on page 87

[Selecting with the Object Selection Tool](#) on page 191

[Select Submenu](#) on page 191

Selecting Ranges for Several Tracks

You can create selection ranges that cover several tracks. It is also possible to exclude tracks from a selection range.

PROCEDURE

1. Create a selection range from the first to the last track.
 2. Press **Ctrl/Cmd** and click in the selection range on the tracks that you want to exclude from the selection.
-

Editing Selection Ranges

Adjusting the Size of Selection Ranges

You can adjust the size of a selection range in the following ways:

- By dragging its edges.
The pointer takes the shape of a double arrow when you move it over an edge of the selection range.
- By holding down **Shift** and clicking.
The closest selection range edge will be moved to the position at which you clicked.

- By adjusting the selection range start or end position on the info line.
- By using the trim buttons on the toolbar.
The left trim buttons move the start of the selection range and the right buttons move the end. The edges are moved by the amount specified on the **Grid** pop-up menu.

NOTE

The trim buttons are located on the **Nudge Palette**, which is not visible on the toolbar by default.

- By using **Move Left** and **Move Right** on the toolbar.
These move the whole selection range to the left or the right. The amount of movement depends on the selected display format and the value specified on the **Grid** pop-up menu.

IMPORTANT

The contents of the selection are not moved. Using **Move Left/Move Right** is the same as adjusting the start and end of the selection range at the same time by the same amount.

NOTE

The move buttons are located on the **Nudge Palette**, which is not visible on the toolbar by default.

- To crop all events or parts that are partially within the selection range, select **Edit > Range > Crop**.
Events that are fully inside or outside the selection range are not affected.

RELATED LINKS

[Setup Context Menus](#) on page 994

Moving and Duplicating Selection Ranges

- To move a selection range, click and drag it to a new position.
This will move the contents of the selection range to the new position. If the range intersected events or parts, these are split before moving, so that only the sections within the selection range are affected.
- To duplicate a selection range, hold down **Alt** and drag.
You can also use the duplicate, repeat, and fill loop functions that are available for duplicating events.

RELATED LINKS

[Duplicating Events](#) on page 198

Cutting, Copying, and Pasting Selection Ranges

You can cut or copy and paste selection ranges, using the functions on the **Edit** menu. You can also use the **Cut Time** and **Paste Time** options.

Cut

Cuts out the data in the selection range and moves it to the clipboard. The selection range is replaced by empty track space in the **Project** window, meaning that events to the right of the range keep their positions.

Copy

Copies the data in the selection range to the clipboard.

Paste

Pastes the clipboard data to the start position and track of the current selection. Existing events on the tracks remain at their original position.

Paste at Origin

Pastes the clipboard data back at its original position. Existing events on the tracks remain at their original position.

This option is available in **Edit > Functions**.

Cut Time

Cuts out the selection range and moves it to the clipboard. Events to the right of the removed range are moved to the left to fill the gap.

This option is available in **Edit > Range**.

Paste Time

Pastes the selection range from the clipboard to the start position and track of the current selection. Existing events are moved to make room for the pasted data.

This option is available in **Edit > Range**.

Paste Time at Origin

Pastes the selection range from the clipboard to its original position. Existing events are moved to make room for the pasted data.

This option is available in **Edit > Range**.

Global Copy

Copies everything between the left and right locator.

This option is available in **Edit > Range**.

Deleting Data in Selection Ranges

- To replace data within the deleted selection range with empty track space, select **Edit > Delete** or press **Backspace**.
Events to the right of the range keep their position.
- To remove the selection range and make the events to the right move to the left to fill the gap, select **Edit > Range > Delete Time**.

Splitting Selection Ranges

- To split any events or parts that are intersected by the selection range, at the positions of the selection range edges, select **Edit > Range > Split**.

Inserting Silence

You can insert empty track space from the start of the selection range. The length of the silence equals the length of the selection range.

- To insert silence, select **Edit > Range > Insert Silence**.
Events to the right of the selection range start are moved to the right to make room. Events that are intersected by the selection range start are split, and the right section is moved to the right.

Playback and Transport

Cubase offers multiple methods and functions to control playback and transport.

RELATED LINKS

[Transport](#) on page 1035

Transport Panel

The **Transport** panel contains the main transport functions as well as many other options related to playback and recording.

- To show the transport panel, select **Transport > Transport Panel** or press **F2**.

Transport Panel Sections

The **Transport** panel has different sections that you can show or hide by activating the corresponding options on the transport panel context menu.

- To show all **Transport** panel sections, right-click anywhere on the **Transport** panel and select **Show All**.

The following sections are available:

Performance




Shows the audio processing load and the hard disk transfer rate.

Record Mode




Determines what happens to your recordings and to any existing events on the track when you are recording. This section also contains the automatic MIDI record quantize function.

Locators



Allows you to go to the left or right locator position, and to set the left and right locator position numerically.

Punch Points



Allows you to activate/deactivate **Punch In** and **Punch Out**.

The section to the right of the punch buttons allows you to set up the punch positions numerically. For this to work, **Lock Punch Points to Locators** must be deactivated. You can hide/show that section by clicking the points on the divider.

Main Transport




Shows the basic transport controls as well as the time display options.

Arranger



Shows the arranger functions.


Pre-roll & Post-roll



Allows you to activate/deactivate pre-roll and post-roll.

The section to the right of the pre-roll buttons allows you to set the pre-roll values numerically. You can hide/show that section by clicking the points on the divider.


Tempo & Time Signature



Allows you to activate/deactivate the tempo track and the metronome click, and to set the tempo value and the first time signature value numerically.

The section to the right of the value fields allows you to activate/deactivate external synchronization and metronome click in count-in. You can hide/show that section by clicking the points on the divider.

Marker



Shows the basic marker functions.

MIDI Activity



Allows you to monitor the MIDI input and the MIDI output signals.

Audio Activity



Allows you to monitor the audio input and output signals.

Audio Level Control



Shows clipping indicators and allows you to control the output level.

RELATED LINKS

[Transport](#) on page 1035

[Transport - Scrub](#) on page 1036

Transport Menu

The **Transport** menu contains several transport functions as well as many other options related to playback and recording.

Transport Panel

Opens the **Transport** panel.

Transport

Start

Starts playback.

Stop

Stops playback.

Start/Stop

Starts/Stops playback.

Cycle

Activates/Deactivates cycle mode.

Record

Activates/Deactivates record mode.

Rewind

Moves backward.

Forward

Moves forward.

Fast Rewind

Moves backward at a faster speed.

Fast Forward

Moves forward at a faster speed.

Nudge Cursor Left

Moves the project cursor position to the left.

Nudge Cursor Right

Moves the project cursor position to the right.

Enter Project Cursor Position

Allows you to enter the project cursor position manually.

Enter Tempo

Allows you to enter the tempo manually.

Enter Time Signature

Allows you to enter the time signature manually.

Go to Project Start

Moves the project cursor position to the start of the project.

Go to Project End

Moves the project cursor position to the end of the project.

Exchange Time Formats

Switches the primary and the secondary time display.

Locators

Go to Left Locator Position

Moves the project cursor position to the left locator.

Go to Right Locator Position

Moves the project cursor position to the right locator.

Set Left Locator to Project Cursor Position

Sets the left locator to the project cursor position.

Set Right Locator to Project Cursor Position

Sets the right locator to the project cursor position.

Enter Left Locator Position

Allows you to enter the position of the left locator manually.

Enter Right Locator Position

Allows you to enter the position of the right locator manually.

Set Locators to Selection Range

Sets the locators to encompass the selection.

Exchange Left & Right Locator Positions

Switches the positions of the left and right locator.

Loop Selection Range

Activates playback from the start of the current selection and keeps starting over again when reaching the selection end.

Punch Points

Lock Punch Points to Locators

Allows you to unlock/lock the punch in and punch out position to the left and the right locator.

Activate Punch In

Activates/Deactivates punch in.

Activate Punch Out

Activates/Deactivates punch out.

Go to Punch In Position

Moves the project cursor position to the punch in position.

Go to Punch Out Position

Moves the project cursor position to the punch out position.

Set Punch In to Project Cursor Position

Moves the punch in position to the project cursor position.

Set Punch Out to Project Cursor Position

Moves the punch out position to the project cursor position.

Enter Punch In Position

Allows you to enter the punch in position manually.

Enter Punch Out Position

Allows you to enter the punch out position manually.

Set Punch Points to Selection Range

Sets the punch in and the punch out position to the selected event range.

Set Project Cursor Position

Locate Selection Start

Moves the project cursor to the beginning of the selection.

Locate Selection End

Moves the project cursor to the end of the selection.

Locate Next Marker

Moves the project cursor to the next marker.

Locate Previous Marker

Moves the project cursor to the previous marker.

Locate Next Hitpoint

Moves the project cursor to the next hitpoint on the selected track.

Locate Previous Hitpoint

Moves the project cursor to the previous hitpoint on the selected track.

Locate Next Event

Moves the project cursor to the next event on the selected track.

Locate Previous Event

Moves the project cursor to the previous event on the selected track.

Play Project Range

Play from Selection Start

Activates playback from the start of the current selection.

Play from Selection End

Activates playback from the end of the current selection.

Play until Selection Start

Activates playback two seconds before the start of the current selection and stops at the selection start.

Play until Selection End

Activates playback two seconds before the end of the current selection and stops at the selection end.

Play until Next Marker

Activates playback from the project cursor and stops at the next marker.

Play Selection Range

Activates playback from the start of the current selection and stops at the selection end.

Pre-roll & Post-roll

Use Pre-roll

Activates/Deactivates the pre-roll.

Use Post-roll

Activates/Deactivates the post-roll.

Post-roll from Selection Start

Starts playback from the beginning of the selected range and stops after the time set in the post-roll field on the **Transport** panel.

Post-roll from Selection End

Starts playback from the end of the selected range and stops after the time set in the post-roll field on the **Transport** panel.

Pre-roll to Selection Start

Stops playback at the selection start. The playback start position is set in the pre-roll field on the **Transport** panel.

Pre-roll to Selection End

Stops playback at the selection end. The playback start position is set in the pre-roll field on the **Transport** panel.

Use Tempo Track

Activates/Deactivates the tempo track.

Common Record Modes

Punch In/Out

Activates/Deactivates punch in/out.

Re-Record

Activates/Deactivates the re-record mode.

Start Recording at Project Cursor Position

Activates/Deactivates the start of the recording at the project cursor position.

Start Recording at Left Locator/Punch In Position

Activates/Deactivates the start of the recording at the left locator.

Audio Record Mode

These options allow you to select what happens when you record over existing events.

Keep History

Keeps existing events or portions of events.

Cycle History + Replace

Replaces existing events or portions of events by the new recording. In cycle mode, all takes from the current cycle recording are kept.

Replace

Replaces existing events or portions of events by the last take.

MIDI Record Mode

These options allow you to select what happens when you record over existing parts.

New Parts

Keeps existing parts and saves the new recording as a new part.

Merge

Keeps existing events in parts and adds the newly recorded events.

Replace

Replaces existing events in parts by the new recording.

Auto Quantize in Record

Activates automatic quantizing during record.

MIDI Cycle Record Mode

Mix

Adds everything you record to what was previously recorded.

Overwrite

Overwrites all MIDI that you have recorded on previous laps as soon as you play a MIDI note or send any MIDI message.

Keep Last

Replaces previously recorded laps only if the new lap is completed.

Stacked

Turns each recorded cycle lap into a separate MIDI part, and divides the track into lanes for each cycle lap. The parts are stacked above each other, each on a different lane. All takes but the last one are muted.

Mix-Stacked (No Mute)

Same as Stacked, but parts are not muted.

Auto Quantize in Record

Activates automatic quantizing during record.

Retrospective MIDI Record

Allows you to capture MIDI notes that you play in stop mode or during playback. For this to work, you need to enable the **Retrospective Record** option in the **Preferences** dialog (**Record—MIDI** page).

Metronome Setup

Opens the **Metronome Setup** dialog.

Activate Metronome

Activates/Deactivates the metronome click.

Project Synchronization Setup

Opens the **Project Synchronization Setup** dialog.

Use External Synchronization

Sets Cubase to be synchronized externally.

RELATED LINKS

- [Left and Right Locators](#) on page 219
- [Punch In and Punch Out](#) on page 223
- [Pre-Roll and Post-Roll](#) on page 222
- [Common Record Modes](#) on page 239
- [Audio Record Modes](#) on page 244
- [MIDI Record Modes](#) on page 250
- [Enabling Retrospective MIDI Record](#) on page 252
- [Metronome Click](#) on page 224

Transport

The **Transport** contains all transport functions in an integrated and fixed zone of the **Project** window.

- To activate the transport, click **Setup Window Layout** on the **Project** window toolbar and activate **Transport**.



- To display all transport elements, right-click in an empty area of the transport and select **Show All**.
- To show all controls of a section, click the points to the right of the section and drag all the way to the right. To hide the controls again, drag to the left.



RELATED LINKS

- [Transport](#) on page 49

Transport Sections

The **Transport** has different sections that you can show or hide by activating the corresponding options on the context menu.



- To activate the **Transport**, click **Set up Window Layout** on the **Project** window toolbar and activate **Transport**.



- To show/hide tools, open the **Transport** context menu by right-clicking in an empty area of the **Transport** and activate the tools that you want to display. To show all tools, select **Show All**.


The following options are available:

Constrain Delay Compensation




Allows you to minimize the latency effects of the delay compensation.

Common Record Modes




Allow you to determine what happens if you click **Record** during an audio or MIDI recording.

Audio Record Modes




Allow you to select what happens when you record over existing audio events.

MIDI Record Modes



Allow you to select what happens when you record over existing MIDI parts.

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

System Performance Meter



Shows the meters for ASIO time usage and hard disk transfer load.

Locators



Allows you to go to the left or right locator position, and to set the left and right locator position numerically.

Punch Points



Allows you to activate/deactivate **Punch In** and **Punch Out**. These points determine the record start and stop positions.

The section to the right of the punch buttons allows you to set up the punch positions numerically. For this to work, **Lock Punch Points to Locators** must be deactivated. You can hide/show that section by clicking the points on the divider.

Main Transport



Shows the main transport controls.

Time Displays



Shows the time display options.

Pre-roll & Post-roll



Allows you to activate/deactivate pre-roll and post-roll, and to set the values numerically.

Tempo & Time Signature



Allows you to activate/deactivate the tempo track, and to set the tempo value and the first time signature value numerically.

External Sync State



Allows you to activate/deactivate external synchronization and to open the **Project Synchronization Setup** dialog.

Click & Count-In & Click Pattern



Allows you to activate/deactivate the metronome click, the metronome click in count-in, and the click pattern.

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Input/Output Activity



Allows you to monitor the MIDI input/output signals, the audio input/output signals, and allows you to control the output level.

Transport Pop-Up Window

The **Transport** pop-up window allows you to access specific transport commands if the **Transport** panel and the **Transport** are closed.

The following default key commands open the **Transport** pop-up window:

- **Enter Left Locator**
Shift-L
- **Enter Right Locator**
Shift-R
- **Enter Project Cursor Position**
Shift-P
- **Enter Tempo**
Shift-T
- **Enter Time Signature**
Shift-C
- **Enter Punch In Position**
Shift-I
- **Enter Punch Out Position**
Shift-O
- **Go to Left Locator**
Num1
- **Go to Right Locator**
Num2

Using a specific key command opens the corresponding section of the **Transport** pop-up window:



Transport pop-up window for entering the left **Locator** position.

NOTE

To close the **Transport** pop-up window, press **Esc**.

Time Display Window


The **Time Display** window allows you to view the current time position in a separate window. You can adjust its size and specify the time format that you want to display.

- To show the **Time Display** window, select **Studio > More Options > Time Display**.



- You can set up the time format by right-clicking the window and selecting an option from the context menu.

The **Show Beat Count Only** option allows you to show the beat counts. This is useful if you want to use the **Time Display** window as a visual metronome.



- To adjust the window size to the size of the displayed values, double-click the window. To adjust the size of the displayed values step by step, you can also right-click and select **Increase Window Size** or **Decrease Window Size** from the context menu.
- To set the transparency of the window, adjust the **Window Transparency** slider in the **Studio Setup** dialog (**Time Display** page).

RELATED LINKS

[Time Signature Events](#) on page 908

Left and Right Locators

The left and right locators are a pair of markers that you can use to set up cycle boundaries. Left and right locators are available in the **Project** window as well as in the editors.



Locators are indicated by the flags in the ruler. The area between the left and the right locator is the locator range. The locator range is highlighted in the ruler and the event display.

NOTE

The event display in the MIDI editors is only highlighted if **Show Part Borders** is deactivated.

- To activate/deactivate the cycle mode, click the locator range in the upper part of the ruler.



- NOTE

If you activate cycle mode, and the right locator is positioned before the left locator, the locator range is skipped during playback.



RELATED LINKS

[Cycle Recording](#) on page 238

[Toolbar](#) on page 710

Setting Locator Ranges

There are several ways to set locator ranges.

To set the locator range, do one of the following:

- Click in the upper part of the ruler and drag to the right.
- Select a range or an event and select **Transport > Locators > Set Locators to Selection Range**.
- Double-click a cycle marker.
- Press **P**.

To move the locator range, do the following:

- Click, keep the mouse button pressed, and then drag left or right in the upper part of the ruler.

To create a new locator range in a range, do the following:

- Press **Ctrl/Cmd-Alt** and drag left or right in the upper part of the ruler.

To set both locators to the nearest snap position, do the following:

- Press **Ctrl/Cmd-Alt** and click at a position in the upper part of the ruler.

Setting Locator Positions

There are several ways to set the locator positions.

To set locator positions, do one of the following:

- Drag the left handle in the upper part of the ruler.
- Drag the right handle in the upper part of the ruler.
- Press **Ctrl/Cmd** and click at the position in the upper part of the ruler to set the left locator.
- Press **Alt** and click at the position in the ruler to set the right locator.
- Adjust the **Left/Right Locator Position** value on the **Transport** panel.

To set locator positions to the project cursor position, do one of the following:

- Press **Ctrl/Cmd**, and on the numeric keypad press **1** to set the left locator.
- Press **Ctrl/Cmd**, and on the numeric keypad press **2** to set the right locator.
- Press **Alt** and click **Go to Left/Right Locator Position** on the **Transport** panel.

Setting the Project Cursor Position

You have several possibilities to set the project cursor position, that is, to locate to specific time positions in the **Project** window.

- By using the main transport functions.
- By holding down **Shift-Alt** and clicking in the event display.
- By clicking or dragging in the lower part of the ruler.
- By using the functions in the **Set Project Cursor Position** submenu of the **Transport** menu.
- By clicking in an empty section in the event display.

NOTE

For this to work you must activate **Locate when Clicked in Empty Space** in the **Preferences** dialog (**Transport** page).

- By using locators.

NOTE

You can use **Num1** to set the project cursor to the left locator position, and **Num2** to set the project cursor to the right locator position.

- By using markers.
- By using the arranger functions.
- By using key commands.

RELATED LINKS

[Transport Panel Sections](#) on page 208

[Ruler](#) on page 46

[Transport Menu](#) on page 210

[Transport](#) on page 1035

[Left and Right Locators](#) on page 219

[Markers](#) on page 307

[Arranger Track](#) on page 290


[Key Commands](#) on page 973

Auto-Scroll

Auto-Scroll allows you to keep the project cursor visible in the window during playback.


If you activate **Auto-Scroll** on the toolbar of the **Project** window or one of the editors, the following modes are available in the **Switch Auto-Scroll Settings** pop-up menu:

Page Scroll



The project cursor moves from the left side to the right side of the window. When the project cursor reaches the right side of the window, the ruler and the project cursor jump to the left side of the window and start over again. This behavior can be compared to turning a page of a book.

Stationary Cursor



The project cursor is kept in the middle of the window and the ruler scrolls continuously to the left.

RELATED LINKS

[Toolbar](#) on page 40

Suspend Auto-Scroll When Editing

If you do not want the **Project** window display to change when editing during playback, activate **Suspend Auto-Scroll when Editing**.

Suspend Auto-Scroll when Editing is available as an option in the **Switch Auto-Scroll Settings** pop-up menu to the right of the **Auto-Scroll** button.

If this option is activated, auto-scrolling is suspended as soon as you click anywhere in the event display during playback until playback stops or you click **Auto-Scroll** again.

As a visual feedback, the **Auto-Scroll** button changes its color.

Time Formats

You can set up different time formats.

Selecting the Primary Time Format

On the **Transport** panel, you can select the primary time format. This is the global display format that is used for all rulers and position displays in the program, except the ruler tracks.

PROCEDURE

1. In the main transport section on the **Transport** panel, click **Select Primary Time Format**.
2. Select a time format from the pop-up menu.



You can also select **Project > Project Setup > Display Format** to select the primary time format.

RESULT

The time format on the **Transport** panel and all rulers and position displays are updated.

Independent Time Displays

You can show time displays that are independent from the global display format.

To select an independent time display, do one of the following:

- In the ruler of the **Project** window or any editor, click the arrow button to the right of the ruler.
- Select **Project > Add Track > Ruler** to add a ruler track, and right-click the ruler.
- In the **Main Transport** section of the **Transport** panel, click **Select Secondary Time Format**.

RELATED LINKS

[Ruler](#) on page 46

[Ruler Track](#) on page 142

Pre-Roll and Post-Roll

You can activate pre-roll and post-roll with the corresponding buttons in the **Pre-roll & Post-roll** section on the **Transport** panel or by selecting **Transport > Pre-roll & Post-roll > Use Pre-roll/Use Post-roll**.

- By setting a pre-roll value you instruct Cubase to roll back a short section whenever playback is activated.

- By setting a post-roll value you instruct Cubase to play back a short section after automatic punch out before stopping.


NOTE

This only works if **Punch Out** is activated on the **Transport** panel, and if **Stop after Automatic Punch Out** is activated in the **Preferences** dialog (**Record** page).

Using Pre-Roll and Post-Roll


PREREQUISITE

On the **Transport** panel, **Lock Punch Points to Locators** is activated.

PROCEDURE

1. Set the locators to where you want to start and end recording.

2. On the **Transport** panel, activate **Punch In** and **Punch Out**.
3. In the **Preferences** dialog, select **Record**.
4. Activate **Stop after Automatic Punch Out**.
5. On the **Transport** panel, activate **Pre-roll** and **Post-roll**.



6. In the **Pre-roll Amount** and **Post-roll Amount** fields, enter the pre-roll and post-roll values.
 7. Activate **Record**.
-

RESULT

The project cursor rolls back by the time specified pre-roll value and playback starts. When the cursor reaches the left locator, recording is automatically activated. When the cursor reaches the right locator, recording is deactivated, but playback continues for the specified post-roll value before stopping.

Punch In and Punch Out

The punch in and the punch out points are a pair of markers that you can use for punch in and punch out recordings. The punch in position determines the record start position whereas the punch out position determines the record stop position.

You can activate punch in and punch out by activating the corresponding buttons on the **Transport** panel.

The punch in position is locked to the left locator position and the punch out position to the right locator position. The punch position fields are unavailable.

However, you can detach the punch points from the locators by deactivating **Lock Punch Points to Locators**.



If you do so, the value fields become available and you can use them to set up the punch positions independently from the locator positions.

You can also drag the punch in and punch out handles in the ruler to set the punch positions.



RELATED LINKS

[Activating Recording Automatically](#) on page 237

[Stopping Recording](#) on page 237

Metronome Click

You can use the metronome click as a timing reference for playing along and recording. The two parameters that govern the timing of the metronome are project tempo and the time signature that you can set up in the **Transport** panel.

- To activate the metronome click, activate **Activate Metronome Click** on the **Transport** panel.
You can also select **Transport > Activate Metronome** or use the corresponding key command.
- To define if the metronome click is played during playback, recording or count-in, select **Transport > Metronome Setup** and open the **General** page.
- To set up the sounds for the metronome click, select **Transport > Metronome Setup** and open the **Click Sounds** page.

RELATED LINKS

[Transport Panel Sections](#) on page 208

[Project Tempo Modes](#) on page 892

Click Patterns

Click patterns allow you to create a custom metronome click.

By default, the metronome click in Cubase has a 4/4 pattern with a fixed number of 4 clicks. The click level of the first click is high, while the level of the other beats is low.



The default metronome click pattern with 4 clicks at a 4/4 time signature



A metronome click pattern with 3 clicks at a 3/4 time signature

By setting up click patterns for the metronome at the current time signature, you can create a custom metronome click. You can determine the number of clicks and the level of the clicks to your liking.

If you have different project parts with different time signatures or tempos, and you want to set up different click patterns to match the rhythm and feel of these parts, you can set up a metronome click pattern for each signature event in your project.

You can also add the same time signature for different sections and set up different patterns for them.

NOTE

- If you want to visualize the current click pattern in the **Project** window, **Key Editor** or **Drum Editor** event display, activate **Use Metronome Click Pattern Level for Grid Line**

Emphasis in the corresponding ruler context menu. This is useful if **Snap** is activated and the **Snap Type** is set to **Grid**.

- Grid lines are only emphasized, if they are shown. If you want to visualize a click pattern that is set to 6 **Clicks** and a 4/4 **Time Signature**, you must set the **Grid Type** to a triplet value.

The **Click Patterns** page in the **Metronome Setup** dialog allows you to manage the available click patterns. You can remove and rename them or create new click patterns for specific time signatures.

RELATED LINKS

[Click Pattern Editor](#) on page 225

[Setting Up a Metronome Click Pattern](#) on page 226

[Setting Up Metronome Click Patterns for Signature Events](#) on page 226


[Toolbar](#) on page 40

Click Pattern Editor

The **Click Pattern Editor** allows you to set up a click pattern for your project to create new grooves and feels for the metronome click. This is useful if you want to create a triplet pattern for a 4/4 signature, for example.

The **Click Pattern Editor** is available on the **Transport**. If you add a signature track, it is available in the **Inspector** and on the info line.

- To open the **Click Pattern Editor** on the **Transport**, click the points to the right of the **Click & Count-In & Click Pattern** section and drag all the way to the right. Click the pattern field to open the **Click Pattern Editor**.



Clicks

Allows you to define the number of clicks that are used in the pattern.

Pattern

Allows you to select a pattern preset or to save your own ones. Which patterns are available depends on the current time signature, and on the settings in the **Metronome Setup** dialog on the **Click Patterns** page.

NOTE

To view, edit and rename the pattern presets, open the **Click Patterns** page in the **Metronome Setup** dialog.

Event Display

Shows the defined number of beats for the selected pattern.

You can change the accent level for a beat by changing its vertical position in the event display. There are 4 different settings. These correspond to the settings in the **Metronome Setup** dialog on the **Click Sounds** page. You can mute a beat by clicking the lowest vertical position.

RELATED LINKS

[Transport Sections](#) on page 215

[Signature Track](#) on page 143

Setting Up a Metronome Click Pattern

You can set up a different metronome click pattern for your project.

PROCEDURE

1. In the **Transport**, click the points to the right on the **Click & Count-in & Click Pattern** section and drag all the way to the right to show the click pattern section.
 2. Click the pattern field to open the **Click Pattern Editor**.
 3. Do one of the following:
 - Open the **Pattern** pop-up menu and select one of the presets.
 - Use the **Clicks** setting to define the number of clicks that you want to hear, and click in the event display to set up a new click pattern.
 4. When you are done, click outside the **Click Pattern Editor** to close it.
 5. Activate the metronome click.
-

RESULT

The metronome click is played back with the defined click pattern.

RELATED LINKS

[Click Pattern Editor](#) on page 225

Setting Up Metronome Click Patterns for Signature Events

You can set up a metronome click pattern for each signature event in your project. This is useful if you have different project parts with different time signatures, and you want to customize click patterns to the rhythm and feel of these parts. You can also add the same time signature for different sections and set up different patterns for them.

PROCEDURE

1. Double-click the plus sign or the pattern to the right of the time signature value to open the **Click Pattern Editor**.
 2. Do one of the following:
 - Open the **Pattern** pop-up menu and select one of the presets.
 - Use the **Clicks** setting to define the number of clicks that you want to hear, and click in the event display to set up a new click pattern.
 3. When you are done, click outside the **Click Pattern Editor** to close it.
 4. Repeat this for each signature event for which you want to set up a click pattern.
-

RESULT

If you play back the project and activate the metronome click, the different project parts use the defined click patterns. The **Click Pattern Editor** in the **Transport** shows the pattern at the project cursor position.

RELATED LINKS

[Click Pattern Editor](#) on page 225

[Signature Track](#) on page 143


[Time Signature Events](#) on page 908

Metronome Setup

You can make settings for the metronome in the **Metronome Setup** dialog.

To open the **Metronome Setup** dialog, do one of the following:

- Select **Transport > Metronome Setup**.
- On the **Transport**, open the **Click & Count-In & Click Pattern** section, and click **Open Metronome Setup**.



RELATED LINKS


[General Page](#) on page 228

[Click Sounds Page](#) on page 229

[Click Patterns Page](#) on page 231

General Page

The **General** page allows you to make basic metronome settings.



In the topmost section, the following options are available:

Activate Metronome Click

Activates/Deactivates the metronome click.

In the **Click Destinations** section, the following options are available:

Use MIDI Click

Activates a MIDI click for the metronome.

Use Audio Click

Activates an audio click for the metronome that is output via the audio hardware.

Select Audio Click Outputs

If you use multiple output busses, this allows you to activate the output bus where you want to route the metronome click.

In the **Click Options** section, the following options are available:

Click while Recording

Activates the metronome click during recording.

Click while Playing

Activates the metronome click during playback.

Click during Count-In

Activates a musical count-in that is played when you start recording from stop mode.

In the **Count-In** section, the following options are available:


- **Number of Bars in Count-In**

Allows you to set the number of bars that the metronome counts in before recording starts.

- **Time Signature at Record Start Position**
Activate this to let the count-in automatically use the time signature and tempo set at the position where recording starts.
- **Time Signature at Project Position**
Activate this to let the count-in use the time signature at the project position.
- **Use Custom Time Signature**
Allows you to set a time signature for the count-in. In this mode, signature changes in the project do not affect the count-in.

Click Sounds Page

The **Click Sounds** page allows you to set up and audition the MIDI click and the audio click. You can use the default audio or MIDI click, choose from a list of factory preset sounds, or assign your own custom sounds.



The **MIDI Click Settings** section allows you to set up the MIDI click that sounds if you activate **MIDI Click** in the **Click Destinations** section on the **General** page.

MIDI Output Port

Allows you to select a MIDI output port for the MIDI click. You can also select a VST instrument previously set up in the **VST Instruments** window.

MIDI Output Channel

Allows you to select a MIDI output channel for the MIDI click.

Note

Allows you to set the MIDI note number, that is, the pitch from C-2 to G8. Set the note number for the first beat in a bar in the top row, and the note numbers for the other beats in the rows below.

Velocity

Allows you to set the velocity of the MIDI click sound. Set the velocity for the first beat in a bar in the top row, and the velocities for the other beats in the rows below.

The **Audio Click Settings** section allows you to set up the audio click that sounds if you activate **Audio Click** in the **Click Destinations** section on the **General** page.

Use Steinberg Click Sound

Activates the default sounds for the metronome click.

Pitch

Allows you to set the pitch for the default sounds. Set the pitch for the first beat in a bar in the top row, and the pitches for the other beats in the rows below.

Level

Allows you to set the level for the default sounds. Set the level for the first beat in a bar in the top row, and the levels for the other beats in the rows below.

Use Custom Sounds

Activates custom sounds for the metronome click. For this to work, you must select an audio file for the custom sounds by clicking in the **Sound** column.

Sound

Allows you to select an audio file for the custom sounds. Select an audio file for the first beat in a bar in the top row, and the audio files for the other beats in the rows below.

Level

Allows you to set the level for the custom sounds. Set the level for the first beat in a bar in the top row, and the levels for the other beats in the rows below.

Audio Click Level

Allows you to adjust the level of the audio click.

Click Sound Presets

Allows you to load one of the click sound presets that supports up to 4 accents. Amongst other click sounds that are suited for a broad range of applications, you can also select **Steinberg Click Sound**, the default click sound of Cubase.

You can also create your own presets and save them.

Audition Click Sounds

Click **Play** to audition the activated click sounds.

Setting Up a Custom Audio Click Sound

PREREQUISITE

In the **Metronome Setup** dialog on the **General** page, **Activate Metronome** is activated. In the **Click Destinations** section, **Use Audio Click** is activated.

PROCEDURE

1. Open the **Click Sounds** page, and in the **Audio Click Settings** section, activate **Use Custom Sounds**.
2. In the **Sound** column click the top row.
3. In the file dialog, navigate to the audio file that you want to use as a custom sound for the first beat and select it.
4. Click **Open**.
5. Click the other rows to select audio files for the other beats.

6. Set the level of the sounds by clicking the respective rows in the **Audio Click Level** column and adjusting the value.
7. Optional: Click **Play** to audition the custom sounds.

RESULT


The metronome uses the defined custom sounds for the audio click.

AFTER COMPLETING THIS TASK

Open the **Click Sound Presets** pop-up menu and save your custom sounds as a preset.

Click Patterns Page

The **Click Patterns** page allows you to manage click patterns. Click patterns allow you to edit the default metronome click.



The following options are available:

- 1 **Add New Signature**
Click and enter a time signature value to add a new time signature.
- 2 **Available Time Signatures**
Shows the available time signatures.
- 3 **Available Patterns**
Shows the available click patterns.
- 4 **Add New Pattern**
Double-click to add a new click pattern for the time signature.
- 5 **Clicks**
Allows you to change the number of clicks used in the click pattern.
- 6 **Click Pattern**

Shows the click pattern. You can open the **Click Pattern Editor** by clicking the pattern.

7 Remove Click Pattern

Removes the click pattern from the list of available patterns.

8 Add New Pattern

Adds a new default click pattern for the time signature.

NOTE

If you scroll all the way down, you can reset all click patterns to the factory settings by clicking **Reset to Factory Patterns**.

You can double-click the name of a pattern and enter a new one to rename a click pattern.

Creating a Click Track

PROCEDURE

- Do one of the following:
 - Select **Project > Signature Track > Render Audio Click between Locators**.
 - Select **Project > Signature Track > Render MIDI Click between Locators**.
-

RESULT

- An audio track containing an audio event with the click is added to your project. The level corresponds to the **Audio Click Level** setting on the **Click Sounds** page of the **Metronome Setup** dialog.
- A MIDI track containing a MIDI part with the click is added to your project. The output of the MIDI track is routed to the MIDI output port that you set up on the **Click Sounds** page of the **Metronome Setup** dialog.

Chase

Chase is a function that makes sure your MIDI instruments sound as they should when you locate to a new position and start playback. This is accomplished by the program transmitting a number of MIDI messages to your instruments each time that you move to a new position in the project, making sure all MIDI devices are set up correctly with regard to program change, controller messages (such as MIDI Volume), etc.

EXAMPLE


You have a MIDI track with a program change event inserted at the beginning. This event makes a synth switch to a piano sound.

At the beginning of the first chorus you have another program change event which makes the same synth switch to a string sound.

You now play back the song. It begins with the piano sound and then switches to the string sound. In the middle of the chorus you stop and rewind to some point between the beginning and the second program change. The synth now still plays the string sound although in this section it really should be a piano.

The **Chase** function takes care of that. If program change events are set to be chased, Cubase tracks the music back to the beginning, finds the first program change, and transmits it to your synth, setting it to the correct sound.

The same thing can apply to other event types as well. In the **Preferences** dialog (**MIDI** page), the **Chase Events** settings determine which event types are chased when you locate to a new position and start playback.



RELATED LINKS

[Chase Events](#) on page 1026

On-Screen Keyboard

The **On-Screen Keyboard** allows you to play and record MIDI notes by using your computer keyboard or mouse. This is useful if you have no external MIDI instrument at hand and you do not want to draw in notes with the **Draw** tool.

When the **On-Screen Keyboard** is displayed, the usual key commands are blocked because they are reserved for the **On-Screen Keyboard**. The only exceptions are:

- Save: **Ctrl/Cmd-S**
- Start/Stop Record: **Num ***
- Start/Stop Playback: **Space**
- Jump to left locator: **Num 1**
- Delete: **Delete** or **Backspace**
- Cycle on/off: **Num /**
- Show/Hide Transport panel: **F2**
- Show/Hide On-Screen Keyboard: **Alt-K**

Recording MIDI With the On-Screen Keyboard

PREREQUISITE

You have selected a MIDI or instrument track and activated **Record Enable**.

PROCEDURE

1. Select **Studio > On-Screen Keyboard**.
2. Activate **Record**.
3. Perform one of the following actions to enter some notes:
 - Click on the keys of the **On-Screen Keyboard**.
 - Press the corresponding key on your computer keyboard.


NOTE

Press several keys simultaneously to enter polyphonic parts. The maximum number of notes that can be played at one time varies between the different operating systems and hardware configurations.

AFTER COMPLETING THIS TASK

Close the **On-Screen Keyboard** to make all key commands available again.

On-Screen Keyboard Options



1 Note Velocity Level

This slider allows you to adjust the volume of the **On-Screen Keyboard**. You can also use the **Up Arrow** key or the **Down Arrow** key for this.

2 Change On-Screen Keyboard Type

This button allows you to switch between computer keyboard and piano keyboard display mode.

The computer keyboard mode, you can use the two rows of keys that are displayed on the **On-Screen Keyboard** to enter notes.

The piano keyboard has a wider range of keys. It allows you to enter more than one voice simultaneously. You can also use the **Tab** key for this.

3 Octave Offset

These buttons allow you to switch the keyboard range to a lower or higher octave. You have seven full octaves at your disposal. You can also use the **Left Arrow** key or the **Right Arrow** key for this.

4 Pitchbend/Modulation Sliders

These sliders are only available in piano keyboard mode. The left slider displays pitchbend, the right slider shows modulation changes. To introduce modulation, click on a key and drag upwards or downwards. To introduce pitchbend drag left or right.

Recording

In Cubase, you can record audio and MIDI.

Make the following initial preparations:

- Set up, connect, and calibrate your audio hardware.
- Open a project and set up the project setup parameters according to your specifications. Project setup parameters determine the record format, sample rate, project length, etc. that affect the audio recordings that you make during the course of the project.
- If you plan to record MIDI, set up and connect your MIDI equipment.

RELATED LINKS

[Setting Up Audio](#) on page 11

[Setting Up MIDI](#) on page 18

[Setting Up a Metronome Click Pattern](#) on page 226

Basic Recording Methods

The basic recording methods apply to audio and MIDI recordings.

Record Enabling Tracks

To be able to record, you must record-enable the tracks on which you want to record.

- To record-enable a track, activate **Record Enable** in the track list, in the Inspector, or in the MixConsole.
- To record-enable all audio tracks simultaneously, set up a key command for **Activate Record Enable for all Audio Tracks** in the **Mixer** category of the **Key Commands** dialog and use it.
- To record-enable audio or MIDI tracks on selection, activate the **Enable Record on Selected Audio Track** or the **Enable Record on Selected MIDI Track** option in the **Preferences** dialog (**Editing—Project & MixConsole** page).

NOTE

The exact number of audio tracks that you can record simultaneously depends on your computer CPU and hard disk performance. Activate the **Warn on Processing Overloads** option in the **Preferences** dialog (**VST** page) to show a warning message as soon as the CPU overload indicator lights up during recording.

RELATED LINKS

[Editing - Project & MixConsole](#) on page 1018

[VST](#) on page 1037

Activating Recording

You can activate recording manually or automatically.

Activating Recording Manually

- To activate recording, click **Record** on the **Transport** panel or on the toolbar. You can also use the corresponding key command, by default **Num-***.

Recording starts from the current cursor position.

NOTE

When you start recording in **Stop** mode, you can start recording from the left locator by activating **Start Record at Left Locator/Punch In Position** on the **Transport** menu. The pre-roll setting or the metronome count-in will be applied.

Activating Recording Automatically

Cubase can automatically switch from playback to recording at a given position. This is useful if you must replace a section of a recording and want to listen to what is already recorded up to the recording start position.


PROCEDURE

1. Set the left locator to the position where you want to start recording.
If you want to set up the punch points independently from the locators, deactivate **Lock Punch Points to Locators** on the **Transport** panel, and set up the punch in and punch out positions in the value fields to the right.
 2. Activate **Punch In** on the **Transport** panel.
 3. Activate playback from any position before the left locator.
-

RESULT

If you have unlocked the punch positions from the locator positions, recording is automatically activated when the project cursor reaches the punch in position.

If cycle mode is activated, the punch in point corresponds to the position of the left locator, and the punch out point is set before the right locator, recording is stopped at the punch out position and resumed at the punch in position.



If the punch positions are locked to the locators, recording is automatically activated when the project cursor reaches the left locator.

RELATED LINKS

[Punch In and Punch Out](#) on page 223

Stopping Recording

- To stop recording and playback, click **Stop** on the **Transport** panel or use the corresponding key command, by default **Num-0**.
- To stop recording and continue playback, click **Record** or use the corresponding key command, by default **Num-***.
- To stop recording automatically when the project cursor reaches the punch out position and continue playback, activate **Punch Out** on the **Transport** panel.

NOTE

If you have unlocked the punch positions from the locator positions, recording is automatically stopped when the project cursor reaches the punch out position.

NOTE

If cycle mode is activated, the punch in point is set after the left locator, and the punch out point corresponds to the right locator, recording is started at the punch in position, stopped at the punch out position, and resumed at the punch in position.

RELATED LINKS

[Punch In and Punch Out](#) on page 223

Cycle Recording

You can record in a cycle, that is, you can record a selected section repeatedly and seamlessly.

PREREQUISITE

A cycle is set up with the left and right locators.

PROCEDURE

1. Click the **Cycle** on the **Transport** panel to activate cycle mode.
 2. Activate recording from the left locator, before or within the cycle.
As soon as the project cursor reaches the right locator, it jumps back to the left locator and continues recording a new lap.
-

RESULT

The results of cycle recording depend on the selected record mode. They also differ for audio and MIDI.

RELATED LINKS

[Left and Right Locators](#) on page 219

[Recording MIDI](#) on page 248

[Recording Audio](#) on page 243

Using Pre-Roll and Post-Roll

You can set up a pre-roll and a post-roll for recording.

PREREQUISITE

Activate **Stop after Automatic Punch Out** in the **Preferences** dialog (**Record** page).

PROCEDURE

1. Set the locators to where you want to start and end recording.
 2. On the **Transport** panel, activate **Punch In** and **Punch Out**.
 3. Activate **Pre-roll** and **Post-roll**.
 4. Specify a **Pre-roll Amount** and a **Post-roll Amount**.
 5. Click **Record**.
-

RESULT

The project cursor rolls back and starts playback at the time that has been set as pre-roll amount. When the cursor reaches the left locator, recording is automatically activated. When the cursor reaches the right locator, recording is deactivated, and the playback continues as long as the time that has been set as post-roll amount.

Common Record Modes

The **Common Record Modes** determine what happens if you click **Record** during an audio or MIDI recording.

- To access the record modes, select **Transport > Common Record Modes**.
You can also access the **Common Record Modes** by clicking the upper part of the **Record Modes** section in the **Transport** panel.

Punch In/Out

In this mode, the recording is stopped.

Re-Record

In this mode, the recording is reinitiated, the events are removed and recording is restarted from the exact same position.

Start Recording at Cursor

In this mode, recording starts from the cursor position.

Start Recording at Left Locator/Punch In Position

In this mode, recording starts from the left locator.

RELATED LINKS

[Transport Menu](#) on page 210

[Transport Panel Sections](#) on page 208

Re-Recording

PROCEDURE

1. Activate **Transport > Common Record Modes > Re-Record**.
 2. Activate recording.
 3. Hit **Record** again to restart recording.
-

RESULT

The project cursor jumps back to the record start position and recording is reinitiated. Pre-roll and count-in settings are taken into account.

NOTE

The previous recordings are removed from the project and cannot be retrieved using **Undo**. However, they remain in the **Pool**.

Monitoring

In Cubase, monitoring means listening to the input signal while preparing to record or while recording.

The following ways of monitoring are available.

- Via Cubase.

- Externally by listening to the signal before it reaches Cubase.
- By using ASIO Direct Monitoring.
This is a combination of both other methods.

Monitoring via Cubase

If you use monitoring via Cubase, the input signal is mixed with the audio playback. This requires an audio hardware configuration with a low latency value.

PROCEDURE

1. In the track list, activate **Monitor**.



2. In the **MixConsole**, adjust the monitoring level and the panning.
You can add effects and EQ to the monitor signal using the track's channel. If you are using plug-in effects with large inherent delays, the automatic delay compensation function in Cubase will increase the latency. If this is a problem, you can use the Constrain Delay Compensation function while recording.
 3. In the **Preferences** dialog, select **VST**.
 4. Open the **Auto Monitoring** pop-up menu and select a monitoring mode.
-

RESULT

The monitored signal will be delayed according to the latency value which depends on your audio hardware and drivers. You can check the latency of your hardware in the **Studio Setup** dialog (**VST Audio System** page).

RELATED LINKS

[VST on page 1037](#)

External Monitoring

External monitoring means listening to the input signal before it is sent into Cubase. It requires an external mixer for mixing the audio playback with the input signal. The latency value of the audio hardware configuration does not affect the monitor signal. When using external monitoring, you cannot control the level of the monitor signal from within Cubase or add VST effects or EQ to the monitor signal.

PROCEDURE

1. In the **Preferences** dialog, select **VST**.
 2. Open the **Auto Monitoring** pop-up menu and select **Manual**.
 3. Deactivate **Monitor** in Cubase.
 4. On your mixing desk or mixer application for your audio hardware, activate the **Thru** or **Direct Thru** mode to send the input audio back out again.
-

ASIO Direct Monitoring

If your audio hardware is ASIO 2.0 compatible, it may support ASIO Direct Monitoring. This feature may also be available for audio hardware with macOS drivers. In ASIO Direct Monitoring mode, the monitoring is done in the audio hardware, and monitoring is controlled from Cubase. The latency value of the audio hardware configuration does not affect the monitor signal when using ASIO Direct Monitoring.

PROCEDURE

1. In the track list, activate **Monitor**.



2. Select **Studio > Studio Setup**.
3. In the **Devices** list, select your audio hardware driver, and activate **Direct Monitoring**.
If the checkbox is grayed out, your audio hardware (or its driver) does not support ASIO Direct Monitoring. Consult the audio hardware manufacturer for details.
4. In the **Preferences** dialog, select **VST**.
5. Open the **Auto Monitoring** pop-up menu and select a monitoring mode.
6. In the **MixConsole**, adjust the monitoring level and panning.
Depending on the audio hardware, this might not be possible.

AFTER COMPLETING THIS TASK

You can monitor the input levels of audio tracks, that is, you can map the input bus metering to monitor-enabled audio tracks and watch the input levels of your audio tracks when working in the **Project** window.

- Activate **Map Input Bus Metering to Audio Track (in Direct Monitoring)** in the **Preferences** dialog (**Metering** page).
As the tracks are mirroring the input bus signal you will see the same signal in both places. When using mapped metering, any functions that you apply to the audio track are not reflected in its meters.

NOTE

With Direct Monitoring activated, Direct Routing cannot be used for routing destinations 2-8. Only the first bus can be used for Direct Monitoring.

RELATED LINKS

[VST](#) on page 1037

Monitoring MIDI Tracks

You can monitor everything you play and record through the MIDI output and channel that are selected for the MIDI track.

PREREQUISITE

Local Off is activated on your MIDI instrument.

PROCEDURE

1. In the **Preferences** dialog, select **MIDI**.
2. Make sure **MIDI Thru Active** is activated.
3. In the track list, activate **Monitor**.



RESULT

Incoming MIDI is echoed back out again.

RELATED LINKS

[MIDI](#) on page 1025

Audio Recording Specifics

Preparations

Selecting a Record File Format

You can set up the record file format, that is, the sample rate, bit depth, and record file type for new audio files.

PROCEDURE

1. Select **Project > Project Setup**.
2. Set up the settings for **Sample Rate**, **Bit Depth**, and **Record File Type**.

IMPORTANT

The bit depth and file type can be changed at any time while the sample rate of a project cannot be changed at a later stage.

RELATED LINKS

[Creating New Projects](#) on page 83

Setting the Audio Record Folder

Each Cubase project has a project folder containing an **Audio** folder. By default, this is where recorded audio files are stored. However, you can select record folders independently for each audio track if needed.

PROCEDURE

1. In the track list, select all tracks that you want to assign the same record folder.
 2. Right-click one of the tracks to open the context menu.
 3. Select **Set Record Folder**.
 4. In the file dialog, navigate to the folder that you want to use as record folder or create a new folder by clicking **New Folder**.
If you want to have separate folders for different types of material (speech, ambient sounds, music, etc.), you can create subfolders within the project **Audio** folder and assign different tracks to different subfolders. This way, all audio files will still reside within the project folder, which will make managing the project easier.
-

Getting the Track Ready for Recording

Creating a Track and Setting the Channel Configuration

PROCEDURE

1. Select **Project > Add Track > Audio**.
2. In the **Count** field, enter the number of tracks that you want to add.
3. Open the **Configuration** pop-up menu and select a channel configuration.
4. Optional: Enter a track name.

5. Click **Add Track**.
-

RELATED LINKS

[Add Track Dialog](#) on page 151

RAM Requirements for Recording


Each track on which you record requires a certain amount of RAM, and the memory usage increases the longer the recording lasts. For each audio channel, 2.4 MB of RAM are required for MixConsole settings, etc. The memory usage increases with the length of the recording, the sample rate, and the number of tracks you record. Consider the RAM limitation of your operating system when setting up your project for recording.

Selecting an Input Bus for the Track

Before you can record on your track, you must add and set up the required input busses and specify from which input bus the track will record.

PROCEDURE

1. In the **Inspector** for the audio track, open the **Input Routing** pop-up menu.



2. Select an input bus.
-

RELATED LINKS

[Setting Up Input and Output Ports](#) on page 17

[Audio Bus Setup](#) on page 17

[Audio Track Inspector](#) on page 98

Recording Audio

You can record audio using any of the basic recording methods.

When you finish recording, an audio file is created in the **Audio** folder within the project folder. In the Pool, an audio clip is created for the audio file, and an audio event that plays the whole clip appears on the recording track. Finally, a waveform image is calculated for the audio event. If the recording was very long, this may take a while.

NOTE

The waveform image will be calculated and displayed during the actual recording process. This realtime calculation uses some processing power. If your processor is slow or if you are working on a CPU-intensive project, deactivate **Create Audio Images During Record** in the **Preferences** dialog (**Record—Audio** page).

RELATED LINKS

[Basic Recording Methods](#) on page 236

[Cycle Recording](#) on page 238

Audio Record Modes

By selecting an **Audio Record Mode** you decide what happens to your recording and to any existing events on the track where you are recording. This is necessary because you will not always record on an empty track. There may be situations where you record over existing events, especially in cycle mode.

- To access the record modes, select **Transport > Audio Record Mode**.

You can also access the **Audio Record Modes** by clicking to the right of the audio symbol in the **Record Modes** section in the **Transport** panel.

Keep History

Existing events or portions of events that are overlapped by a new recording are kept.

Cycle History + Replace

Existing events or portions of events that are overlapped by a new recording are replaced by the new recording. However, if you record in cycle mode, all takes from the current cycle recording are kept.

Replace

Existing events or portions of events that are overlapped by a new recording are replaced by the last recorded take.

RELATED LINKS

[Transport Menu](#) on page 210

[Transport Panel Sections](#) on page 208

Recording with Effects

Cubase allows you to add effects and/or EQ directly while recording. This is done by adding insert effects and/or making EQ settings for the input channel in the MixConsole.

IMPORTANT

If you record with effects, the effects become part of the audio file itself. You cannot change the effect settings after recording.

When you are recording with effects, consider using 32-bit float or 64-bit float format. This way, the bit depth will not be reduced, which means there is no risk of clipping at this stage. Also, this preserves the signal quality perfectly. If you record in 16-bit or 24-bit format, the available headroom is lower, which means clipping can occur if the signal is too loud.

Recording a Mix of Separate Tracks

You can create a downmix of separate tracks, bass drum, hi-hats, or snare, for example. This is done by selecting an output bus, a group bus, or an FX channel bus as an input for your recording.

PROCEDURE

1. Set up your separate tracks and add a group track.
2. For each of the drum tracks, open the **Output Routing** pop-up menu and select the group track as output.
3. Create a new audio track, open the **Input Routing** pop-up menu for it and select the group track as input for this audio track.
4. Record-enable this audio track and start recording.

RESULT

The output of the group track will be recorded on the new track and you will get a mix of your separate tracks.

NOTE

You can also select an FX channel as recording source. In this case, only the output of the FX channel will be recorded.

RELATED LINKS

[Routing](#) on page 344

Undoing Recording

If you decide that you do not like what you just recorded, you can delete it.

- Select **Edit > Undo**.

This removes the events that you just recorded from the **Project** window and moves the audio clips in the Pool to the trash folder. To remove the recorded audio files from the hard disk, open the Pool, right-click the **Trash** icon and select **Empty Trash**.

RELATED LINKS

[Pool Window](#) on page 527

Recovering Audio Recordings

Cubase allows you to recover audio recordings in two situations: if you specified an audio pre-record time when you hit **Record** too late and after a system failure during recording.

Specifying an Audio Pre-Record Time

You can capture up to 1 minute of any incoming audio that you play in Stop mode or during playback. This is possible because Cubase can capture audio input in buffer memory, even when not recording.

PROCEDURE

1. In the **Preferences** dialog, select **Record > Audio**.
 2. Specify a time (up to 60 seconds) in the **Audio Pre-Record Seconds** field.
This activates the buffering of audio input, making pre-record possible.
 3. Make sure that an audio track is record-enabled and receives audio from the signal source.
 4. When you have played some audio material that you want to capture (either in Stop mode or during playback), click **Record**.
 5. Stop the recording after a few seconds.
This creates an audio event that starts where the cursor position was when you activated recording. If you were in stop mode, and the cursor was at the beginning of the project, you may have to move the event to the right in the next step. If you were playing along to a project, you leave the event where it is.
 6. Select the **Object Selection** tool and place the cursor on the bottom left edge of the event so that a double arrow appears. Then click and drag to the left.
-

RESULT

The event is now extended, and the audio that you played before activating the recording is inserted. This means that if you played along during playback, the captured notes end up exactly where you played them in relation to the project.

RELATED LINKS

[Record - Audio](#) on page 1031

Recovering Audio Recordings after System Failure

Cubase allows you to recover audio recordings after a system failure, because of a power cut or other mishap, for example.

When you experience a computer crash during a recording, relaunch the system and check the project record folder. By default, this is the **Audio** subfolder inside the project folder. It should contain the audio file that you recorded, from the moment when you started recording to the time when your computer crashed.

NOTE

- This feature does not constitute an overall guarantee by Steinberg. While the program itself was improved in such a way that audio recordings can be recovered after a system failure, it is always possible that a computer crash, power cut, etc. might have damaged another component of the computer, making it impossible to save or recover any of the data.
 - Do not try to actively bring about this kind of situation to test this feature. Although the internal program processes have been improved to cope with such situations, Steinberg cannot guarantee that other parts of the computer are not damaged as a consequence.
-

MIDI Recording Specifics

Preparations

The preparations described in the following sections mainly focus on external MIDI devices.

MIDI Instruments and Channels

Most MIDI synthesizers can play several sounds at the same time, each on a different MIDI channel. This allows you to play back several sounds (bass, piano, etc.) from the same instrument.

Some devices, such as General MIDI compatible sound modules, always receive on all 16 MIDI channels. If you have such an instrument, there is no specific setting to make in the instrument.

On other instruments, you must use the front panel controls to set up a number of parts, timbres, or similar so that they all receive on one MIDI channel.

For more information, refer to the manual that came with your instrument.

Naming MIDI Ports

MIDI inputs and outputs are often displayed with long and complicated names. In Cubase, you can rename your MIDI ports to more descriptive names.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **MIDI Port Setup**.
The available MIDI inputs and outputs are listed. On Windows, the device to choose depends on your system.
 3. Click in the **Show As** column and type in a new name.
 4. Click **OK**.
-

RESULT

The new port names appear on the **MIDI Input** and **Output Routing** pop-up menus.

Setting the MIDI Input

In the **Inspector**, you set the MIDI input for the track.

PROCEDURE

1. In the track list, select the track to which you want to assign a MIDI input.
2. In the topmost **Inspector** section, open the **Input Routing** pop-up menu and select an input.
The available inputs on the menu depend on the type of MIDI interface that you are using. If you hold down **Shift-Alt**, the selected MIDI input is used for all selected MIDI tracks.

NOTE

If you select **All MIDI Inputs**, the track will receive MIDI data from all available MIDI inputs.

Setting the MIDI Channel and Output

The MIDI channel and output settings determine where the recorded MIDI is routed during playback. They are also relevant for monitoring MIDI in Cubase. You can select the channel and output in the track list or in the Inspector.

PROCEDURE

1. In the track list, select the track to which you want to assign a MIDI channel and output.
2. In the topmost **Inspector** section, open the **Output Routing** pop-up menu and select an output.
The available outputs on the menu depend on the type of MIDI interface that you are using. If you hold down **Shift-Alt**, the selected MIDI output is used for all selected MIDI tracks.
3. Open the **Channel** pop-up menu and select a MIDI channel.

NOTE

If you select the **Any** MIDI channel, the MIDI material is routed to the channels that are used by your MIDI instrument.

Selecting a Sound

You can select sounds from within Cubase by instructing the program to send Program Change and Bank Select messages to your MIDI device.

PROCEDURE

1. In the track list, select the track to which you want to assign a sound.
2. In the track list or the **Inspector**, open the **Program Selector** pop-up menu and select a program.
Program Change messages give access to 128 different program locations.
3. If your MIDI instruments have more than 128 programs, you can open the **Bank Selector** pop-up menu and select different banks, each containing 128 programs.

NOTE

Bank Select messages are recognized differently by different MIDI instruments. The structure and numbering of banks and programs may also vary. Refer to the documentation of your MIDI instruments for details.

RELATED LINKS

[MIDI Track Inspector](#) on page 112

Recording in MIDI Editors

You can record MIDI data into the MIDI part that is opened in a MIDI editor.

PREREQUISITE

You have selected **Merge** or **Replace** as a **MIDI Record Mode**.

PROCEDURE

1. Click in the MIDI editor so that it gets the focus.
 2. In the MIDI editor toolbar, activate **Record in Editor**.
 3. Do one of the following to activate recording:
 - Click **Record** on the **Transport** panel.
 - Click **Record** on the toolbar.
-

RESULT

The MIDI data is recorded into the MIDI part that is opened in the MIDI editor. If you record outside the part borders, the part is automatically enlarged.

RELATED LINKS

[Toolbar](#) on page 710

Recording MIDI

You can record MIDI using any of the basic recording methods.

When you finish recording, a part that contains MIDI events is created in the **Project** window.

NOTE

If you perform a live recording on a VST instrument, you usually compensate the latency of the audio card by playing earlier. In consequence, the timestamps are recorded too early. If you activate **ASIO Latency Compensation** on the track list, all recorded events are moved by the current latency setting.

The following preferences affect MIDI recording:

- Length Adjustment
- Snap MIDI Parts to Bars
- MIDI Record Catch Range in ms
- ASIO Latency Compensation Active by Default

You can find them in the **Preferences** dialog on the **MIDI** and on the **Record—MIDI** page.

RELATED LINKS

[Basic Recording Methods](#) on page 236

[MIDI](#) on page 1025

[Record - MIDI](#) on page 1032

Recording Different Types of MIDI Messages

You can record different types of MIDI messages.

- To specify which event types are recorded, deactivate the options for the type of MIDI message that you want to record in the **Preferences** dialog (**MIDI—MIDI Filter** page).

RELATED LINKS

[MIDI - MIDI Filter](#) on page 1029

Recording MIDI Notes

If you press and release a key on your synthesizer or on another MIDI keyboard, the following messages are recorded:

- Note On (key down)
- Note Off (key up)
- MIDI channel

NOTE

Normally, the MIDI channel information is overridden by the MIDI channel setting for the track. However, if you set the track to the **Any** MIDI channel, the notes will be played back on their original channels.

Recording Continuous Messages

Pitchbend, aftertouch, and controllers, such as modulation wheel, sustain pedal, volume, etc. are considered as MIDI continuous events, as opposed to the momentary key down and key up messages.

You can record continuous messages together or independently from the notes, that is, afterwards or before.

You can record continuous messages on their own tracks, separately from the notes to which they belong. As long as you set the two tracks to the same output and MIDI channel, it will appear to the MIDI instrument as if you made the two recordings at the same time.

Recording Program Change Messages

When you switch from one program to another on your synthesizer or on another MIDI keyboard, a number corresponding to that program is sent out via MIDI as a Program Change message.

You can record Program Change Messages together or independently from the notes, that is, afterwards or before.

You can record Program Change Messages on their own tracks, separately from the notes to which they belong. As long as you set the two tracks to the same output and MIDI channel, it will appear to the MIDI instrument as if you made the two recordings at the same time.

Recording System Exclusive Messages

System Exclusive (SysEx) messages are special types of MIDI messages that are used to send data that only makes sense to a unit of a certain make and type.

SysEx can be used to transmit a list of the numbers that make up the settings of one or more sounds in a synth.

Reset Function

The **Reset** function sends out note-off messages and resets controllers on all MIDI channels. This is sometimes necessary if you experience hanging notes, constant vibrato, etc. when punching in and out on MIDI recordings with pitchbend or controller data.

- To perform a MIDI reset manually, select **MIDI > Reset**.
- If you want Cubase to perform a MIDI reset on stop, activate **Reset on Stop** in the **Preferences** dialog (**MIDI** page).
- If you want Cubase to insert a reset event at the end of a recorded part, activate **Insert Reset Events after Record** in the **Preferences** dialog (**MIDI** page).

This resets controller data such as sustain, aftertouch, pitchbend, modulation, and breath control. This is useful if a MIDI part is recorded and the sustain pedal is still held after stopping recording. Usually, this would cause all following parts to be played with sustain, as the pedal off command was not recorded.

RELATED LINKS

[MIDI](#) on page 1025

MIDI Record Modes

By selecting a **MIDI Record Mode** you decide what happens to any existing parts on the track where you are recording. MIDI tracks can play back all events in overlapping parts. If you record several parts in the same locations or move parts so that they overlap, you will hear the events in all parts.

- To access the record modes, select **Transport > MIDI Record Mode**.
You can also access the **MIDI Record Modes** by clicking to the right of the MIDI symbol in the **Record Modes** section in the **Transport** panel.

MIDI Record Mode

New Parts

Existing parts that are overlapped by a new recording are kept. The new recording is saved as a new part.

Merge

Existing events in parts that are overlapped by a new recording are kept. The newly recorded events are added to the existing part.

Replace

Existing events in parts that are overlapped by a new recording are replaced.

NOTE

In **Merge** or **Replace** mode you can activate **Record in Editor** to record MIDI data in the editor. For this to work, the editor must have the focus. Otherwise, the data is recorded on the MIDI track in the **Project** window.

MIDI Cycle Record Mode

When you record MIDI in cycle mode, the result not only depends on the MIDI record mode, but also on the cycle record mode that is selected in the **MIDI Cycle Record Mode** section.

Mix

For each completed lap, everything you record is added to what was previously recorded. This is useful for building up rhythm patterns. Record a hi-hat part on the first lap, the bass drum part on the second lap, etc.

Overwrite

As soon as you play a MIDI note or send any MIDI message, all MIDI that you have recorded on previous laps is overwritten from that point. Make sure that you stop playing before the next lap begins. Otherwise, you will overwrite the entire take.

Keep Last

Each completed lap replaces the previously recorded lap. If you deactivate recording or press **Stop** before the cursor reaches the right locator, the previous take will be kept. If you do not play or input any MIDI during a lap, nothing happens, and the previous take will be kept.

Stacked

Each recorded cycle lap is turned into a separate MIDI part, and the track is divided into lanes, one for each cycle lap. The parts are stacked above each other, each on a different lane. All takes but the last one are muted.

Mix Stacked

Same as **Stacked**, but parts are not muted.

RELATED LINKS

[Transport Menu](#) on page 210

[Transport Panel Sections](#) on page 208

Quantizing MIDI Recordings

Cubase can automatically quantize MIDI notes on recording.



- To enable automatic quantizing, open the **Transport** panel and in the **Record Mode** section, click in the **MIDI Record Modes** field, and activate **Auto Quantize**.
The notes that you record are automatically quantized according to the quantize settings.

RELATED LINKS

[Quantizing MIDI and Audio](#) on page 264

[Quantize Panel](#) on page 269

Recovering MIDI Recordings

Cubase allows you to recover MIDI recordings.

Enabling Retrospective MIDI Record

The **Retrospective MIDI Record** setting allows you to capture any MIDI notes that you play in Stop mode or during playback and turn them into a MIDI part after the fact. This is possible because Cubase can capture MIDI input in buffer memory, even when not recording.

PROCEDURE

1. In the **Preferences** dialog, select **Record > MIDI**.
 2. Enable **Retrospective Record** and specify a **Retrospective Record Buffer Size**. This activates the buffering of MIDI input.
 3. In the MIDI track list, activate **Record Enable**.
 4. Play some MIDI material either in Stop mode or during playback.
 5. Select **Transport > Retrospective MIDI Record**.
-

RESULT

The content of the MIDI buffer is turned into a MIDI part on the record-enabled track, and the captured notes end up exactly where you played them in relation to the project.

RELATED LINKS

[Record - MIDI](#) on page 1032

Remaining Record Time

The **Max. Record Time** display lets you see how much time you have left for recording.

51h 25min

The available time depends on the current setup, for example, on the amount of tracks that are record-enabled, the sample rate for your project, and the available hard disk space.

- To open the display, select **Studio > More Options > Max. Record Time**.

NOTE

The remaining record time is also shown in the status line above the track list.

If you use individual record folders to store your tracks on different drives, the time display refers to the medium with the least storage space available.

Lock Record

The **Lock Record** function prevents you from accidentally deactivating the record mode.

- Select **File > Key Commands** and in the **Transport** category, assign key commands to the **Lock Record** and **Unlock Record** commands.

If **Lock Record** is activated and you want to enter Stop mode, a dialog opens in which you need to confirm that you want to stop recording. You can also use the **Unlock Record** key command first and then enter Stop mode as usual.

NOTE

An automatic punch out at the right locator position will be ignored in **Lock Record** mode.

Importing Audio and MIDI Files

You can add audio and MIDI files to your project by importing them.

Importing Audio Files

You can import compressed and uncompressed audio files in a variety of different formats. You can also import audio from audio CDs or extract the audio of video files.

RELATED LINKS


[Importing Media](#) on page 539

Setting Up Audio File Import Options

You can specify how audio files should be handled on import.

PROCEDURE

1. In the **Preferences** dialog, select **Editing > Audio**.
2. Select an option from the **On Import Audio Files** pop-up menu.



3. Click **OK**.
-

RESULT

The import settings are saved and will take effect when you import audio. If you selected **Open Options Dialog**, the **Import Options** dialog opens on every import and allows you to make your settings. If you selected **Use Settings**, the settings specified in the **On Import Audio Files** section of the **Preferences** dialog are used.

RELATED LINKS


[Import Options for Audio Files](#) on page 254

[On Import Audio Files Settings](#) on page 255

Import Options for Audio Files

The **Import Options** dialog allows you to make specific settings for the audio import.

- When you import audio files and **Open Options Dialog** is activated in the **On Import Audio Files** section of the **Preferences** dialog (**Editing—Audio** page), the **Import Options** dialog opens.



Copy Files to Working Directory

Copies the audio file to the **Audio** folder of the project, and has the clip refer to the copy.

Deactivate this option to have the clip refer to the original file in the original location. In this case, it is marked as “external” in the **Pool**.

Convert and Copy to Project if Needed

Converts the imported file if the sample rate or the bit depth differ from the settings in the **Project Setup** dialog.

Split Channels/Split Multi Channel Files

Splits stereo or multi channel audio files into a corresponding number of mono files, one for each channel, and copies the imported files to the **Audio** folder of the project.

Inserts the split files into the project and into the **Pool** as separate mono tracks.

The **Split File Name Format** pop-up menu allows you to specify how the split files are named. This allows for compatibility with other products when exchanging audio files.

Please, don't ask again


Always imports files according to the settings, without opening the dialog again. You can reset this option in the **Preferences** dialog (**Editing—Audio** page).

RELATED LINKS

[Setting Up Audio File Import Options](#) on page 254

On Import Audio Files Settings

You can set up standard settings that are performed automatically each time you import audio files.



- If you import audio files and **Use Settings** is activated in the **On Import Audio Files** section of the **Preferences** dialog (**Editing—Audio** page), the following settings are used for importing audio:

Copy Files to Working Directory

Copies the audio file to the **Audio** folder of the project, and has the clip refer to the copy.

Deactivate this option to have the clip refer to the original file in the original location. In this case, it is marked as “external” in the **Pool**.

Convert and Copy to Project if Needed

Converts the imported file if the sample rate or the bit depth differ from the settings in the **Project Setup** dialog.

Split Channels/Split Multi Channel Files

Splits stereo or multi channel audio files into a corresponding number of mono files, one for each channel, and copies the imported files to the **Audio** folder of the project.

Inserts the split files into the project and into the **Pool** as separate mono tracks.

The **Split File Name Format** pop-up menu allows you to specify how the split files are named. This allows for compatibility with other products when exchanging audio files.

Importing Audio Files

You can import uncompressed audio and compressed audio in several formats.

PROCEDURE

1. Select **File > Import > Audio File**.
2. In the file dialog that opens, locate and select the audio file and click **Open**.
3. Make your settings in the **Import Options** dialog.

NOTE

If **Use Settings** is activated in the **Preferences** dialog (**Editing—Audio** page), the corresponding import settings are used.

RESULT

In the **Project** window, an event referencing the audio file is inserted on the selected track at the project cursor position. If no track was selected, a new track is created.

A new audio clip is created and added to the **Pool**.

If you chose a compressed audio file other than FLAC, Cubase copies the original compressed file and converts it to wave format (Windows) or AIFF format (macOS).

NOTE

The resulting Wave/AIFF file is significantly larger than the original compressed file.

The imported file is placed in the **Audio** folder of the project.

RELATED LINKS

[Setting Up Audio File Import Options](#) on page 254

Supported Compressed Audio File Formats

EXAMPLE

The following compressed audio file formats are supported:

- **FLAC File**
This is an open source format that reduces the size of audio files by 50 to 60 % compared to regular Wave files. The files have the extension **.flac**.
- **MPEG**
This is a family of standards used for encoding audio-visual information such as movies, video, and music in a digital compressed format. Cubase can read MPEG Layer 2 and

MPEG Layer 3. MP3 files are highly compressed files that still provide good audio quality. The files have the extension **.mp3**.

- **Ogg Vorbis File**

This is an open source, patent-free audio encoding and streaming technology. The Ogg Vorbis encoder uses variable bit rate encoding. It offers compressed audio files of small size, but with comparatively high audio quality. The files have the extension **.ogg**.

- **Windows Media Audio File** (Windows only)

This is an audio file format defined by Microsoft Inc. WMA files can be decreased in size with no loss of audio quality. WMA Pro features the possibility of mixing down to 5.1 surround sound. The files have the extension **.wma**.

Importing Audio CD Tracks

You can import audio from audio CDs into Cubase projects.

PROCEDURE

1. Select **File > Import > Audio CD** to import the CD tracks into the **Project** window.
 2. Activate the **Copy** column for every audio file you want to import.
 3. Optional: Set a **Default Name** and a **Destination Folder** for the imported audio files.
 4. Click the **Copy** button to create a local copy of the audio files or sections.
 5. Click **OK**.
-

RESULT

The copied audio files are imported into the **Project** window and inserted on new tracks at the project cursor position. By default, imported audio CD tracks are saved as wave files (Windows) or AIFF files (macOS) in the **Audio** folder of the current project.

New audio clips are created and added to the **Pool**.

NOTE


You can also import audio files to the **Pool** only without importing them into the **Project** window.

RELATED LINKS

[Importing Media](#) on page 539

Import From Audio CD

The **Import from Audio CD** dialog allows you to specify how the CD tracks are imported.



Drive

Opens a pop-up menu that allows you to select the correct CD drive.

Speed

Allows you to select the data transfer speed (Windows only).

NOTE

While you normally want to use the fastest possible speed, you may have to select a slower speed for flawless audio extraction.

Eject CD

Opens the CD drive.

Secure Mode

Activates error checking and correction when reading the CD (Windows only).

Columns

The columns in the dialog have the following functions:

Copy

Activate this option for the tracks that you want to copy/import.

#

Shows the track number.

CD Track

The name of the CD track. On import, this is used as file name. It is provided automatically from CDDB, if available.

To rename a track, click the track name and type in a new name.

Length

The length of the audio CD track in minutes and seconds.

Size

The file size of the audio CD track in MB.

Copy Start


The start of the section that is imported. On the ruler, drag to the right to adjust this.

Copy End

The end of the section that is imported. On the ruler, drag to the left to adjust this.

The Ruler

The ruler has the following functions:



1 Play Tracks

Plays back the selected track from the start to the end or from the left marker to the right marker.

2 Stop Playback

Stops playback.

3 Play from Left Marker

Starts playback at the left marker.

4 Play to Right Marker

Starts playback some moments before the right marker and stops at the right marker.

5 Left Marker

Allows you to set the copy start manually.

6 Right Marker

Allows you to set the copy end manually.

Destination Folder

Allows you to select a folder for the imported files.

Copy

Copies the files.

Copied Files

Lists the files that you copied for import.

Importing Audio from Video Files

You can import the audio from a video file without importing the video itself.

PROCEDURE

1. Select **File > Import > Audio from Video File**.
 2. In the file dialog that opens, locate and select the video file, and click **Open**.
-

RESULT

The audio of the selected video file is extracted and converted to a wave file that is saved in the **Audio** folder.

A new audio clip is created and added to the **Pool**. In the **Project** window, an event referencing the audio file is inserted on the selected track at the project cursor position. If no track was selected, a new track is created.

RELATED LINKS

[Extract Audio from Video](#) on page 962

[Importing Video Files](#) on page 958

Importing ReCycle Files

You can import REX and REX 2 audio files created by ReCycle from Propellerhead Software. ReCycle slices a loop and creates separate samples of each beat, so that you can tempo match and edit a loop as if it was built of individual sounds.

PREREQUISITE

REX Shared Library is installed on your system.

PROCEDURE

1. Select an audio track and move the project cursor to where you want the imported file to start.
You probably want to import REX files to audio tracks that are set to musical time base, because this will allow you to change the tempo later on (having the imported REX file automatically adjust).
2. Select **File > Import > Audio File**.
3. In the file dialog, open the file type pop-up menu and select REX File or REX 2 File.
4. Select the file you want to import, and click **Open**.

RESULT

The file is imported and automatically adjusted to the current Cubase tempo.

The imported REX file consists of several events, one for each slice in the loop. The events are automatically placed in an audio part on the selected track and positioned so that the original internal timing of the loop is preserved.

AFTER COMPLETING THIS TASK

Open the part in the **Audio Part Editor** to edit each slice separately by muting, moving, and resizing events, adding effects and processing, for example.

You can also adjust the tempo and have the REX file automatically follow, provided that its track is set to a musical time base.

NOTE

You can achieve similar results by using Cubase's own loop slicing features.

RELATED LINKS


[Slices](#) on page 468

Importing MIDI Files

Cubase can import standard MIDI files. This allows you to transfer MIDI material to and from virtually any MIDI application on any platform.

Import Options for MIDI Files

The **Import Options** for MIDI files allow you to specify what data is included in imported MIDI files.



Extract First Patch

Converts the first **Program Change** and **Bank Select** events for each track to **Inspector** settings for the track.

Extract First Volume/Pan

Converts the first **MIDI Volume** and **Pan** events for each track to **Inspector** settings for the track.

Import Controller as Automation Tracks

Converts **MIDI Controller** events in the MIDI file to automation data for the MIDI tracks. If this option is deactivated, controller data for the MIDI parts will be imported.

Import to Left Locator

Aligns the imported MIDI file at the position of the left locator. If this option is deactivated, MIDI files start at the project start position. If you choose to have a new project created automatically, the MIDI file always starts at the project start position.

Import Markers

Imports Standard MIDI File Markers in the file and converts them to Cubase markers.

Import Dropped File as Single Part

Places the file on one track if you drag and drop a MIDI file into the project.

Ignore Master Track Events on Merge

Ignores tempo track data if you import a MIDI file into the current project. The imported MIDI file will play according to the current Tempo track in the project.

If this option is deactivated, the **Tempo Track Editor** will be adjusted according to the tempo information in the MIDI file.

Auto Dissolve Format 0

Automatically dissolves imported MIDI files of type 0. Each embedded MIDI channel in the file is placed on a separate track in the **Project** window.

If this option is deactivated, only one MIDI track is created. This track is set to MIDI channel **Any**, allowing all MIDI events to play back on their original channels. You can also use the **Dissolve Part** function on the **MIDI** menu to distribute the events onto different tracks (or lanes) with different MIDI channels at a later stage.

Destination

Allows you to specify what happens when you drag a MIDI file into the project:

- **MIDI Tracks** creates MIDI tracks for the imported file.
- **Instrument Tracks** creates instrument tracks for each MIDI channel in the MIDI file and lets the program automatically load appropriate presets.
- **HALion Sonic SE multi-timbral** creates several MIDI tracks, each routed to a separate instance of HALion Sonic SE in the **VST Instruments** window, and loads the appropriate presets.

Import Karaoke Lyrics as Text

Converts karaoke lyrics in the MIDI file to text that can be displayed in the **Score Editor**. If this option is deactivated, lyrics are only shown in the **List Editor**.

Importing MIDI Files

PROCEDURE

1. Select **File > Import > MIDI File**.
 2. Optional: If a project is open, choose if you want to create a new project. If you select **No**, the MIDI file is imported into the current project.
 3. In the file dialog that opens, locate and select the MIDI file and click **Open**.
-

RESULT

The MIDI file is imported. The result depends on the contents of the MIDI file and the setting you made in the **Import Options** section in the **Preferences** dialog (**MIDI—MIDI File** page).

It is also possible to import a MIDI file from disk by dragging and dropping it from the File Explorer/macOS Finder into the **Project** window. The **Import Options** apply as well.

RELATED LINKS

[Import Options for MIDI Files](#) on page 261
[Markers](#) on page 307

Yamaha XF Format

Cubase supports the Yamaha XF format. XF is an extension of the standard MIDI file format that allows you to save song-specific data with a MIDI file of type 0.

When importing a MIDI file containing XF data, this data is placed in parts on separate tracks called **XF Data**, **Chord Data**, or **SysEx Data**. You can edit such a part in the **List Editor** to add or change lyrics, for example.

IMPORTANT

Do not change the order of events within the XF data or the event data itself, unless you have a lot of experience with XF data.

Cubase can also export XF data as part of a MIDI file of type 0. If you do not want to export the XF data together with the MIDI data, mute or delete the tracks containing the XF data.

MIDI Loops

In Cubase, you can import MIDI loops.

To import MIDI loops, use the **MediaBay**. MIDI loops have the file extension `.midiloop`.

RELATED LINKS

[Importing MIDI Loops](#) on page 636

Quantizing MIDI and Audio

Quantizing means moving recorded audio or MIDI and positioning it on the nearest grid position that is musically relevant. Quantizing is designed to correct errors, but you can also use it in a creative way.

You can quantize audio and MIDI to a grid or to a groove. You can also quantize multiple audio tracks simultaneously.

Audio and MIDI can be quantized at the same time. However, what exactly happens during quantizing differs for audio and MIDI:

- Audio quantizing affects the audio event starts or the content of your audio.
- MIDI quantizing can affect the starts of MIDI events in a part, the MIDI event lengths, or the MIDI event ends.

NOTE

Quantizing is based on the original position of the events. Therefore, you can freely try out different quantize settings without the risk of destroying anything.

RELATED LINKS

[Quantizing Audio Event Starts](#) on page 266

[Quantizing Audio Event Lengths \(AudioWarp Quantizing\) \(Cubase Pro only\)](#) on page 267

[Quantizing MIDI Event Starts](#) on page 265

[Quantizing MIDI Event Lengths](#) on page 266

[Quantizing MIDI Event Ends](#) on page 266

Quantize Functions

The quantize functions are available in the **Edit** menu and in the **Snap/Quantize** section of the **Project** window toolbar.

Quantize Functions on the Edit Menu

Quantize

Quantizes audio or MIDI event starts.

Reset Quantize

Reverts your audio or MIDI to its original, unquantized state, and resets any length changes that you performed using the **Scale Length/Legato** slider in the **Quantize Panel**.

Quantize Panel

Opens the **Quantize Panel**.

Advanced Quantize

From this submenu you can select the following functions:

- **Quantize MIDI Event Lengths**
Cuts off the ends of selected MIDI events so that the events match the length quantize value. The start positions are kept.
- **Quantize MIDI Event Ends**
Moves the ends of MIDI events to the nearest grid positions.
- **Freeze MIDI Quantize**
Makes the start and end positions of MIDI events permanent. This function is useful in situations where you want to quantize a second time, based on the current quantized positions rather than the original positions.
- **Create Groove Quantize Preset**
Creates a groove quantize map based on hitpoints that you have created in the **Sample Editor**.

Quantize Functions on the Project Window Toolbar



- 1 **Iterative Quantize On/Off**
Activates/Deactivates iterative quantize.
- 2 **AudioWarp Quantize On/Off**
Activates AudioWarp quantizing.
- 3 **Quantize Presets**
Allows you to select a quantize or a groove preset.
- 4 **Apply Quantize**
Applies the quantize settings.
- 5 **Open Quantize Panel**
Opens the **Quantize Panel**.

Quantizing MIDI Event Starts

PREREQUISITE

You have set up a quantize grid on the **Quantize Presets** pop-up menu on the **Project** window toolbar.

PROCEDURE

1. Perform one of the following actions:
 - In the **Key Editor**, select the MIDI events that you want to quantize.
 - In the **Project** window, select a MIDI part.
2. Select **Edit > Quantize**.

RESULT

The starts of the selected MIDI events or all events of the selected MIDI part are quantized. Events that do not match exact note positions are moved to the closest grid position. The note lengths are maintained.

Quantizing MIDI Event Lengths

PREREQUISITE

You have set up a length quantize value on the **Length Quantize** pop-up menu on the **Key Editor** toolbar.

PROCEDURE

1. Perform one of the following actions:
 - In the **Key Editor**, select the MIDI events that you want to quantize.
 - In the **Project** window, select a MIDI part.
 2. Select **Edit > Advanced Quantize > Quantize MIDI Event Lengths**.
-

RESULT

The ends of the selected MIDI events are cut off so that the events match the length quantize value. The start positions are kept.

NOTE

If you have selected **Quantize Link**, the events are resized according to the grid that is set up in the **Quantize Presets** pop-up menu. The **Swing**, **Tuplet**, and **Catch Range** settings on the **Quantize Panel** are taken into account.

Quantizing MIDI Event Ends

PREREQUISITE

You have set up a quantize grid on the **Quantize Presets** pop-up menu on the **Project** window toolbar.

PROCEDURE

1. Perform one of the following actions:
 - In the **Key Editor**, select the MIDI events that you want to quantize.
 - In the **Project** window, select a MIDI part.
 2. Select **Edit > Advanced Quantize > Quantize MIDI Event Ends**.
-

RESULT

The ends of the MIDI events are moved to the nearest grid positions.

Quantizing Audio Event Starts

PREREQUISITE

You have set up a quantize grid on the **Quantize Presets** pop-up menu on the **Project** window toolbar.

PROCEDURE

1. In the **Project** window, select an audio event, a sliced loop, or an audio part.
 2. Select **Edit > Quantize**.
-

RESULT

The event snap point, or, if not available, the start of the audio event, is quantized. Event starts that do not match exact note positions are moved to the closest grid positions.

NOTE

If you use the **Quantize** function on an audio part, the starts of the events inside the part are quantized.

Quantizing Audio Event Lengths (AudioWarp Quantizing) (Cubase Pro only)

You can quantize an audio event or an audio selection range by applying time stretch to the content of the audio event.

PROCEDURE

1. Perform one of the following actions:
 - Select the audio event that you want to quantize.
 - Select a range of the event that you want to quantize.
 2. On the toolbar, activate **AudioWarp Quantize**.
 3. Perform one of the following actions:
 - Click **Quantize Presets**, and select a quantize grid preset from the pop-up menu.
 - Click **Open Quantize Panel**, and define the quantize grid with the available parameters.
 4. Select **Edit > Quantize**.
-

RESULT

The audio event is quantized, that is, its warp markers are aligned with the quantize grid by applying time stretch, and the audio sections between the warp markers are stretched or compressed to fit into the time interval that you set up on the **Quantize Presets** pop-up menu.

NOTE

If you use a quantize value of 1/4 on audio that is based on 16th notes, the warp markers at the 1/4 note positions are quantized to the grid, and the remaining warp markers are moved, keeping the relative distances between the warp markers.

RELATED LINKS

[Quantize Panel](#) on page 269

[Slices](#) on page 468

Quantizing Multiple Audio Tracks (Cubase Pro only)

You can quantize multiple audio tracks at the same time.

PROCEDURE

1. Select **Project > Add Track > Folder**.
2. Move all audio tracks that you want to quantize into the folder track.

NOTE

The audio on all tracks must have the same start and end positions.

3. Select the folder track and activate **Group Editing** in the track list.
 4. On the **Project** window toolbar, click **Open Quantize Panel** to open the **Quantize Panel**.
 5. Make your settings in the **Slice Rules** section of the **Quantize Panel**, and click **Slice**.
The audio events in the edit group are sliced.
 6. Make your settings in the quantize section of the **Quantize Panel**, and click **Quantize**.
The sliced events are quantized.
 7. Optional: to correct overlaps or gaps in the quantized audio, make your settings in the **Crossfades** section of the **Quantize Panel**, and click **Crossfade**.
-

RESULT

The audio events are quantized.

RELATED LINKS

[Quantize Panel](#) on page 269

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

AudioWarp Quantizing Multiple Audio Tracks (Cubase Pro only)

You can use warp markers for quantizing multiple audio tracks. However, AudioWarp quantizing does not maintain phase coherence.

PROCEDURE

1. Select **Project > Add Track > Folder**.
2. Move all audio tracks that you want to quantize into the folder track.

NOTE

The audio on all tracks must have the same start and end positions.

3. Select the folder track and activate **Group Editing** in the track list.
 4. On the **Project** window toolbar, activate **AudioWarp Quantize On/Off**.
 5. Click **Open Quantize Panel** to open the **Quantize Panel**.
 6. Make your settings in the **Warp Marker Creation Rules** section of the **Quantize Panel**, and click **Create**.
 7. Make your settings in the quantize section of the **Quantize Panel**, and click **Quantize**.
-

RESULT

AudioWarp quantizing is applied to all tracks in the edit group.

RELATED LINKS

[Quantize Panel](#) on page 269


[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Quantize Panel

The **Quantize Panel** allows you to define how to quantize audio or MIDI to the grid or to a groove. Depending on what method you choose, different parameters are shown.


To open the **Quantize Panel**, perform one of the following actions:

- Click **Open Quantize Panel** on the toolbar.
- Select **Edit > Quantize Panel**.



Quantize Presets

To the top of the **Quantize Panel** the quantize presets are shown. Here, you can load and save presets that include all settings for quantizing.



Select Preset

Allows you to select a preset.

Save Preset

Allows you to save the current settings as a preset, so that they become available on all **Quantize Presets** pop-up menus.

Remove Preset

Allows you to remove the selected preset.

Rename Preset

Opens a dialog where you can rename the selected preset.

Restore Factory Presets

Allows you to restore the factory presets.

Creating Groove Quantize Presets

You can create a groove quantize map based on hitpoints that you have created in the **Sample Editor**.

PROCEDURE

1. In the **Project** window, double-click the audio event from which you want to extract the timing.
The **Sample Editor** opens.
2. Open the **Hitpoints** section.
The hitpoints for the audio event are detected and displayed automatically.
3. Click **Create Groove**.
The groove is extracted.

RESULT

The groove is extracted from the audio event and made available in the **Quantize Presets** pop-up menu on the **Project** window toolbar.

AFTER COMPLETING THIS TASK

Open the **Quantize Panel** and save the groove as a preset.

RELATED LINKS


[Creating a Groove Quantize Map](#) on page 470

[Quantize Presets](#) on page 269

Options For Quantizing to a Musical Grid

You can use the musical grid to quantize your recorded music.

- To access the options for quantizing to a musical grid, select a musical time format from the **Select Preset** pop-up menu.



The following options become available:

Grid

Allows you to select the basic value for the quantize grid.

Swing

Offsets every second position in the grid, creating a swing or shuffle feel.

NOTE

Swing is only available if **Grid** is set to a straight value and **Tuplet** is deactivated.

Catch Range

Allows you to set a value that determines that quantizing affects only audio or MIDI within the set distance from the grid lines. This is reflected in the grid display.

Non-Quantize

Creates a safe zone before and after the quantize positions. If you specify a distance in ticks (120 ticks = one 16th note), events that lie within this zone are not quantized. This way, slight variations are kept.

Grid Display

Shows the quantize grid. Quantized audio or MIDI is moved to the positions indicated by the vertical grid lines.

Tuplet

Creates rhythmically more complex grids by dividing the grid into smaller steps, and thereby creating n-tuplets.

Randomize

Allows you to set a distance in ticks, so that your audio or MIDI is quantized to random positions within the specified distance from the quantize grid. This allows for

slight variations and, at the same time, prevents your audio or MIDI from ending up too far away from the grid.

iQ Mode

Applies a loose quantization so that your audio or MIDI moves only part of the way to the closest quantize grid position. The **Iterative Strength** value to the right determines how close your audio or MIDI moves towards the grid.

NOTE

Iterative quantizing is based on the current, quantized positions and not on the original event positions. You can repeatedly use the **iQ** mode to gradually move your audio or MIDI closer to the quantize grid until you have found the right timing.

AudioWarp

Quantizes the content of your audio event by applying time stretch. The warp markers are aligned with the defined quantize grid.

MIDI CC

Moves controllers related to MIDI notes (pitchbend, etc.) automatically with the notes when these are quantized.

Reset Quantize

Resets your audio or MIDI to its original, unquantized state.

IMPORTANT

This function has no effect on an event that was moved manually.

Auto

Applies any changes immediately to the selected parts or events. A way of using this feature is to set up a playback loop and adjust the settings until you are satisfied with the result.

Quantize


Applies your settings.

Options for Quantizing to a Groove

You can generate a timing grid from a MIDI part or an audio loop, and use this groove to quantize your recorded music. This way, you can recreate the rhythmic feel of this specific event or part.

To access the options for quantizing to a groove, select a MIDI part, from an audio loop, an audio event with hitpoints, or sliced audio, and perform one of the following actions:

- Drag the part or event and drop it on the grid display in the middle of the **Quantize Panel**.
- Select **Edit > Advanced Quantize > Create Groove Quantize Preset**.



The following options become available:

Position

Determines how much the timing of the groove affects the music.

Velocity (MIDI Only)

Determines how much the velocity values within the groove affect the music.

NOTE

Not all grooves contain velocity information.

Length (MIDI Only)

Allows you to specify how much the lengths of the notes are affected by the groove.

NOTE

For drums, the Length setting is ignored.

Non-Q

Allows you to create a safe zone before and after the quantize positions. If you specify a distance in ticks (120 ticks = one 16th note), events that lie within this zone are not quantized. This way, slight variations are kept.

Grid Display

Shows the quantize grid. Quantized audio or MIDI is moved to the positions indicated by the vertical grid lines.

Pre-Q

Allows you to select a musical grid to which you can quantize your audio or MIDI first. This gets the notes closer to their groove destination.

NOTE

If you apply a shuffle groove to a 16th-note pattern, for example, set up a pre-quantize value of 16 to straighten up the timing before applying the groove quantizing.

Max. Move

Allows you to select a note value to specify a maximum distance that the audio or MIDI is moved.

Orig. Position

Sets the original starting position of the quantized material as starting point of the quantizing. This allows you to synchronize material that does not start from bar 1 of the project.

Randomize

Allows you to set a distance in ticks so that your audio or MIDI is quantized to random positions within the specified distance from the quantize grid. This allows for slight variations and, at the same time, prevents your audio or MIDI from ending up too far away from the grid.

iQ Mode

Applies a loose quantization so that your audio or MIDI moves only part of the way to the closest quantize grid position. The **Iterative Strength** value to the right determines how close your audio or MIDI moves towards the grid.

NOTE

Iterative quantizing is based on the current, quantized positions and not on the original event positions. You can repeatedly use the **iQ** mode to gradually move your audio or MIDI closer to the quantize grid until you have found the right timing.

AudioWarp

Quantizes the content of your audio event by applying time stretch. The warp markers are aligned with the defined quantize grid.

MIDI CC

Moves controllers related to MIDI notes (pitchbend, etc.) automatically with the notes when these are quantized.

Reset Quantize

Resets your audio or MIDI to its original, unquantized state.

IMPORTANT

This function has no effect on an event that was moved manually.

Auto

Applies any changes immediately to the selected parts or events. A way of using this feature is to set up a playback loop and adjust the settings until you are satisfied with the result.

Quantize


Applies your settings.

RELATED LINKS

[Creating Groove Quantize Presets](#) on page 270

Options for Quantizing Multiple Audio Tracks

If you quantize multiple audio tracks, the **Slice Rules** section becomes available in the **Quantize Panel**. Here, you determine how the audio events are sliced at the hitpoints.



- To access the **Slice Rules** section, move your audio tracks to a folder track, activate **Group Editing**, and open the **Quantize Panel**.

Hitpoint Tracks

Lists all audio tracks of your edit group that have hitpoints.

Priority

Click and drag to the right or to the left to specify a priority. The hitpoints of the track with the highest priority determine slice positions for the audio on all tracks. If the zoom factor is high enough, cutting positions are marked in the **Project** window by vertical lines.

Range

Allows you to specify the distance in which two hitpoints on different tracks are considered to mark the same beat.

Offset

Allows you to set an offset that determines how far before the actual hitpoint position an audio event is sliced. This allows for slight variations of the cutting position and is useful if you want to create crossfades at the slice positions. Furthermore, it helps to avoid cutting off signals on tracks that do not contain any hitpoints.

AudioWarp Quantize On/Off

Activate this button to quantize the content of your audio event by applying time stretch. This enables the **Warp Marker Creation Rules** section that allows you to specify a priority. The hitpoints of the track with the highest priority determines warp marker positions for the audio on all tracks.

Slice

Slices all audio events of the edit group, and sets the event snap points to the position of the hitpoint with the highest priority.

Reset

Undoes the slicing and restores the original state of the audio events.

RELATED LINKS

[Options for AudioWarp Quantizing Multiple Audio Tracks](#) on page 276

[Crossfades Section](#) on page 276

[AudioWarp Quantizing Multiple Audio Tracks \(Cubase Pro only\)](#) on page 268

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Crossfades Section

The **Crossfades** section becomes available after you have sliced the audio events. The functions in this section allow you to correct the overlaps or the gaps that might appear due to the re-positioning of your audio.



Clicking **Crossfade** cuts the end of the first event at the start position of the following event (in case of overlaps), and stretches the second event until it starts at the end of the previous event (in case of gaps).

In some cases, you might want to achieve seamless transitions, applying crossfades after closing the gaps. For this purpose, use the following parameters:

Open Crossfade Editor

Opens the **Crossfade** editor, where you can specify curve kind, length, and other parameters for your crossfades.

Nudge Crossfade Left/Right

Moves the fade area in the audio event to the left or to the right in steps of one millisecond. This is useful if the **Offset** value in the **Slice Rules** section was not high enough, and you want to avoid that the crossfade cuts an attack.

Length

Specifies the length of the crossfade area.

RELATED LINKS

[Crossfade Editor](#) on page 284

Options for AudioWarp Quantizing Multiple Audio Tracks

The **Warp Marker Creation Rules** section becomes available when you activate AudioWarp quantizing for multiple audio tracks.



Priority

In this column, you can define a priority for each track. The track with the highest priority defines where the warp markers are created.

If you set up the same priority for several tracks, the warp marker position is defined by the track that contains the first hitpoint within the specified range. This is decided for each warp marker position anew.

- To specify a priority, click and drag to the right or to the left.
If no star is shown, the hitpoints on the corresponding track are not taken into account.

Range

Two hitpoints on different tracks are considered to mark the same beat if they are located within a certain distance from each other. The **Range** parameter specifies this distance. The following rules apply:

- If one of the tracks has a higher priority, its hitpoint is used to create the warp marker.
- If the tracks have the same priority, the first hitpoint in the range is used.

Reset

Undoes the creation of warp markers.

AudioWarp Quantize On/Off

Activates/deactivates AudioWarp quantizing. This enables the **Slice Rules** section.

Create

Creates warp markers for all the tracks.

RELATED LINKS

[Options for Quantizing Multiple Audio Tracks](#) on page 274

[AudioWarp Quantizing Multiple Audio Tracks \(Cubase Pro only\)](#) on page 268

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Fades, Crossfades, and Envelopes

Fades allow you to gradually increase or decrease the volume at the start or end of audio events or audio clips, and to create smooth transitions.

You can create the following fades:

- **Fade ins/fade outs**

Fade ins and fade outs allow you to gradually increase or decrease the volume of audio events or audio clips. Fade ins and fade outs can be either event-based or clip-based.

Event-based fades are calculated in real time when you play back audio events. You can create different fade curves for several events, even if they refer to the same audio clip.

NOTE

The more event-based fades you apply, the more processing power is used.

Clip-based fades are applied to the audio clip. Events that refer to the same clip will have the same fades.

- **Crossfades**

Crossfades allow you to create smooth transitions for consecutive audio events on the same track. Crossfades are always event-based.

- **Auto fades**

Auto fades allow you to automatically apply short fade ins and fade outs to the events on specific audio tracks. You can also apply them globally on all audio tracks. This creates smooth transitions between events.

- **Event envelopes**

Event envelopes are volume curves for audio events or audio clips. They allow for volume changes not only at the start or the end, but also within the audio or clip. They can be either event-based or clip-based.

RELATED LINKS

[Event-Based Fades](#) on page 278

[Creating Clip-Based Fades](#) on page 282

[Crossfades](#) on page 283

[Auto Fades and Crossfades](#) on page 285

[Event Envelopes](#) on page 288

Event-Based Fades

You can create event-based fade ins and fade outs. These are calculated in real time when you play back audio events. You can create different fade curves for several events, even if they refer to the same audio clip.

There are several ways to create event-based fades:

- By using the event handles

- By using range selections

You can edit event-based fades in the **Fade** dialogs.

RELATED LINKS

[Creating and Editing Fades with the Handles](#) on page 279

[Creating and Editing Fades with the Range Selection Tool](#) on page 280

[Fade Dialog for Event-Based Fades](#) on page 281


Creating and Editing Fades with the Handles

You can create and edit event-based fade ins and fade outs using the event handles. This gives you a visual feedback and allows you to apply the same fade type to several selected events.

PROCEDURE

1. Select the audio events for which you want to create fades and point at one of them with the mouse.

Triangular fade handles become visible in the upper left and right corners.



2. Perform one of the following actions:

- Drag the left fade handle to the right to create a fade in.



- Drag the right fade handle to the left to create a fade out.

RESULT

The fade is applied and shown in the event waveform. If you select multiple events, the same fade is applied to all selected events.

NOTE

You can change the length of the fades at any time by dragging the handles.


Event Handles

Audio events have a fade-in and a fade-out handle, as well as a volume handle. These handles provide a quick way to change the fade length or the volume of events in the **Project** window.

Event handles become visible if you point the mouse at an event or if you select events.

NOTE

To show event handles and fade curves always and not only when you point at events, activate **Show Event Volume Curves Always** in the **Preferences** dialog (**Event Display—Audio** page).




In the upper left and right corners you find triangular fade handles that allow you to change the fade-in or fade-out length. In the top middle you find a square handle that allows you to change the volume.

- To change the fade-in length, drag the fade handle in the upper left to the right or to the left.
- To change the fade-out length, drag the fade handle in the upper right to the left or to the right.
- To change the volume, drag the volume handle in the top middle up or down.

Fade and volume changes are reflected in the event waveform and on the info line.

NOTE

To change the event volume and the fades with the mouse wheel, activate **Use Mouse Wheel for Event Volume and Fades** in the **Preferences** dialog (**Editing—Audio** page). When you press **Shift** while moving the mouse wheel, and position the mouse pointer somewhere in the left half of the event, the fade in end point is moved. When the mouse pointer is in the right half of the event, the fade out start point is moved.



Creating and Editing Fades with the Range Selection Tool

You can create and edit event-based fades with the **Range Selection** tool. This allows you to apply a fade in and a fade out at the same time. Using the **Range Selection** tool is also useful if you want to create fades for multiple audio events on separate tracks.

PROCEDURE

1. On the **Project** window toolbar, select the **Range Selection** tool.
2. Perform one of the following actions:
 - To create a fade in that starts at the event start, select a range that starts at the event start.
 - To create a fade out that ends at the event end, select a range that ends at the event end.
 - To create a fade in and a fade out, select a range in the middle of the event.
 - To create fades on multiple tracks, select a range that spans multiple audio events on multiple audio tracks.
3. Select **Audio > Adjust Fades to Range**.

Removing Event-Based Fades


You can remove event-based fades for a whole event or for a range.

PROCEDURE

1. Perform one of the following actions:
 - To remove the fades for an event, select the event with the **Object Selection** tool.
 - To remove the fades for a range, select the fade area with the **Range Selection** tool.

2. Select **Audio > Remove Fades**.

Fade Dialog for Event-Based Fades



- To open the dialog for event-based fades, create a fade for one or more audio events, select the events and select **Audio > Open Fade Editor(s)**.

NOTE

If you select several events, you can adjust the fade curves for all selected events at the same time. This is useful if you want to apply the same type of fade in to more than one event, etc.

The available options are:

- 1 **Spline Interpolation**
Applies a spline interpolation to the curve.
- 2 **Damped Spline Interpolation**
Applies a damped spline interpolation to the curve.
- 3 **Linear Interpolation**
Applies a linear interpolation to the curve.
- 4 **Fade display**
Shows the shape of the fade curve. The resulting waveform shape is shown darker, the current waveform shape is shown lighter.
 - To add points, click the curve.
 - To change the curve shape, click and drag existing points.
 - To remove a point from the curve, drag it outside the display.
- 5 **Restore**
Click this button to cancel any changes you have made since opening the dialog.
- 6 **Fade Length field**
Use this field to enter fade lengths numerically. The format of values displayed here is determined by the time display in the **Transport** panel.
 - If you activate **Apply Length**, the value entered in the **Fade Length** value field is used when clicking **Apply** or **OK**.
 - If you set the current fade as the default fade, the length value is included as part of the default settings.
- 7 **Presets**
Allows you to set up presets for fade-in or fade-out curves.

- To apply a stored preset, select it from the pop-up menu.
- To remove a stored preset, select it from the pop-up menu and click **Remove**.

8 As Default

Click this button to save the current settings as default fade.

9 Shape buttons

Give you quick access to some common curve shapes.

Creating Clip-Based Fades

You can create and edit clip-based fade ins and fade outs using **Direct Offline Processing**. These fades are applied to the audio clip. Events that refer to the same clip get the same fades.

PREREQUISITE

Cubase Pro only: In the **Direct Offline Processing** window, **Auto Apply** is activated.

PROCEDURE

1. In the **Project** window, select one or more audio events or a range for which you want to create a fade.
The length of your selection determines the length of the fade area.
 2. Perform one of the following actions:
 - To create a fade in, select **Audio > Processes > Fade In**.
 - To create a fade out, select **Audio > Processes > Fade Out**.
 3. On the **Direct Offline Processing** process panel, click the **Curve Kind** buttons to specify a fade curve, or click and drag with the mouse in the curve display to draw in a curve.
 4. Optional: Activate **Audition** to hear the effect of the specified fade on the selected audio event.
-

RESULT


The fade is applied to the audio. You can remove or modify the fades at any time using the **Direct Offline Processing** window.

RELATED LINKS

- [Direct Offline Processing](#) on page 416
- [Fade In/Fade Out](#) on page 425
- [On Processing Shared Clips](#) on page 282

On Processing Shared Clips

If several events refer to the same audio clip, this clip is a shared clip. If you edit one of the events that refer to a shared clip, you can decide if you want to apply the processing to all events referring to this clip.



Continue

Click **Continue** to apply the processing to all events that refer to the audio clip.

New Version


Click **New Version** to create a separate, new version of the audio clip for the selected event.

Crossfades

Crossfades allow you to create smooth transitions for consecutive audio events on the same track. Crossfades are always event-based.

You can only create crossfades if the consecutive events or their respective clips overlap.

- If the audio events overlap, a crossfade of the default shape (linear, symmetric) is applied in the overlapping area.



NOTE

You can edit the default crossfade length and shape in the **Crossfade** editor.

- If the respective audio clips overlap, the two events are resized so that they overlap, and a crossfade of the default length and shape is applied in the overlapping area.
- If neither the audio events nor the clips do overlap, a crossfade cannot be created.

RELATED LINKS

[Crossfade Editor](#) on page 284

Creating Crossfades

PROCEDURE

1. Perform one of the following actions:
 - To create a crossfade between two events, select the **Object Selection** tool, and select two consecutive audio events.
 - To create a crossfade to a selected range between two events, select the **Range Selection** tool, and select a range covering the area where you want to apply a crossfade.
2. Select **Audio > Crossfade** or use the key command **X**.

RESULT

The crossfade is applied.

Changing the Crossfade Length

PROCEDURE


1. Select the **Range Selection** tool.
2. Select a range between two events that covers the length of the crossfade you want to apply.
3. Select **Audio > Adjust Fades to Range**.

RESULT

The crossfade length is adjusted to the selected range.

Crossfade Editor

The **Crossfade** editor allows you to edit crossfades. It contains fade-in and fade-out curve settings, and common settings.



- To open the **Crossfade** editor, select one or both crossfaded events, and select **Audio > Crossfade**, or double-click the crossfade zone.

Fade curve displays

Shows the shape of the fade-out and fade-in curve, respectively.

- To add points, click a curve.
- To change the fade shape, click and drag existing points.
- To remove a point, drag a point outside the display.

Curve Kind and Shape buttons

Determine whether the corresponding fade curve uses **Spline Interpolation** (left button), **Damped Spline Interpolation** (middle button) or **Linear Interpolation** (right button).



The curve shape buttons give you quick access to some common curve shapes.



Equal Gain

Adjusts the fade curves so that the summed fade-in and fade-out amplitudes are the same all along the crossfade region. This is often suitable for short crossfades.

Equal Power

Adjusts the fade curves so that the energy (power) of the crossfade is constant all along the crossfade region.

Equal Power curves have only one editable curve point. You cannot change the curve shape if this mode is selected.

Play buttons

- To audition the whole crossfade, click **Play Crossfade**.
- To audition the fade-out part of the crossfade, click **Play Fade Out**.
- To audition the fade-in part of the crossfade, click **Play Fade In**.

You can set up key commands for this in the following categories of the **Key Commands** dialog.

Pre-roll and Post-roll

- To start playback before the fade area, activate **Use pre-roll**.
- To stop playback after the fade area, activate **Use post-roll**.

- To adjust the pre-roll time, use the **Pre-roll Amount** value field.
- To adjust the post-roll time, use the **Post-roll Amount** value field.

Audition Level

Allows you to set the audition level.

Length

Specifies the length of the crossfade area. Cubase tries to center the crossfade, that is, the length change will be applied equally to both sides. To be able to resize a crossfade, it must be possible to resize the corresponding event. For example, if the fade out event already plays its audio clip to the end, its end point cannot be moved any further to the right.

Presets

Click **Store** to the right of the **Presets** pop-up menu to store the crossfade settings so that you can apply them to other events.

- To remove a preset, select it on the pop-up menu and click **Delete**.

Default buttons

Click **As Default** to store the current settings as default. Default settings are used whenever you create new crossfades.

Click **Recall Default** to apply the curves and settings of the default crossfade to the **Crossfade** editor.

RELATED LINKS

[Key Commands](#) on page 973

[Event Handles](#) on page 279

[Auto-Scroll](#) on page 221

Removing Crossfades

PROCEDURE

1. Perform one of the following actions:
 - Select the **Object Selection** tool and select one of the crossfaded events.
 - Select the **Range Selection** tool and select the crossfades you want to remove.
 2. Select **Audio > Remove Fades**.
-

RESULT

The selected crossfades are removed.

NOTE

You can also remove a crossfade by clicking and dragging it outside the track.

Auto Fades and Crossfades

Cubase features an **Auto Fade** function that can be set both globally and separately for each audio track. Auto fades allow you to create smoother transitions between events by applying fade ins and fade outs with a length between 1 and 500 ms.

IMPORTANT


As event-based fades are calculated in real time during playback, applying auto fades to a higher number of audio events results in a higher demand on the processor.

NOTE

Auto fades are not indicated by fade lines.

Auto Fades Dialog


The **Auto Fades** dialog allows you to set up auto fades and crossfades for the whole project, or separately for each audio track.



- To open the global **Auto Fades** dialog, select **Project > Auto Fades Settings**.
- To open the **Auto Fades** dialog for a track, right-click in the track list and select **Auto Fades Settings**.

1 Fades

Click this tab to show the settings for auto fades.




The **Curve Kind** buttons allow you to determine whether the corresponding fade curve uses **Spline Interpolation** (left button), **Damped Spline Interpolation** (middle button) or **Linear Interpolation** (right button).

The curve shape buttons give you quick access to common curve shapes.

2 Crossfades

Click this tab to show the settings for auto crossfades.



Equal Gain allows you to adjust the fade curves so that the summed fade in and fade out amplitudes are the same all along the crossfade region.

Equal Power allows you to adjust the fade curves so that the energy (power) of the crossfade is constant all along the crossfade region.

3 Length

Allows you to specify the length of the auto fades or crossfades.

4 Auto Fade In

Allows you to activate auto fade ins.

5 Auto Fade Out

Allows you to activate auto fade outs.

6 Auto Crossfades

Allows you to activate auto crossfades.

7 As Default

Allows you to save your settings as default.

8 Use Project Settings

This is only available if you opened the **Auto Fades** dialog for individual tracks. Deactivate this to set up and apply the settings to individual tracks only. If you want a track with individual auto fade settings to use the global settings again, activate **Use Project Settings**.

Making Global Auto Fade Settings

PROCEDURE

1. Select **Project > Auto Fades Settings**.
This opens the **Auto Fades** dialog for the project.
 2. Set up the auto fades as desired.
 3. Click **OK**.
-

RELATED LINKS

[Fade Dialog for Event-Based Fades](#) on page 281

[Crossfade Editor](#) on page 284

Making Auto Fade Settings for Individual Tracks

As auto fades use computing power, you might consider to turn auto fades off globally and activate them only for individual tracks.

PROCEDURE

1. Perform one of the following actions:
 - Right-click the track in the track list, and from the context menu, select **Auto Fades Settings**.
 - Select the track, and in the Inspector, click **Auto Fades Settings**.


The **Auto Fades** dialog for the track opens.

2. Deactivate **Use Project Settings**.
Any settings you now make are applied to the track only.
 3. Set up the auto fades.
 4. Click **OK**.
-

Event Envelopes

Event envelopes are volume curves for audio events. They allow you to create volume changes within the event, not only at the start or end.

On the event envelopes, you can create volume changes by adding curve points with the **Draw** tool.




The envelope curve is a part of the audio event. If you move or copy the event, the event envelope follows.

Creating Event-Based Volume Changes

PROCEDURE

1. Zoom in on the event so that you can view its waveform properly.
2. Select the **Draw** tool and click at the position in the event where you want to change the volume.
3. Click with the **Draw** tool.



A curve point is added to the envelope curve.

4. Drag the curve point to adjust the volume curve.
-

RESULT

The volume change is created. The waveform image of the event changes according to the volume change.

Removing Event Envelopes

PROCEDURE

- Perform one of the following actions:
 - To remove a curve point from the envelope, click on it and drag it outside the event.

- To remove an event envelope curve from a selected event, select **Audio > Remove Volume Curve**.
-

Creating Clip-Based Volume Changes

PROCEDURE

1. In the **Project** window, select the event.
 2. Select **Audio > Process > Envelope**.
 3. In the **Envelope** dialog, make your settings, and click **Process**.
-

RESULT

The volume change is created. The waveform image of the event changes according to the volume change.

RELATED LINKS

[Envelope](#) on page 425

Arranger Track

The arranger functions in Cubase allow you to work in a non-linear fashion. Using an arranger track allows you to specify how and when specific sections are played back, even in live performances. This way, you do not need to move, copy, and paste events in the **Project** window.

NOTE

There can be only one arranger track in a project.

To use the arranger functions, you must add an arranger track and define arranger events. Arranger events can be of any length. They can overlap and are not bound to the start or end of existing events and parts. You can order them in a list, and add repeats as desired.



You can edit arranger events using the standard techniques. Copies from arranger events are independent from the original event.

You can create several arranger chains that allow you to save different versions of a song within the project.

You can flatten arranger chains to convert them into a linear project.

RELATED LINKS

[Adding Arranger Events on the Arranger Track](#) on page 290

[Setting up an Arranger Chain and Adding Events](#) on page 294

[Flattening the Arranger Chain](#) on page 295

Adding Arranger Events on the Arranger Track

On the arranger track, you can add arranger events that define specific sections of the project.

PREREQUISITE

Snap is activated, and **Snap Type** is set to **Events**.

PROCEDURE

1. Select **Project > Add Track > Arranger**.
The arranger track is added.
2. Select the **Draw** tool and draw an arranger event on the arranger track.
An arranger event is added.
3. Draw as many events as you need.

RESULT

The arranger events are added to your project.

AFTER COMPLETING THIS TASK

Use the functions of the **Arranger Editor** to arrange the events.

RELATED LINKS

[Setting up an Arranger Chain and Adding Events](#) on page 294

[Snap Function](#) on page 78

[Snap Types](#) on page 79

Renaming Arranger Events

When you add arranger events, they are automatically named in alphabetical order. You can change the names so that they reflect the structure of your project, such as Intro, Chorus, Bridge, for example.


PROCEDURE

1. Select the arranger event that you want to rename.
2. Perform one of the following actions:
 - Select the event name on the info line.
 - Hold down **Alt** and double-click the name in the arranger chain.
3. Enter a new name.

Arranger Editor

The **Arranger Editor** allows you to set up arranger chains.

To open the **Arranger Editor**, click **e** in the **Inspector** or in the track list.



- 1 Arranger Controls**
Shows the transport buttons, the arranger transport buttons, and the arranger tools.
- 2 Current Arranger Chain**

NOTE

Initially, the arranger chain is empty. To fill it up, you must add events from the **Arranger Events** list.

Shows the order in which the events are played back, from top to bottom, and how many times they are repeated.


- 3 Arranger Events**
Lists the available arranger events in the order they appear on the timeline.

Arranger Controls

The **Arranger Controls** are shown in the **Arranger Editor**.

NOTE

Some of these controls are also available in the **Arranger Controls** section of the **Project** window toolbar, and on the **Transport** panel.



- 1 Stop/Play**
Stops/Starts playback.
- 2 Previous Chain Step**
Navigates to the previous entry in the current arranger chain list.
- 3 Next Chain Step**
Navigates to the next entry in the current arranger chain list.
- 4 First Repeat of Current Chain Step**
Navigates to the first repeat of the current entry in the current arranger chain list.
- 5 Last Repeat of Current Chain Step**
Navigates to the last repeat of the current entry in the current arranger chain list.
- 6 Activate Arranger Mode**
Activates playback in arranger mode.
- 7 Select Active Chain**
Allows you to select and activate an arranger chain.
- 8 Rename Current Chain**
Allows you to rename the current arranger chain.
- 9 Create New Chain**
Creates a new, empty arranger chain.
- 10 Duplicate Current Chain**
Creates a duplicate of the current arranger chain, containing the same events.
- 11 Remove Current Chain**

Removes the selected arranger chain. This is only available if you have created more than one arranger chain.

12 Flatten

Converts the current arranger chain into a linear project.

13 Flatten (with Options & Preferences)

Allows you to set up the flatten options.

Arranger Chain Repeat Modes

The **Arranger Editor** features a function that allows you to repeat and loop your arranger events. This way, you can create a sketch of a song structure.

To select one of the repeat modes, click the **Mode** column in the **Current Arranger Chain** list.

1 Normal

Plays back the arranger chain exactly the way you set it up.

2 Repeat forever

Repeats the current arranger event in a loop until you click another event in the **Arranger Editor** or until you click **Play** once again.

3 Pause after Repeats


Pauses playback after all repeats of the current arranger event have been played back.

NOTE

During playback, the **Counter** column indicates which repetition of the event is playing.

Flattening Options & Preferences

To activate the flattening options, click **Flatten (with Options & Preferences)**.



In the **Source** section, you can specify which arranger chains are flattened.

Current Chain

Flattens the current chain only.

Checked Chains

Opens a list of the available arranger chains where you can activate the arranger tracks that you want to flatten.

All Chains

Flattens all arranger chains of the current project.

The **Destination** section allows you to choose where the result of the flattening is saved.

Current Project

This is only available if **Source** is set to **Current Chain**. Activate this option if you want to save the flattened chain in the current project.

New Project

Allows you to flatten one or more chains in a new project with the following naming options:

- **Append Chain Name**
Appends the chain names to the project name.
- **Use Chain Name**
Names the new projects after the current arranger chains.
- **Add Number**
Names the new projects after the old ones and adds a number.

The **Options** section contains further settings.

Keep Arranger Track

Keeps the arranger track after flattening. Activate **Rename Arranger Events** to append numbers to the events.

Make Real Event Copies

Allows you to create real copies of the arranger track instead of shared copies.

Don't Split Events

Excludes MIDI notes that start before or are longer than the arranger event. Only MIDI notes that begin and end inside the arranger event are taken into account.

Open New Projects

Creates a new project for every flattened arranger chain. If you activate **Cascade New Projects**, the opened projects are cascaded.

RELATED LINKS

[Flattening the Arranger Chain](#) on page 295

Setting up an Arranger Chain and Adding Events

In the **Arranger Editor** you can set up arranger chains and add events to them.

PROCEDURE

1. Click **e** to open the **Arranger Editor**.
2. Activate **Activate Arranger Mode**.



3. Perform one of the following actions to add arranger events to the arranger chain:
 - Double-click an event in the **Arranger Events** list.
 - Select one or more events in the **Arranger Events** list, right-click, and select **Append Selected In Arranger Chain**.
 - Drag an arranger event from the **Arranger Events** list and drop it in the **Current Arranger Chain** list.
 - Drag an arranger event from the **Project** window and drop it in the **Current Arranger Chain** list.
 4. Click **Play**.
-

RESULT

The arranger events are played back in the order that you specified in the arranger chain.

RELATED LINKS

[Arranger Chain Repeat Modes](#) on page 293

Adding a New Arranger Chain

You can create several arranger chains in order to set up alternative versions for playback.

PREREQUISITE

Arranger Mode is activated.

PROCEDURE

1. Open the **Arranger Editor**.
2. Click **Create New Chain**.

RESULT

A new, empty arranger chain is activated. This is reflected by a new name in the **Select Active Chain** pop-up menu and a new, empty **Current Arranger Chain** list.

Editing Arranger Events in the Arranger Chain

In the **Current Arranger Chain** list, you can edit your arranger events.

You can perform the following actions:

- To select multiple events, **Ctrl/Cmd**-click or **Shift**-click them.
- To move events in the list, drag them up or down.
- To copy events, select them, hold **Alt** and drag.
- To repeat events, click in the **Repeats** column and enter the number of repeats.
- To specify how the event is repeated, click in the **Mode** column and select a **Repeat Mode** from the pop-up menu.
- To move the playback position to the start of an event, click the arrow to the left of the event.
- To remove an event from the list, right-click on it, and from the context menu, select **Remove Touched**.
- To remove several events, select them, right-click, and from the context menu, select **Remove Selected**.

RELATED LINKS

[Arranger Chain Repeat Modes](#) on page 293

Flattening the Arranger Chain

When you have set up an arranger chain that you like, and you are sure that you do not want to edit it any more, you can convert it to a linear project.

PREREQUISITE

You have saved a copy of the project before flattening the arranger chain.

NOTE


Flattening the arranger chain may remove events and parts from the project. Only use **Flatten** when you know you do not want to edit the arranger track/chain any more. If in doubt, save a copy of the project before flattening the arranger chain.

PROCEDURE

1. Select the arranger chain that you want to convert into a linear project.
2. Optional: Click **Flatten (with Options & Preferences)**



3. Optional: Activate the desired flattening options.



NOTE

If you realize that you want to do further adjustments, click **Go Back**. The activated flatten options are kept.

4. Click **Flatten**.
-

RESULT

The events and parts in the project are reordered, repeated, resized, moved and/or deleted, so that they correspond exactly to the arranger chain.

Jump Mode

If you have set up an arranger track and play it back, you have live access to the playback order. This way, you can loop your arranger events with more flexibility regarding the length of the playback.

PREREQUISITE

An arranger chain is set up and the arranger mode is activated.

PROCEDURE

1. Click **Play** to play back your project.
2. In the lower part of the **Inspector**, open the **Jump Mode** pop-up menu, and select an option from the pop-up menu.



This determines how long the active arranger event is played, before jumping to the next one.

3. In the **Arranger Events** list of the **Inspector**, click the arrow to the left of the arranger event that you want to trigger.
-

RESULT

The arranger event is looped according to your settings, until you click another arranger event.

NOTE

You can assign key commands to trigger arranger events in the **Arranger** category of the **Key Commands** dialog.

AFTER COMPLETING THIS TASK


- To stop **Jump Mode**, click **Stop**.
- To continue playback from a specific arranger event, click the arranger event in the **Current Arranger Chain** list.

RELATED LINKS

[Jump Mode Options](#) on page 297

Jump Mode Options

The **Jump Mode** pop-up menu allows you to define how long the active arranger event is played before jumping to the next one.



The following options are available:

None

Jumps to the next section immediately.

4 bars, 2 bars

Jumps to the next arranger event after 2 or 4 bars. If the current arranger event is shorter than 2 or 4 bars, playback jumps to the next arranger event at the event end.

1 bar

Jumps to the next section at the next barline.

1 beat

Jumps to the next section at the next beat.

End

Plays the current section to the end, then jumps to the next section.

Arranging Music to Video

When you compose music for video, you can use arranger events to fill a specific video section with music. Here comes an example on how you could do that.

PREREQUISITE

You have connected and set up an external sync master device to your computer. You have created a new, empty project and added a MIDI track.

PROCEDURE

1. Create a MIDI part that starts at position 00:00:00:00 and ends at position 00:01:00:00.
2. Create a MIDI part that starts at position 00:01:00:00 and ends at position 00:02:00:00.
3. Create a MIDI part that starts at position 00:02:00:00 and ends at position 00:03:00:00.
4. On the **Transport** panel, activate **Sync**.
5. Select **Project > Add Track > Arranger**.
6. Add arranger events at the positions of the MIDI parts.
7. Set up the arranger chain A-A-B-B-C-C.
8. Activate **Arranger** mode and click **Play**.
9. On your external sync master device, start external timecode at position 00:00:10:00. In your project, the position 00:00:10:00 is located, and arranger part A is played back.
10. Start your external sync master device at a position that does not match the Project Start time, for example, 00:01:10:00. In your project, the position 00:01:10:00 is located, and arranger part A is played back.

RESULT

If you position the external sync master device to a position that does not match the project start time, Cubase automatically jumps to the right position in the arranger track.

NOTE

The reference for the external timecode can be MIDI or any other timecode that can be interpreted by Cubase.

Transpose Functions

The transpose functions for audio and MIDI in Cubase allow you to change the pitches of audio and MIDI for playback without changing the actual MIDI notes or the audio.

You can transpose the following:

- An entire project by changing the **Project Root Key** on the **Project** window toolbar.
- Specific sections of your project by creating a transpose track and adding transpose events.
- Individual parts or events by changing their transpose value on the **Project** window info line.

IMPORTANT

As a general rule, always set the root key first when you work with content with a defined root key.

NOTE

To transpose MIDI notes on a selected track, you can also use MIDI modifiers. If you want to change the actual notes, use the MIDI transpose functions in the **Transpose Setup** dialog and in the MIDI effects (see the separate document **Plug-in Reference**).

RELATED LINKS

[Transposing with the Project Root Key](#) on page 300

[Transposing Sections of a Project with Transpose Events](#) on page 303

[Transposing Individual Parts or Events using the Info Line](#) on page 305

[MIDI Modifiers](#) on page 670

[Transpose and Velocity on the Info Line](#) on page 678

[Transpose Setup](#) on page 690

Project Root Key

The **Project Root Key** allows you to transpose your project. Audio or MIDI events in your project use it as a reference.

To change the **Project Root Key**, use the **Project Root Key** pop-up menu on the **Project** window toolbar.



If you change the project root key, loops that already contain root key information will follow automatically.

RELATED LINKS

[Transposing with the Project Root Key](#) on page 300

Transposing with the Project Root Key


The loops included in Cubase already contain root key information. If you change the project root key, these loops will follow automatically.

PREREQUISITE


You have opened a project that contains audio loops with different root keys.

PROCEDURE

1. Optional: Select the drum and percussion loops in your project and set the **Global Transpose** setting on the info line to **Independent**. This setting excludes the loops from being transposed.
2. On the **Project** window toolbar, open the **Project Root Key** pop-up menu and set a root key for the project.



This changes the root key for the entire project and transposes the loops to match this key.



RESULT

The loops follow the project root key.

AFTER COMPLETING THIS TASK

Record audio or MIDI. The newly recorded events get the project root key. Change the project root key. The events with root key information follow.

RELATED LINKS

[Excluding Individual Parts or Events from Global Transpose](#) on page 306

[Transpose Track and Recording](#) on page 305


Assigning the Project Root Key to Parts or Events

Some audio or MIDI events that you have created by recording, for example, might not contain root key information. If you want them to follow the transposition changes, you must set them to the **Project Root Key**.

PROCEDURE

1. On the **Project** window toolbar, open the **Project Root Key** pop-up menu and set a root key for the project.

- Optional: Select the drum and percussion loops in your project and set the **Global Transpose** setting on the info line to **Independent**. This setting excludes the loops from being transposed.
- Select **Project > Add Track > Transpose**. A transpose track is created. You can only have one transpose track in a project.
- In the track list, right-click the transpose track, and from the context menu select **Set root key for unassigned events**.



RESULT

All parts or events that do not contain any root key information are set to the project root key.

RELATED LINKS

[Excluding Individual Parts or Events from Global Transpose](#) on page 306

Recording with a Project Root Key

If you record with a project root key, the recorded events follow this root key automatically. This function is useful if you want to change the root key later and you want the events to follow.

PROCEDURE

- Optional: Select the drum and percussion loops in your project and set the **Global Transpose** setting on the info line to **Independent**. This setting excludes the loops from being transposed.
- On the **Project** window toolbar, open the **Project Root Key** pop-up menu and set the root key. All parts and events are transposed in order to match the root key.
- Record your music.

RESULT

All recorded audio events and MIDI parts get the project root key information. On the info line, the **Global Transpose** setting for recorded events is set to **Follow**.

AFTER COMPLETING THIS TASK

Change the project root key. Your events will follow.

Changing the Root Key of Individual Audio Events

You can change or set the root key information for individual audio events or parts in the **Pool**.

PROCEDURE

- Select **Media > Open Pool Window**.
- Open the **View/Attributes** pop-up menu, and activate the **Root Key** option. The **Key** column is displayed in the **Pool** window.

3. Click the **Key** column for the audio event or part that you want to assign a different root key to, and select a key from the pop-up menu.
-

RESULT

The root key of the audio event or part is changed. The corresponding audio file however, remains unchanged. If you change the project root key, the audio events or parts keep their own root key settings, and are transposed to match the **Project Root Key**.

NOTE

You can also assign root keys in the **MediaBay**.

NOTE

Save the root key in the audio file by selecting the audio event in the event display, and by selecting **Audio > Bounce Selection**.

Changing the Root Key of Individual MIDI Parts

You can change the root key information for individual MIDI parts in the **Project** window info line.

PROCEDURE

1. In the event display, select the MIDI part.
 2. In the **Project** window info line, click **Root Key** and select a key from the pop-up menu.
-

RESULT

The root key of the MIDI part is changed. If you change the project root key, the MIDI parts keep their own root key settings, and are transposed to match the **Project Root Key**.

Transpose Track

The transpose track allows you to transpose the entire project or sections of it. This function is useful if you want to create harmonic variations.

For this function to work, you must add transpose events. These transpose events allow you to transpose specific sections of your project in semitones.

EXAMPLE

If your singer does not reach a certain pitch, you can transpose the entire project by adding a transpose track and creating a transpose event with the value -2 semitones. After recording, set the transpose event back to 0.

EXAMPLE

If you want to brighten up your loops in C major, you can transpose them by adding a transpose track and creating a transpose event with the value 5. This transposes them by 5 semitones, so that the subdominant on F major is played back.

EXAMPLE


If you want to turn your song more interesting, you can transpose the last chorus of your project by adding a transpose track and creating a transpose event with the value 1.

Transposing Sections of a Project with Transpose Events


You can transpose specific sections of your project by creating transpose events on the transpose track.

PROCEDURE

1. Select **Project > Add Track > Transpose**.
A transpose track is created. You can only have one transpose track in a project.
2. Select the **Draw** tool and click on the transpose track.
A transpose event is created from the point where you clicked until the end of the project.



3. Click at a new position to add another transpose event.



4. Click the value in the lower left corner of the event, and enter a transpose value between -24 and 24 semitones.
 5. Play back your project.
-

RESULT

The sections of your project that are situated at the same time positions as the transpose events are transposed.

RELATED LINKS

[Excluding Individual Parts or Events from Global Transpose](#) on page 306

Muting the Transpose Track

You can mute the transpose track. This is useful if you want to compare the effect of the transposition with the original sound, for example.

PROCEDURE

- In the track list of the transpose track, click **Mute Transpose Events**.
-

RESULT

The transpose events are not taken into account during playback.

Transpose Lock

The lock function on the transpose track allows you to prevent your transpose events from being moved or changed by mistake.

To lock the transpose track, activate **Lock** in the track list.



Keep Transpose in Octave Range

Keep Transpose in Octave Range on the transpose track keeps the transposition in the octave range.

This ensures that nothing is transposed by more than seven semitones, and that your music never sounds unnatural because the pitch was raised too high or too low. We also recommend activating this function, when you work with audio loops.

EXAMPLE

You have opened the **Key Editor** and activated **Indicate Transpositions** .

You have added a transpose track and activated **Transpose in Octave Range** .


If you add a transpose event with a value of 8 semitones or higher, the chord is transposed to the nearest interval or pitch.

Indicate Transpositions


For MIDI parts, you can get a visual feedback that allows you to compare the original sounds and the music transposed for playback.

To activate this, open the part in the **Key Editor**, and activate **Indicate Transpositions**.

- If **Indicate Transpositions** is activated, the transposed note pitches are shown.



- If **Indicate Transpositions** is deactivated, the original pitches of the notes in the MIDI part are shown.



Transpose Track and Recording

The transpose track affects the result of the recorded parts or events.

If your project contains a transpose track with transpose events, and you record audio or MIDI, the following happens:

- **Global Transpose** is automatically set to **Independent** for the recorded parts or events.
- The project root key is not taken into account.

If your project does not contain a transpose track or if no transpose events are added, the following happens:

- **Global Transpose** is automatically set to **Follow** for the recorded parts or events.
- The recorded parts or events get the project root key.

Transpose on the Info Line

In the **Project** window info line, you can change the transpose value for individual parts or events.

To do this, change the transpose value in the **Transpose** field on the info line.



The Transpose field also indicates transpositions introduced by changing the **Project Root Key**.

Transposing Individual Parts or Events using the Info Line

You can transpose individual audio events and MIDI parts on the info line **Transpose** field.

PROCEDURE

1. Select the event or part that you want to transpose.
2. On the **Project** window info line, click the **Transpose** field and enter a transpose value in semitones.

NOTE

If the project already contains global transpose changes, it might be useful to activate **Keep Transpose in Octave Range**.

RESULT

The event is transposed accordingly. The transpose value is added to any global transpose change that you have created by using the root key or the transpose track.

RELATED LINKS


[Keep Transpose in Octave Range](#) on page 304

Excluding Individual Parts or Events from Global Transpose

If you add global transposition, for example, by changing the root key or by creating transpose events, you can exclude specific events from being transposed. This is useful for drum and percussion loops or special effects (FX) loops.

PROCEDURE

1. Select the event or part that you want to exclude from being transposed.
2. On the info line, click the **Global Transpose** field to set the value to **Independent**.
Events that are excluded from **Global Transpose** show a symbol in the upper right corner.



RESULT

If you change the project root key or add transpose events, the **Independent** parts or events are not affected.

NOTE

Ready-made parts or events that are tagged as drums or FX, are automatically set to **Independent**.

Markers

Markers are used to locate certain positions quickly. There are two types of markers: position markers and cycle markers.

If you often find yourself jumping to a specific position within a project, you should insert a marker at this position. You can also use markers to make range selections or for zooming.

Markers are located on the marker track. You can add 1 marker track in Cubase Artist and up to 10 marker tracks in Cubase Pro.

Position Markers

Position markers allow you to save a specific position.

Position markers on the marker track are shown as marker events: vertical lines with the marker description (if assigned) and number beside it. If you select a marker track, all its markers are shown in the Inspector.

Cycle Markers

By creating cycle markers you can save any number of left and right locator positions as start and end positions of a range and recall them by double-clicking on the corresponding marker.

Cycle markers are shown on a marker track as two markers bridged by a horizontal line. Cycle markers are ideal for saving sections of a project.

By defining cycle markers for the intro, verse, and chorus of a song, for example, you can quickly navigate to the song sections and repeat the section by activating **Cycle** on the **Transport** panel.

Setting the Locators Using Cycle Markers

Cycle markers represent ranges in your project. You can use them for moving the left and right locators.

PROCEDURE

- To set the left locator to the cycle marker start and the right locator to the cycle marker end, perform one of the following actions:
 - Double-click on a cycle marker.
 - From the **Cycle** pop-up menu in the track list, select a cycle marker.

RESULT

The left and right locators are moved to encompass the cycle marker.

AFTER COMPLETING THIS TASK

Now you can move the project cursor position to the start or the end of the cycle marker by moving it to the corresponding locator or use cycle markers to export specific ranges of your project with the **Export Audio Mixdown** dialog.

Editing Cycle Markers

When editing cycle markers on a marker track, snap is taken into account.

- To add a cycle marker, press **Ctrl/Cmd** click and drag on the marker track.
- To change the start/end position of a cycle marker, drag the start/end handle.
- To move a cycle marker to another position, drag the upper border.
- To delete a cycle marker, click with the **Erase** tool.

If you hold down **Alt** when you click, all consecutive markers are deleted.

- To cut a range in a cycle marker, select a range in the cycle marker and press **Ctrl/Cmd-X**.
- To set the marker start/end of the selected cycle marker to the cursor position, select **Project > Markers** to open the **Markers** window, and select **Functions > Set Marker Start/End to Cursor**.
- To set the left and right locators, double-click a cycle marker.
- To zoom in on a cycle marker, press **Alt** and double-click the cycle marker.

Markers Window

In the **Markers** window, you can view and edit markers. Cubase Pro only: The markers on the active marker track are displayed in the marker list in the order in which they occur in the project. Cubase Artist only: The markers on the marker track are displayed in the marker list in the order in which they occur in the project.

To open the **Markers** window, you have the following possibilities:

- Select **Project > Markers**.
- On the **Transport** panel in the marker section, click **Show**.
- Use a key command (by default **Ctrl/Cmd-M**).



- 1 Locate arrow**
Indicates which marker is at the project cursor position.
- 2 Set focus to marker track**
Cubase Pro only: Allows you to select the marker track that has the focus.
- 3 Functions menu**
Lists all functions available in the **Marker** window.

- 4 Marker type**
Allows you to specify which marker type is shown in the marker list.
- 5 Auto-Scroll with Project Cursor**
Allows you to keep track of the locate arrow, even if your project contains a large number of markers. If this option is activated, the **Marker** window is automatically scrolled to keep the locate arrow visible.
- 6 Markers list**
Shows the markers in the order in which they occur in the project.
- 7 Marker Settings**
Shows the marker settings.

Editing in the Markers Window

In the **Markers** window, you can select, edit, add, move, and remove markers.

- To select or edit a marker, click on it.
Select multiple markers by **Shift** or **Ctrl/Cmd**-clicking them.
- To add a position marker at the cursor position, select **Functions > Insert Marker**.
Cubase Pro only: A position marker is added at the current project cursor position on the active marker track.
Cubase Artist only: A position marker is added at the current project cursor position on the marker track.
- To add a cycle marker at the cursor position, select **Functions > Insert Cycle Marker**.
Cubase Pro only: This adds a cycle marker between the left and right locators on the active marker track.
Cubase Artist only: This adds a cycle marker between the left and right locators on the marker track.
- To move a marker to the cursor position, select the marker and select **Functions > Move Markers to Cursor**.
You can also enter the new position numerically in the **Position** column. If a cycle marker is selected, the move operation affects the cycle marker start position.
- Cubase Pro only: To move markers to another track, select the markers, select **Functions > Move Markers to Track**, and select the marker track.
- To remove a marker, select it and select **Functions > Remove Marker**.

Navigating in the Marker List

You can navigate in the marker list using your computer keyboard and select entries by pressing **Enter**. This is a quick and easy way to jump to markers during playback or recording.

- To move to the previous/next marker in the list, press the **Up Arrow/Down Arrow** keys.
- To jump to the first/last marker, press the **Page Up/Page Down** keys.

Sorting and Reordering the Marker List

You can customize the display of the marker attributes in the marker list by sorting or reordering the columns.


- To sort the marker list by a specific attribute, click on the corresponding column header.
- To reorder the marker attributes, drag and drop the corresponding column headers.
- To adjust the width of a column, place the mouse pointer between two column headers and drag left or right.

NOTE

No matter by which attribute you sort, the second sort criterion will always be the position attribute.

Marker Settings

You can access the marker settings by clicking the corresponding button in the bottom left corner of the **Markers** window.



Cycle follows when locating to Markers

This sets the left and right locators automatically to a position or cycle marker, when locating to this marker. This is useful if you need to set the locators on the fly during recording for Punch In/Punch Out, for example.

Show marker IDs on marker track

If this option is activated, the marker IDs are shown on the marker track.

Sync Selection

If this option is activated, the **Markers** window selection is linked to the selection in the **Project** window.

Marker Attributes

The following marker attributes are shown in the marker list of the **Marker** window:

Locate

An arrow indicates which marker is at the project cursor position (or closest to the project cursor). If you click in this column, the project cursor is moved to the corresponding marker position. This column cannot be hidden.

ID

This column shows the marker ID numbers.

Position

In this column, you can view and edit the markers' time positions (or start positions for cycle markers). This column cannot be hidden.

End

In this column, you can view and edit the end positions of cycle markers.

Length

In this column, you can view and edit the length of cycle markers.

Description

Here you can enter names or descriptions for markers.

RELATED LINKS

[Marker IDs](#) on page 311

[Cycle Markers](#) on page 307

Editing Attributes

- To edit a marker attribute, select the corresponding marker, click in the desired attribute column, and make your settings.

- To change the attributes of several markers, select the markers and click the checkbox for the desired attribute.
All selected markers will change their attributes accordingly. Note that this does not work when clicking on a timecode value or a text field.

NOTE

To navigate in the list of marker attributes, you can also use the **Tab** key and the **Up Arrow**, **Down Arrow**, **Left Arrow**, and **Right Arrow** keys.

Sorting and Reordering Columns

You can customize the display of the marker attributes in the marker list by sorting or reordering the columns.

- To sort the marker list by a specific attribute, click on the corresponding column header.

NOTE

No matter by which attribute you sort, the second sort criterion will always be the position attribute.

- To reorder the marker attributes, drag and drop the corresponding column headers.
- To adjust the width of a column, place the mouse pointer between two column headers and drag left or right.

Marker IDs

Each time you add a marker, it is automatically and sequentially assigned an ID number, starting from 1.

IDs for cycle markers are shown in brackets and start from 1. ID numbers can be changed at any time – this allows you to assign specific markers to key commands.

NOTE

Cubase Pro only: If you move a marker from one marker track to another by drag and drop in the **Project** window, and the marker ID is already used on this track, the inserted marker automatically gets a new ID.

Reassigning Marker IDs

Sometimes, especially when setting markers on the fly, you may forget or miss to set a marker. When added later, this marker's ID will not correspond to its position on the marker track. Therefore, it is possible to reassign the IDs for all markers on a track.

PROCEDURE


1. Open the **Markers** window.
 2. Cubase Pro only: Select the marker track whose ID numbers you want to reassign.
 3. Open the **Functions** pop-up menu and select either **Reassign Position Marker IDs** or **Reassign Cycle Marker IDs**.
-

RESULT

The marker IDs of the selected type are reassigned to match the order of markers on the marker track.

Marker Track

A marker track is used for adding and editing markers.



- 1 Add Marker**
Adds a position marker at the cursor position.
- 2 Add Cycle Marker**
Adds a cycle marker at the cursor position.
- 3 Locate pop-up menu**
If you select a position or a cycle marker in this pop-up menu, the corresponding marker in the event display or in the **Markers** window is selected.
- 4 Cycle pop-up menu**
If you select a cycle marker in this pop-up menu, the left and right locators are set to the corresponding cycle marker.
- 5 Zoom pop-up menu**
If you select a cycle marker in this pop-up menu, the view zooms to the corresponding cycle marker.
- 6 Lock**
Locks the marker track. When a marker track is locked, you cannot edit the track and its markers.
- 7 Toggle Time Base**
Sets the track time base.
- 8 Marker event (inactive)**
Shows an inactive marker event.
- 9 Marker event (active)**
Shows an active marker event.
- 10 Cycle marker event (inactive)**
Shows an inactive cycle marker event.
- 11 Cycle marker event (active)**
Shows an active cycle marker event.

Adding, Moving, and Removing the Marker Track

- To add a marker track to the project, select **Project > Add Track > Marker**.
- To move a marker track to another position in the track list, click and drag it up or down.
- Cubase Pro only: To remove one or more marker tracks, right-click them in the track list and select **Remove Selected Tracks**.
- Cubase Artist only: To remove the marker track, right-click it in the track list and select **Remove Selected Tracks**.
- To remove an empty marker track, select **Project > Remove Empty Tracks**. This also removes any other tracks that are empty.

NOTE

Cubase Pro only: When you remove all marker tracks, the marker track that you removed last (including all its markers) is moved to the clipboard. If you later insert a new marker track, this track is pasted from the clipboard into the track list.

Cubase Pro only: Multiple Marker Tracks

You can create up to 10 marker tracks.

Naming Marker Tracks

By default, the first marker track you create is called “Markers”, the second “Marker 01”, and so on.

You can name marker tracks by double-clicking on the marker track name in the track list or the Inspector and entering a new name.

The Active Marker Track

When you are working with multiple marker tracks, only one track is active. All editing functions affect the markers on the active track only. You activate a track by clicking **Activate this track** in the track list.

The following rules apply:

- When you add a new marker track, this track is automatically active.
- When you remove an active track, the topmost marker track in the track list is activated. When using cycle markers for zooming, only the cycle markers of the active track are displayed on the **Zoom** pop-up menu.
- When exporting an audio mixdown of the audio between the cycle markers, only the cycle markers of the active track are displayed in the **Export Audio Mixdown** dialog.
- Most marker key commands affect the active track.

Locking Marker Tracks

You can lock one or more marker tracks by clicking the corresponding lock button of the track. When a marker track is locked, you cannot edit the track and its markers. However, you can still rename the track or change its status (active/inactive). In the **Markers** window and the Project Browser, the unavailable features of a locked track are grayed out.

RELATED LINKS

[Editing Cycle Markers](#) on page 308

[Importing and Exporting Markers](#) on page 315

Working with Multiple Marker Tracks


PREREQUISITE

You have added at least two marker tracks to the project and named them.


PROCEDURE

1. Select **File > Key Commands**.
2. In the **Marker** category, set up a key command for **Insert and name Marker**. This command adds a position marker, opens the **Markers** window and activates the **Description** column.
3. Set up key commands for **Activate next Marker Track** and **Activate previous Marker Track**.

4. Activate the marker track for the first narrator, and play back the video file.



5. At the position where the first dialogue section should be replaced, trigger **Insert and name Marker**.
The **Marker** window opens with the **Description** column active, so that you can insert a name for the new marker.
6. Enter a name or description for the section, and press **Return** to confirm.
A new marker is created on the active track in the **Project** window.
7. Activate the track on which you want to insert the next marker using the **Activate next/previous Marker Track** key command.
A message informs you that a different marker track is now active.



8. Trigger the **Insert and name Marker** key command at the position where the next dialogue section should be replaced.
Repeat this procedure for all markers that you want to insert.

Editing Markers on the Marker Track

- To add a position marker, click **Add Marker** or use the **Draw** tool.
- To add a cycle marker, click **Add Cycle Marker** or use the **Draw** tool.
- To select a marker, use the standard techniques.
- To resize a cycle marker, select it and drag the handles. You can also do this numerically on the info line.
- To move a marker, select it and drag it. You can also edit marker positions on the info line.
Cubase Pro only: If you move markers from one track to another, the marker gets the numbering of the first free marker ID on the track where it is dropped.
- To remove a marker, select it and press **Delete** or use the **Erase** tool.

Using Markers to Select Ranges

Markers can be used in conjunction with the **Range Selection** tool to make range selections in the **Project** window. This is useful if you quickly want to make a selection that spans all tracks in the project.

PROCEDURE

1. Set markers at the start and end of the section that you want to move or copy.
 2. Select the **Range Selection** tool and double-click on the marker track between the markers.
Everything in the project within the marker boundaries is selected. Any functions or processing you perform now affect the selection only.
 3. Click on the marker track in the selected range and drag the range to a new position.
If you hold down **Alt** while you drag the range, the selection in the **Project** window is copied instead.
-

Importing and Exporting Markers

Markers and marker tracks can be imported and exported.

The following files can contain markers:

- MIDI files
- Track archives (Cubase Pro only)

Importing Markers via MIDI

You can import position markers by importing MIDI files containing markers. This is useful if you want to use your marker tracks in other projects or if you want to share them with other Cubase users. Any markers you have added are included in the MIDI file as standard MIDI file marker events.

- Activate **Import Markers** in the **Preferences** dialog (**MIDI—MIDI File** page).

The following settings are imported:

- The start position of position markers and cycle markers
- Cubase Pro only: The track assignment of markers
- Cubase Pro only: All marker tracks

NOTE

Cubase Pro only: If you import a standard MIDI file created in other applications, all markers are merged on one marker track.

RELATED LINKS

[Importing MIDI Files](#) on page 262

Exporting Markers via MIDI

You can export your markers as part of a MIDI file.

- To include any markers in the MIDI file, activate **Export Markers** in the **Export Options** dialog.

The following settings are exported:

- The start position of position markers and cycle markers
- Cubase Pro only: The track assignment of markers
- Cubase Pro only: All marker tracks

NOTE

Cubase Pro only: To be able to export markers via MIDI export, your project must contain at least one marker track.

Cubase Artist only: To be able to export markers via MIDI export, your project must contain a marker track.

RELATED LINKS

[Exporting MIDI Tracks as Standard MIDI File](#) on page 157

Importing Markers as Part of a Track Archive (Cubase Pro only)

You can import position markers and cycle markers by importing track archives containing marker tracks. Select the tracks that you want to import in the **Import Options** dialog.

The following settings are imported:

- The start and end positions of cycle markers
- The track assignment of markers
- The marker IDs
- All marker tracks

RELATED LINKS

[Importing Tracks from Track Archive](#) on page 155

Exporting Markers as Part of a Track Archive (Cubase Pro only)

If you want to use your marker tracks in other projects, for example to share them with other users, you can export them as part of a track archive. To do so, select the marker tracks that you want to export. Then select **File > Export > Selected Tracks**.

The following settings are exported:

- The start and end positions of cycle markers
- The track assignment of markers
- The marker IDs
- All marker tracks

RELATED LINKS

[Exporting Tracks as Track Archive \(Cubase Pro only\)](#) on page 156

MixConsole

The **MixConsole** provides a common environment for producing mixes in stereo or surround. It allows you to control level, pan, solo/mute status, etc. for audio and MIDI channels. Furthermore, you can set up the input and output routing for multiple tracks or channels at the same time. You can undo/redo **MixConsole** parameter changes for an open project at any time.

You can open the **MixConsole** in a separate window or in the lower zone of the **Project** window.

While the **MixConsole** in the lower zone of the **Project** window features the key functions for mixing, the separate **MixConsole** window gives you access to additional functions and settings.

RELATED LINKS

[MixConsole in Lower Zone](#) on page 317

[MixConsole Window](#) on page 320


MixConsole in Lower Zone

You can show a **MixConsole** in the lower zone of the **Project** window. This is useful if you want to access the most important **MixConsole** functions from within a fixed zone of the **Project** window. The **MixConsole** in the lower zone of the **Project** window is a separate **MixConsole** that does not follow any visibility changes you perform in the **MixConsole** window.

Do one of the following to open a **MixConsole** in the lower zone of the **Project** window:

- Press **Alt+F3**.
- Select **Studio > MixConsole in Project Window**.

The **MixConsole** in the lower zone of the **Project** window is divided into the following sections:



1 Toolbar

The toolbar shows tools and shortcuts for settings and functions in the **MixConsole**.

2 Fader Section

The fader section is always visible and shows all channels in the same order as in the track list.

3 Page Selector

Allows you to select what page is displayed in the fader section: the channel faders, the insert effects for a channel, or the send effects. The top button allows you to show/hide the toolbar.

RELATED LINKS


- [Fader Section](#) on page 336
- [Inserts](#) on page 347
- [Sends](#) on page 359
- [Filtering Channel Types](#) on page 326
- [Undoing/Redoing MixConsole Parameter Changes](#) on page 326
- [Linking Channels](#) on page 330
- [Functions Menu](#) on page 334

Showing/Hiding MixConsole Channels in the Lower Zone

To determine what channels are visible in the **MixConsole** in the lower zone of the **Project** window, you must use the **Track Visibility** in the left zone of the **Project** window.

PROCEDURE

1. Click **Show/Hide Left Zone** on the **Project** window toolbar to activate the **Left Zone**.
2. At the top of the left zone, click the **Visibility** tab.
3. At the bottom of the left zone, click the **Track** tab.



4. Click to the left of a track name to activate/deactivate the visibility for a channel.
-

RESULT

The track in the track list and the corresponding **MixConsole** channel are shown/hidden in the lower zone of the **Project** window.

RELATED LINKS


- [Opening the Track Visibility](#) on page 58
- [Showing/Hiding Individual Tracks](#) on page 59
- [Visibility](#) on page 58

Determining the MixConsole Channel Order in the Lower Zone

You can determine and lock the position of **MixConsole** channels in the lower zone of the **Project** window.

PROCEDURE

1. At the top of the left zone, click the **Visibility** tab.
2. At the bottom of the left zone, click the **Zones** tab.



3. Do one of the following:
 - To lock a channel on the left of the fader section, drag the dot next to the channel name to the left.
 - To lock a channel on the right of the fader section, drag the dot next to the channel name to the right.
-

RESULT

The channel is locked. Locked channels are always displayed.

RELATED LINKS

[Opening the Zones Visibility](#) on page 60

MixConsole Window

You can open the **MixConsole** in a separate window.

Do one of the following to open the **MixConsole**:

- Press **F3**.
- Select **Studio > MixConsole**.
- On the **Project** window toolbar, click **Open MixConsole** .

NOTE

This is only visible on the toolbar if the section **Media & MixConsole Windows** is activated.




The main **MixConsole** sections are:

- 1 Toolbar**
The toolbar shows tools and shortcuts for settings and functions in the **MixConsole**.
- 2 Channel Selector (Left Zone)**
Allows you to set up the visibility and positions of channels in the fader section.
- 3 Channel Racks (Upper Zone)**
Allows you to show additional channel controls as needed.

4 Fader Section

The fader section is always visible and shows all channels in the same order as in the track list.



Apart from the main sections, you can also access the following sections from within the **MixConsole** window:

1 Channel Overview

Displays all channels as boxes. If you have more channels than can be displayed in the window, you can use the channel overview to navigate to other channels and select them.

2 Meter Bridge

Allows you to monitor the levels of your channels.

To select a meter type, open the meter bridge context menu and select either **PPM** or **Wave**.

3 Equalizer Curve

Allows you to draw an EQ curve. Click in the curve display to open a larger view where you can edit the curve points.

4 Pictures

Opens the **Pictures** section that allows you to add a picture to the selected channel. Pictures can help you identify your **MixConsole** channels quickly.

5 Notepad

In the **Notepad** section, you can enter notes and comments about a channel. Each channel has its own notepad.

6 Control Room/Meter (Right Zone) (Cubase Pro only)

Opens the **Control Room/Meter** section.

RELATED LINKS

[Channel Selector](#) on page 322

[MixConsole Toolbar](#) on page 323

[Fader Section](#) on page 336

- [Channel Racks on page 328](#)
- [Track Pictures Browser on page 161](#)
- [Adding Notes to a MixConsole Channel on page 363](#)
- [Control Room \(Cubase Pro only\) on page 372](#)

Channel Selector

The channel selector contains the following tabs: **Visibility** and **Zones** that list all channels contained in your project, and **History** that lists all **MixConsole** parameter changes.

Visibility Tab

The **Visibility** tab allows you to determine which channels are shown in the **MixConsole**. This is particularly helpful if you organize your tracks in folder or group tracks.




- To show/hide channels, check/uncheck them by clicking to the left of the channel name.
- To collapse/expand groups and folders, click the group or folder name.

NOTE

The **MixConsole** in the lower zone of the **Project** window does not follow any visibility changes you perform in the **MixConsole** window and vice versa.

Zones Tab

The **Zones** tab allows you to determine and lock the position of certain channels.




- To lock channels on the left/right of the fader section, drag the dots next to the channel names to the left or to the right.
Locked channels are excluded from scrolling and are always visible.

NOTE

The **MixConsole** in the lower zone of the **Project** window does not follow any visibility changes you perform in the **MixConsole** window and vice versa.

History Tab

The **History** tab allows you to view and undo/redo **MixConsole** parameter changes. All **MixConsole** parameter changes are shown in a list.



Action	Details	Time
TR 909 / Volume	-12.0	11:26:03 AM
Bass / Volume	-13.9	11:26:04 AM
BASS Electro / Volume	-7.18	11:26:08 AM
GTR Tele II DRY / Output Right - Ster		11:26:11 AM
Input Filter / PreGain	-42.4dB	11:26:12 AM
Input Filter / Bypass	On	11:26:15 AM

- To undo **MixConsole** parameter actions, click **Undo** . You can also click the orange line in the history list and drag it up.
- To redo **MixConsole** parameter actions, click **Redo** . You can also click the orange line in the history list and drag it down.

RELATED LINKS

[Undoing/Redoing MixConsole Parameter Changes](#) on page 326

Synchronizing Channel and Track Visibility

You can synchronize the channel visibility in the **MixConsole** with the track visibility in the **Project** window.

PROCEDURE

1. In the **Channel Selector**, open the **Visibility** tab.
2. Click **Sync Visibility of Project and MixConsole: On/Off** .
3. Select **Sync MixConsole and Project** to synchronize the channel visibility with the track visibility.

RESULT

The track and channel visibility are synchronized.

NOTE

Channels that are locked in the **Zones** tab are not synchronized.

RELATED LINKS

[Synchronizing Track and Channel Visibility](#) on page 60

MixConsole Toolbar

The toolbar contains tools and shortcuts for settings and functions in the **MixConsole**.

NOTE

The **MixConsole** toolbar contains a limited set of tools in the lower zone of the **Project** window. This includes: **MixConsole History**, **Channel Filter Types**, **Search**, **Link Group**, **Zoom Palette**, **Mixer Functions Menu**, and **Window Zone Controls**. You can show/hide the toolbar by clicking **Show/Hide MixConsole Toolbar**.

MixConsole History



These buttons allow you to undo/redo **MixConsole** parameter changes.

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

Search




Opens a selector that lists all tracks/channels.

Channel Filter Types



Opens the channel filter that allows you to show/hide all channels of a certain channel type.

Channel Visibility Configurations



Allows you to create configurations that are useful for switching quickly between different visibility setups.

Channel Visibility Agents



Allows you to select channels with specific properties.

Select Rack Types



Opens the rack selector that allows you to show/hide specific racks.

Rack Settings




Opens a pop-up menu with settings for the racks.

Go to Left/Right Locator Position



Allows you to go to the left/right locator positions.

Left/Right Locator Position



Shows the left/right locator positions.

Transport Buttons




Shows the transport controls.

Time Display




Shows the position of the project cursor in the selected time format.

Markers



Allows you to set and locate marker positions.

State Buttons



Allows you to set mute, solo, listen, and automation states. Here you can also bypass inserts, EQs, channel strips, and sends.

Link Group



Allows you to link channels.

Zoom Palette



Allows you to increase/reduce the channel width and the rack height. You can change the width for all channels from viewable (narrow) to editable (wide) by using the default key commands **G** and **H**.

System Performance Meter



Shows the meters for ASIO time usage and hard disk transfer load.

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Mixer Functions Menu



Opens the **Functions Menu** that allows you to make settings in the **MixConsole**.

Window Zone Controls



Allow you to show or hide the left zone, the upper zone, and the right zone (Cubase Pro only) of the **MixConsole**. The **Setup Window Layout** pop-up menu allows you to show or hide the status line, the info line, and the overview line.

Finding Channels

The **Find Track/Channel** function allows you to find specific channels. This is useful if you have a large project with many channels or if you have hidden channels using the visibility features.

PROCEDURE

1. Click **Find Track/Channel** on the **MixConsole** toolbar to open a selector that lists all channels.
2. In the search field, enter the name of the channel.
As you type, the selector filters automatically.
3. In the selector, select the channel and press **Return**.

RESULT

The channel is selected in the channel list.

NOTE

If the channel was outside the view or hidden, it is now shown. Channels that are hidden using **Filter Channel Types** are not shown.

Undoing/Redoing MixConsole Parameter Changes

You can undo/redo **MixConsole** parameter changes and experiment with different **MixConsole** settings.

NOTE

MixConsole parameters that change due to read automation actions are not part of the **MixConsole** history.

To undo/redo a **MixConsole** parameter, do one of the following:

- On the **MixConsole** toolbar in the **MixConsole** window or in the lower zone of the **Project** window, click **Undo**  or **Redo** .
- Press **Alt-Z** to undo **MixConsole** parameter changes or press **Alt-Shift-Z** to redo parameter changes.

The following **MixConsole** parameter changes can be undone/redone:

- Volume changes
- Panorama changes
- Changes on the **Routing** rack
- Filter, gain, and phase changes in the **Pre** rack
- Plug-in changes in the **Inserts** rack
- EQ changes
- Changes on the **Channel Strip** rack
- Changes on the **Sends** rack
- Cubase Pro only: Changes on the **Cue Sends** rack
- Cubase Pro only: Changes on the **Direct Routing** rack

IMPORTANT


The **MixConsole** history is not saved with the project.

Filtering Channel Types

The channel types filter on the **MixConsole** toolbar allows you to determine which channel types are shown.

PROCEDURE

1. Click **Filter Channel Types**.
This opens the channel types filter.



2. Click to the left of a channel type to uncheck it and hide all channels of that type.
-

RESULT

Channels of the filtered type are removed from the fader section and the color of the **Filter Channel Types** button changes to indicate that a channel type is hidden.

Channel Visibility Configurations

The **Channel Visibility Configurations** button on the **MixConsole** toolbar allows you to create configurations that are useful for switching quickly between different visibility setups.

The button displays the name of the active configuration. A list of configurations is shown as soon as you create at least one configuration. To load a configuration, select it from this list. Channel visibility configurations are saved with the project.

Add Configuration

Opens the **Add Configuration** dialog that allows you to save the configuration and enter a name for it.

Update Configuration

If you change the active configuration, this is indicated by an asterisk after the configuration name. Use this function to save changes to the active configuration.

Rename Configuration

Opens the **Rename Configuration** dialog that allows you to rename the active configuration.

Delete Configuration

Allows you to delete the active configuration.

Move Configuration to Position

This function becomes available if 2 or more configurations exist. It allows you to change the position of the active configuration on the menu. This is useful as you can assign key commands to the first 8 configurations in the **Channel & Track Visibility** category of the **Key Commands** dialog.

Saving Configurations

To quickly switch between different channel setups, you can save configurations. The configurations contain visibility and zone settings as well as the show/hide status of channel types and racks.

PROCEDURE

1. Set up the configuration that you want to save.
 2. On the toolbar, click **Configurations**.
 3. From the pop-up menu, select **Add Configuration**.
 4. In the **Add Configuration** dialog, enter a name for the configuration.
 5. Click **OK**.
-

RESULT

The configuration is saved and you can return to it at any time.

Channel Visibility Agents

Channel visibility agents allow you to show or hide all channels, selected channels, or channels with certain properties.

To open the **Channel Visibility Agents** pop-up menu, do one of the following:

- Click **Channel Visibility Agents** on the toolbar.
- In the **Channel Selector**, open the **Visibility** tab and right-click to open the context menu.

Showing Channels with Specific Properties

- To open the **Channel Visibility Agents** pop-up menu, click **Channel Visibility Agents** on the toolbar.

Show all Channels

Shows all channels of your project.

Show Only Selected Channels

Shows only channels that are selected.

Hide Selected Channels

Hides all channels that are selected.

Show Channels for Tracks with Data

Shows all channels for tracks with events or parts.

Show Channels for Tracks with Data at the Cursor Position

Shows all channels for tracks with events or parts at the cursor position.

Show Channels for Tracks with Data between the Locators

Shows all channels for tracks with events or parts between the locators.

Show Channels that are Connected to the First Selected Channel

Shows all channels that are connected to the channel you first selected.

NOTE

You can assign key commands for the channel visibility agents in the **Channel & Track Visibility** category of the **Key Commands** dialog.

Undoing/Redoing Visibility Changes

You can undo/redo up to 10 visibility changes.

PROCEDURE

1. On the **MixConsole** toolbar, click **Channel Visibility Agents**.
 2. Select **Undo Visibility Change** or **Redo Visibility Change**.
-

Rack Selector

The rack selector allows you to activate specific **MixConsole** functions that are organized in racks, such as routing, insert, or send handling.

Channel Racks

You can activate and deactivate the different channel racks in the **MixConsole**.

- To open the rack selector, click **Select Racks**.



Depending on the channel type, you can activate/deactivate the following racks:

Hardware

Allows you to control your audio hardware effects. This rack is only available if supported by your hardware.

Routing

Allows you to set up the input and output routing. For MIDI, you can also select the MIDI channel.

Pre (Filters/Gain/Phase)

For audio-related channels, it contains input filter and gain controls along with **Phase** and **Gain** controls. For MIDI channels, it contains an **Input Transformer** control.

Inserts

Allows you to select insert effects for your channel.

Equalizers (audio-related channels only)

Allows you to set the channel EQ.

Channel Strip (audio-related channels only)

Allows you to integrate channel strip modules, such as Gate, Compressor, EQ, Transformer, Saturator, and Limiter that allow you to enhance your sound.

Sends

Allows you to select send effects for your channel.

Cue Sends (audio-related channels only) (Cubase Pro only)

Allows you to activate and control the level and pan for up to 4 cue sends.

Direct Routing (Cubase Pro only)

Allows you to set and activate outputs for all selected channels at once.

Track Quick Controls

Allows you to add quick controls for instant access.


Device Panels (Cubase Pro only)

Allows you to view the available device panels.

Rack Settings

The **Rack Settings** pop-up menu allows you to make settings for the racks.

- To open the **Rack Settings** pop-up menu, click **Rack Settings**.



Exclusive Expanded Rack

Shows the selected rack exclusively and collapses the other racks.

Fixed Number of Slots

Shows all available slots for the **Inserts**, **Sends**, **Cues**, and **Quick Controls** racks.

Link Racks to Configurations

If this option is activated, the rack status is taken into account when you save and load a configuration.

Show Pre/Filters as <Combined Label & Setting>

Select **Combined Label & Setting** if you want to show the label and the setting in one line.

Select **Separate Label & Setting** if you want to show the label and the setting in separate lines.

Show Inserts as <Plug-in & Preset Names>

Select **Plug-in Names** if you want to show the plug-in names only.

Select **Plug-in & Preset Names** if you want to show the plug-in and the preset names.

Show All Channel Strip Controls

Shows all available controls on the **Channel Strip** rack.

Show One Channel Strip Type

Shows only one channel strip type at a time.

Show Sends as <Combined Destination & Gain>

Select **Combined Destination & Gain** if you want to show the destination and the gain in one line.

Select **Separate Destination & Gain** if you want to show the destination and the gain in separate lines.

Show Quick Controls as <Combined Destination & Value>

Select **Combined Destination & Value** if you want to show the destination and the value in one line.

Select **Separate Destination & Value** if you want to show the destination and the value in separate lines.

Linking Channels


In Cubase Pro, you can link selected channels in the **MixConsole** to form a link group. Any change that is applied to one channel is mirrored by all linked channels, depending on which settings are activated in the link group settings. In Cubase Artist, you can only link selected channels temporarily.

The **Link Group** options on the **MixConsole** toolbar allow you to link channels and to edit links and linking configuration.



Link Group Settings (Cubase Pro only)

The **Link Group Settings** dialog allows you to specify the channel settings that are linked.



- To open the **Link Group Settings** dialog, click **Link** on the **MixConsole** toolbar.

The following options are available:

Name

Allows you to enter a name for the link group.

Use VCA Fader

Activate this option to assign the link group to a VCA fader.

Volume

Activate this to link the volume of the linked channels.

Pan

Activate this to link the panorama of the linked channels.

EQ

Activate this to link the equalizers of the linked channels.

Dynamics (Compressor, Gate, etc.)

Activate this to link the dynamics of the linked channels.

Sends

Activate this to link the sends of the linked channels.

Inserts

Activate this to link the inserts of the linked channels.

Mute/Solo/Listen

Activate this to link the mute, solo, and listen states of the linked channels.

Automation Read/Write

Activate this to link the automation read/write states of the linked channels.

Routing

Activate this to link the routing of the linked channels.

Selection

Activate this to link the selection of the linked channels.

Record Enable/Monitor

Activate this to link the record enable/monitor states of the linked channels.

NOTE

By default the volume, sends, routing, and selection settings are activated. If you associate a link group to a VCA fader, only the sends and the routing parameters are activated.

Display Line (Cubase Pro only)

Whenever you create a link group, a display line is added on top of the fader section in the **MixConsole**.



The display line shows the number and the name of the created link group and provides a **Link Settings** pop-up menu that allows you to edit the link group settings.

On the display line, you can change the name of the link group by double-clicking and entering a different name. If you hold down a modifier key and double-click the name, the **Link Group Settings** dialog opens.

NOTE

If you use a VCA fader for the link group, the displayed link group name on the fader is also changed.

The pop-up menu provides the following options:

Unlink Selected Channels

Only available for a selected link group. Select this option to remove the link between the channels. This removes the link group. If you use a VCA fader, you must specify if you want to revert to the original automation of the linked channels. A VCA fader that controls this link group is not removed.

Edit Link Group Settings

Allows you to change the link group settings.

Included in Link Group: <name of link group>

Shows the link group to which the selected channel belongs. You can assign the selected channel to a different link group. This removes the channel from the current group. If you only want to remove the selected channel from the link group, select **None**.

Linked Channels

Shows which channels are linked in the link group.

RELATED LINKS

[Changing the Link Group Settings \(Cubase Pro only\)](#) on page 333

[Adding Channels to Link Groups \(Cubase Pro only\)](#) on page 333

[Removing Channels from Link Groups \(Cubase Pro only\)](#) on page 334

[VCA Faders \(Cubase Pro only\)](#) on page 365

Creating Link Groups (Cubase Pro only)

You can link several channels to form a link group.

PROCEDURE

1. Select the channels that you want to link.
2. On the **MixConsole** toolbar, click **Link**.
3. In the **Link Group Settings** dialog, activate the parameters that you want to link.
4. Click **OK**.

RESULT

The number and name of the link group is indicated above the channel name in the display line.

NOTE

- If you link groups, insert and channel strip module linking is applied at the slot level. For example, if you change the settings for insert slot 3 on one channel, these changes are also applied to slot 3 on the other channels. Insert effects in other slots remain unaffected.
- If you select a channel that belongs to a link group, all channels in this link group are selected by default. To prevent the multiple selection of all channels that belong to a link group, deactivate **Selection** in the **Link Group Settings** dialog.

RELATED LINKS

[Link Group Settings \(Cubase Pro only\)](#) on page 331

Changing the Link Group Settings (Cubase Pro only)

If you change a setting for a channel of a link group, the change is applied to the whole group.

- To change the link settings for an existing link group, select the group, on the **MixConsole** toolbar, click **Edit Link Group Settings**, and change the settings in the **Link Group Settings** dialog.
- To unlink channels, select one of the linked channels and click **Link** on the **MixConsole** toolbar.
- To prevent the multiple selection of all channels that belong to a link group, deactivate **Selection** in the **Link Group Settings** dialog.
- To make individual settings and changes for a channel in a link group, activate **Sus** on the **MixConsole** toolbar or press **Alt**.
- To make absolute instead of relative value changes, activate **Abs** on the **MixConsole** toolbar.

NOTE

The automation tracks for linked channels are not affected by the **Link** function.

RELATED LINKS

[Link Group Settings \(Cubase Pro only\)](#) on page 331

Adding Channels to Link Groups (Cubase Pro only)

You can add a channel to an existing link group.

PROCEDURE

1. On the display line of the channel that you want to add, open the pop-up menu.

2. Select **Included in Link Group: <None>** and select the link group.
-

RESULT

The channel is added to the link group.

Removing Channels from Link Groups (Cubase Pro only)

You can remove a channel from an existing link group.

PROCEDURE

1. On the display line of the channel that you want to remove, open the pop-up menu.
 2. Select **Included in Link Group: <link group name>**, and from the link group list, select **None**.
 3. If the channel is controlled by a VCA fader, specify if the channel keeps the combined automation.
-

RESULT

The channel is removed from the link group.

Using Quick Link

You can activate the **Temporary Link Mode** to synchronize all touched parameters of selected channels.

PROCEDURE

1. Select the channels that you want to link.
2. On the **MixConsole** toolbar, activate **Q-Link**.

NOTE

You can also press **Shift-Alt** to temporarily link channels. In that case, the link is only active as long as you press the keys.

3. Change the parameters for one of the selected channels.
-

RESULT

The changes are applied to all selected channels until you deactivate **Q-Link**.

Functions Menu

The **Functions Menu** contains tools and shortcuts for settings and functions in the **MixConsole**.

- To open the **Functions Menu**, click **Functions Menu** in the top right corner of the **MixConsole**.



Scroll to Selected Channel

If this option is activated and you select a channel in the **Visibility** tab, the selected channel is automatically displayed in the **Fader** section.

Copy First Selected Channel's Settings

Copies the settings of the first selected channel.

Paste Settings to Selected Channels

Pastes the settings to the selected channels.

Zoom

Opens a submenu where you can increase or reduce the channel width and the rack height.

Open Audio Connections

Opens the **Audio Connections** window.

Control Room Cue Channels

Opens a submenu where you can activate/deactivate cue channels and change level and panning settings.

Constrain Delay Compensation

Allows you to activate/deactivate the **Constrain Delay Compensation** that keeps all channels in perfect sync and automatically compensates any delay inherent in VST plug-ins during playback.

Direct Routing: Summing Mode On/Off

Allows you to feed your signals to several outputs at the same time.

After Fader Listen Mode (Cubase Pro only)

Allows you to enable/disable that the signal of a listen-enabled channel is routed to the **MixConsole** channel after applying the fader and pan settings.

EQ/Filter Transition

Allows you to change the **EQ/Filter Transition** mode from **Soft** to **Quick**.

Save Selected Channels

Saves the settings for the selected channels.

Load Selected Channels

Loads the settings for the selected channels.

Global Meter Settings

Opens a submenu where you can set up the global meter settings.

Reset MixConsole Channels

Allows you to reset EQ, insert, and send effect settings for all or selected channels. Solo and mute buttons are deactivated, the volume fader is set to 0 dB, and pan is set to the center position.

Link MixConsoles

If you opened more than one **MixConsole**, you can link them.

Saving MixConsole Settings

You can save **MixConsole** settings for selected audio-related channels in the **MixConsole** and load them into any project.

PROCEDURE

1. Select the channels with the settings that you want to save.
 2. Select **Functions > Save Selected Channels**.
 3. In the file dialog, specify the file name and location.
 4. Click **Save**.
-

RESULT

The settings for the selected channels are saved with the file extension `.vmx`. The input/output routing is not saved.

Loading MixConsole Settings

You can load **MixConsole** settings that have been saved for selected channels.

PROCEDURE

1. Select the same number of channels that you selected when you saved your **MixConsole** settings.
The loaded **MixConsole** settings are applied in the same order as originally saved. For example, if you have saved the settings for channels 4, 6, and 8, and apply these settings to channels 1, 2, and 3, the settings saved for channel 4 are applied to channel 1, the settings saved for channel 6 to channel 2, and so on.
2. Select **Functions > Load Selected Channels**.
3. In the **Load Selected Channels** dialog, select the `.vmx` settings file and click **Open**.

RESULT


The channel settings are applied to the selected channels.

NOTE

When you apply loaded **MixConsole** settings to fewer channels, some of the saved settings are not applied. Since the saved settings are applied from left to right as shown in the **MixConsole**, the settings for the channels furthest to the right are not applied to any channels.

Fader Section

The fader section is the heart of the **MixConsole**. It shows input and output channels together with audio, instrument, MIDI, group, FX, VCA fader (Cubase Pro only), and ReWire channels.



NOTE

If a channel is deactivated in the channel selector or if its channel type is deactivated, it is not shown in the fader section. The **MixConsole** in the lower zone of the **Project** window does not follow any visibility changes you perform in the **MixConsole** window and vice versa. It is linked to the track visibility of the **Project** window.

The fader section allows you to do the following:

- Edit link group settings (Cubase Pro only)
- Set panorama
- Activate mute and solo
- Enable Listen mode
- Open channel settings
- Set volume
- Enable automation
- Set input levels

NOTE

All fader section functions and settings are also available in the **MixConsole** in the lower zone of the **Project** window.

RELATED LINKS

[Changing the Link Group Settings \(Cubase Pro only\)](#) on page 333

[Using Channel Settings](#) on page 339

[Write/Read Automation](#) on page 606

[Showing/Hiding MixConsole Channels in the Lower Zone](#) on page 318

Setting Pan

For each audio-related channel with at least a stereo output configuration, you can find a pan control at the top of the fader section. For MIDI channels, the pan control sends out MIDI pan messages. The result depends on how your MIDI instrument is set to respond to pan.

The pan control allows you to position a channel in the stereo spectrum. Cubase Pro only: This control is different for stereo and surround configurations. Channels with a multi-channel output configuration feature a miniature **VST MultiPanner** control.

- To make fine adjustments, hold down **Shift** when you move the pan control.
- To select the default center pan position, hold down **Ctrl/Cmd**, and click the pan control.
- To edit the value numerically, double-click the pan control.

RELATED LINKS

[Creating New Projects](#) on page 83

[Surround Sound \(Cubase Pro only\)](#) on page 584

Stereo Balance Panner

The stereo balance panner allows you to control the balance between the left and right channels. It is activated by default.



Stereo Combined Panner (Cubase Pro only)

With the stereo combined panner, the left and right pan controls are linked and keep their relative distance if you move them. It is available for channels with a stereo input and output configuration.

- To activate this panner, open the context menu for a pan control and select **Stereo Combined Panner**.



- To set the pan independently for the left and right channels, hold down **Alt** and drag left or right.
- To reverse the left and right channels, pan the left channel to the right and the right to the left.

The area between the pan controls changes the color to indicate that the channels are reversed.

- To sum two channels, set them to the same pan position (mono).
Note that this increases the volume of the signal.
- To specify the default stereo panner mode for new audio tracks, set the **Default Stereo Panner Mode** in the **Preferences** dialog (**VST** page).

Panning Bypass

You can bypass the panning for all audio-related channels.

- To activate panning bypass, click the button to the left or press **Ctrl/Cmd-Alt-Shift** and click the pan control.
- To deactivate panning bypass, press **Ctrl/Cmd-Alt-Shift** and click again.

When panning is bypassed for a channel, the following happens:

- Mono channels are panned center.
- Stereo channels are panned hard left and right.
- Cubase Pro only: Surround channels are panned center.

Using Solo and Mute

You can silence one or several channels using **Solo** and **Mute**.

- To silence a channel, click **Mute**.
Click again to deactivate the mute state for the channel.
- To mute all other channels, click **Solo** for a channel.
Click again to deactivate the solo state.
- To deactivate the mute or solo states for all channels simultaneously, click **Deactivate All Mute States** or **Deactivate All Solo States**.
- To activate exclusive solo mode, hold down **Ctrl/Cmd** and click **Solo** for the channel.
The **Solo** buttons of all other channels are deactivated.
- To activate solo defeat for a channel, **Alt-click Solo**.



You can also click and hold **Solo** to activate solo defeat. In this mode, the channel is not muted when you solo another channel. **Alt-click** again to deactivate solo defeat.

Listen Mode (Cubase Pro only)

The listen mode allows you to quickly check the signal that is coming from selected channels without interrupting and interfering with the actual mix. During a recording session it allows the sound engineer in the control room to attenuate the signal that is coming from one of the musicians while the recording continues undisturbed, for example.

NOTE

To enable the listen mode, you need to enable the **Control Room**.

- To enable the listen mode, click **Listen** for a channel. This routes the channel to the **Control Room** without interrupting the signal flow.
- To turn off listen mode for all channels simultaneously, click **Deactivate All Listen States** on the **MixConsole** toolbar.

Using Channel Settings

You can open each **MixConsole** channel in a separate **Channel Settings** window. This allows for better overview and editing of the channel settings.

- To open the channel settings for a specific channel, click **E** in the fader section.



The **Channel Settings** window for audio-related channels is divided into several sections:

- **Channel Inserts**
- **Channel Faders**
- **Direct Routing**
- **Channel Sends**

The **Channel Strip** and **Equalizer** are always available.

The sections are arranged in zones at the left and right of the **Channel Settings** window.

- To show a pane with options to open or close the sections, position the mouse pointer at one of the edges of the **Channel Settings** window.

The channel settings are especially suitable for the following actions:

- Routing inserts

This is done on the **Routing** tab in the **Inserts** section.

- Moving the channel strip to Pre/Post-Inserts position
By default, the inserts are positioned before the channel strip in the signal flow. In the **Inserts** section, you can change this by clicking the arrow at the top of the **Strip** tab. The tabs are swapped.
- Making EQ settings
The channel settings feature a large EQ curve display with several modes. By default, the equalizer controls are hidden, but you can click the little button at the top right corner to show the equalizer controls or the equalizer knob controls below the EQ curve.



- Panning sends
This is done on the **Panning** tab in the **Sends** section.
- Showing the output chain
If you click **Show Output Chain**  on the toolbar, the output chain is shown in the **Channel Faders** section. This allows you to keep track of more complicated output routings.
- Browsing through channels

RELATED LINKS

- [Equalizer Settings](#) on page 349
- [Routing Editor](#) on page 399
- [Direct Routing \(Cubase Pro only\)](#) on page 360

Browsing through Channels

Every channel has its own **Channel Settings** window, but you can view any channel's settings from a single window. This allows you to have a single **Channel Settings** window open in a convenient position on the screen and use it for all your EQ and channel effect settings.

To select a channel in the **Channel Settings** window, proceed as follows:

- To show the previous/next channel, click **Go to Previous/Next Channel**.
- To browse through the edited channels, click **Go to Last/Next Edited Channel**.
The buttons are only available if at least 2 channels have been edited.
- Click the channel name or the **Search** tool on the toolbar and select a channel.
- Select a channel in the **MixConsole** to select the corresponding channel in the **Channel Settings** window.

This is the default behavior. If this is not what you want, open the **Functions** menu and deactivate **Follow 'e' buttons or selection changes**.

- Select a track in the **Project** window to select the corresponding channel in the **MixConsole** and the **Channel Settings** window.

This is the default behavior. If this is not what you want, deactivate **Sync Selection in Project Window and MixConsole** in the **Preferences** dialog (**Editing—Project & MixConsole** page).

Setting Volume

Each channel in the fader section of the **MixConsole** has a volume fader. The fader levels are displayed below the fader, in dB for audio-related channels and as MIDI volume (0 to 127) for MIDI channels.

- To change the volume, move the fader up or down.
- To make fine volume adjustments, press **Shift** while moving the faders.
- To reset the volume to its default value, press **Ctrl/Cmd** and click a fader.

For audio channels, the volume fader controls the volume of the channel before it is routed to an output bus, directly or via a group channel. For output channels, the volume fader controls the master output level of all audio channels that are routed to an output bus. For MIDI channels, the volume fader controls the volume changes in the **MixConsole** by sending out MIDI volume messages to the connected instruments that are set to respond to MIDI messages.

Global Meter Setting

You can change the meter characteristics for audio channels using the context menu of the channel meter.

Right-click the channel meter and select one of the following options from the **Global Meter Settings** menu:

Meter Peak Options - Hold Peaks

The highest registered levels are held and shown as static horizontal lines in the meter.

Meter Peak Options - Hold Forever

If this option is activated, the peak levels are shown until you reset the meters. If this option is deactivated, you can use the **Meters' Peak Hold Time** parameter in the **Preferences** dialog (**Metering** page) to specify for how long the peak levels are held. The peak hold time can be between 500 and 30000 ms.

Meter Position - Input

If this option is activated, the meters show input levels for all audio channels and input/output channels. The input meters are post input gain.

Meter Position - Post-Fader

If this option is activated, the meters show post-fader levels.

Meter Position - Post-Panner

If this option is activated, the meters show post-fader levels and also reflect pan settings.

Reset Meters

Resets the meters.

Level Meters

The channel meters show the level when you play back audio or MIDI. The **Meter Peak Level** indicator shows the highest registered level.

- To reset the peak level, **Alt**-click the **Meter Peak Level** value.

NOTE

Input and output channels have clipping indicators. When they light up, lower the gain or the levels until the indicator is no longer lit.

Input Levels

When recording digital sound, it is important to set the input levels high enough to ensure low noise and high audio quality. At the same time, you must avoid clipping (digital distortion).

Setting Input Levels

PROCEDURE

1. Select **Functions > Global Meter Settings > Meter Position** and activate **Input**.
In this mode, the input channel level meters show the level of the signal at the input of the bus, before any adjustments, such as input gain, EQ, effects, level, or pan are made. This allows you to check the level of the unprocessed signal coming into the audio hardware.
2. Play back the audio and check the level meter for the input channel.
The signal should be as loud as possible without exceeding 0 dB, that is, the clipping indicator for the input bus should not light up.
3. If necessary, adjust the input level in one of the following ways:
 - Adjust the output level of the sound source or the external mixer.
 - If possible, use the audio hardware's own application program to set the input levels. Refer to the documentation for the audio hardware.
 - If your audio hardware supports the ASIO control panel function, it may be possible to make input level settings. To open the ASIO control panel, select **Studio > Studio Setup** and in the **Devices** list, select your audio card. When this is selected, you can open the control panel by clicking **Control Panel** in the settings section to the right.
4. Optional: Select **Functions > Global Meter Settings > Meter Position** and activate **Post-Fader**.

NOTE

This allows you to check the level of the audio being written to a file on your hard disk, which is only necessary if you make any adjustments to the input channel.

5. Optional: In the **Channel Racks** section, in the **Inserts** rack, click a slot and select an effect, or in the **Equalizers** rack, make your EQ settings.
For some effects you may want to adjust the level of the signal going into the effect. Use the input gain function for this. Press **Shift** or **Alt** to adjust the input gain.
 6. Play back the audio and check the level meter of the input channel.
The signal should be reasonably loud without exceeding 0 dB, that is, the clipping indicator for the input bus should not light up.
 7. If necessary, use the input channel fader to adjust the signal level.
-

Clipping

Clipping typically occurs in the audio hardware when an analog signal is too loud and therefore converted to digital in the hardware's A/D converters.

Clipping can also occur when the signal from the input bus is written to a file on your hard disk. The reason for this is that you can make settings for the input bus, adding EQ, effects, etc. to the signal while it is being recorded. This may raise the level of the signal, which causes clipping in the recorded audio file.

Working with Channel Racks

The **Channel Racks** section contains specific **MixConsole** functions, such as routing, insert, or send handling. These are organized in racks.



NOTE

The **MixConsole** in the lower zone of the **Project** window features the **Inserts** and the **Sends** rack only.

RELATED LINKS

- [Routing](#) on page 344
- [Pre \(Filters/Gain/Phase\)](#) on page 346
- [Inserts](#) on page 347
- [Equalizers \(EQ\)](#) on page 349
- [Channel Strips](#) on page 351
- [Sends](#) on page 359
- [Cue Sends \(Cubase Pro only\)](#) on page 359
- [Direct Routing \(Cubase Pro only\)](#) on page 360
- [Track Quick Controls](#) on page 362
- [Device Panels](#) on page 363

Copying and Moving Rack and Channel Settings

You can use drag and drop to copy or move rack and channel settings.

NOTE

This function is only available in the **MixConsole** window.

Drag and drop works between different channels or different rack slots on the same channel. When you drag, a visual feedback indicates the sections where you can drop your settings.

The following applies:

- To move the rack settings from one rack to another, drag the rack and drop it on the rack to which you want to move the settings.
- To copy the rack settings from one rack to another, press **Alt**, drag the rack, and drop it on the rack to which you want to copy the settings.
- To copy the channel settings from one channel to another, drag the channel and drop it on the channel to which you want to copy the settings.

You can copy rack and channel settings between different types of channels, provided that the target channels have corresponding settings.

- For example, copying from input/output channels leaves the sends settings in the target channel unaffected.
- Cubase Pro only: For projects with surround sound, any insert effects that are routed to surround speaker channels become muted when the settings are pasted to a mono or stereo channel.

Routing

The **Routing** rack allows you to configure input and output routing, that is, setting up input and output busses.

NOTE

This channel rack is only available in the **MixConsole** window.

Input busses are used when you record on an audio track. In this case, you must select from which input bus the audio is received.

NOTE

The settings that you make for the input channel will be a permanent part of the recorded audio file.

Output busses are used when you play back an audio, group, or FX channel. In this case, you must route the channel to an output bus.

You can route the outputs from multiple audio channels to a group. For example, to control the channel levels using one fader, and to apply the same effects and equalization to all the channels.

Setting up Routing

PREREQUISITE

Set up busses and group channels in the **Audio Connections** window.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Routing** to show the **Routing** rack above the fader section.
2. Click one of the slots of the **Routing** rack to open the input or the output routing pop-up menu for a channel.
3. In the routing selector, select an entry.
 - To set up the routing for multiple selected channels simultaneously, press **Shift-Alt** and select a bus.

- To set several selected channels to incrementing busses (the second selected channel to the second bus, the third to the third bus, etc.), press **Shift** and select a bus.
 - To disconnect input or output bus assignments, select **No Bus**.
-

Input Busses

The input routing selector only lists busses that correspond to the channel configuration.

NOTE

If you select a group channel as input for an audio channel, you can record a downmix.

Input Routing Configurations for Mono Channels

- Mono input busses or individual channels within a stereo or surround input bus (Cubase Pro only).
- External inputs configured on the **Control Room** tab of the **Audio Connections** window. These can be mono or individual channels within a stereo or surround bus (Cubase Pro only). They can also be routed to the **Talkback** input.
- Mono output busses, mono group output busses, or mono FX channel output busses. These should not lead to feedback.

RELATED LINKS

[Routing](#) on page 344

Input Routing Configurations for Stereo Channels

- Mono or stereo input busses or stereo child busses within a surround bus (Cubase Pro only).
- External inputs that are configured on the **Control Room** tab of the **Audio Connections** window. These can be mono input busses or stereo input busses. They can also be routed to the **Talkback** input.
- Mono or stereo output busses, mono or stereo group output busses, and mono or stereo FX channel output busses. These should not lead to feedback.

RELATED LINKS

[Routing](#) on page 344

Input Routing Configurations for Surround Channels (Cubase Pro only)

- Surround input busses.
- External inputs that are configured on the **Control Room** tab of the **Audio Connections** window. These must have the same input configuration.
- Output busses. These must have the same input configuration and should not lead to feedback.

RELATED LINKS

[Routing](#) on page 344

Output Busses

For output busses any assignment is possible.

Using Group Channels

You can route the outputs from multiple audio channels to a group. This enables you to control the channel levels using one fader, apply the same effects and EQ to all channels, etc. You can also select a group channel as input for an audio track, to record a downmix of separate tracks, for example.

PREREQUISITE

You have created and set up a group channel track in stereo.

PROCEDURE

1. Route the group channel track to an output bus.
 2. Add effects to the group channel as insert effects.
 3. Route the mono audio track to the group channel.
-

RESULT

The signal from the mono audio track is sent directly to the group, where it passes through the insert effect, in stereo.

Pre (Filters/Gain/Phase)

The **Pre** rack for audio-related channels features a high-cut and a low-cut filter as well as gain and phase settings.

NOTE

This channel rack is only available in the **MixConsole** window.

For MIDI channels the **Pre** rack allows you to open the **Input Transformer**.

NOTE

You cannot edit the **Pre** rack settings in the EQ curve display.

RELATED LINKS

[Input Transformer Window](#) on page 669

[Equalizer Settings](#) on page 349

Making Filter Settings

Each audio-related channel has separate high-cut and low-cut filters that allow you to attenuate signals with frequencies that are higher or lower than the cutoff frequency.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Pre (Filters/Gain/Phase)** to show the **Pre** rack above the fader section.
2. Click to the left of the high-cut filter to activate the high-cut filter. You have the following options:
 - Drag the slider to adjust the cutoff frequency.
The available range spans from 20 kHz to 50 Hz.
 - Click **Select Filter Slope** on the right of the high-cut filter to select a filter slope.

You can choose between 6, 12, 24, 36, and 48 dB. The default value is 12 dB.

3. Click to the left of the low-cut filter to activate the low-cut filter. You have the following options:
 - Drag the slider to adjust the cutoff frequency.
The available range spans from 20 Hz to 20 kHz.
 - Click **Select Filter Slope** on the right of the low-cut filter to select a filter slope.
You can choose between 6, 12, 24, 36, and 48 dB. The default value is 12 dB.
-

RESULT

The changed settings are visible in the curve display. If you deactivate the high-cut and low-cut filters, the filter curves are removed from the display. Bypassed high-cut and low-cut filters are displayed in a different color.

Making Input Gain Settings

The **Pre-Gain** slider allows you to change the level of a signal before it reaches the EQ and the effects section. This is useful as the level going into certain effects can change the way the signal is affected. A compressor, for example, can be driven harder by raising the input gain. Gain can also be used to boost the level of poorly recorded signals.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Pre (Filters/Gain/Phase)** to show the **Pre** rack above the fader section.
 2. Drag the **Gain** slider to the left or to the right to cut or boost the gain.
-

Making Phase Settings

Each audio-related channel and input/output channel has a **Phase** button that allows you to correct the phase for balanced lines and microphones that are wired backwards or that are out of phase due to their positioning.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Pre (Filters/Gain/Phase)** to show the **Pre** rack above the fader section.
 2. Activate **Phase** to invert the phase polarity for the signal.
-

Inserts

The **Inserts** rack for audio-related channels features insert effect slots that allow you to load insert effects for a channel. For MIDI channels you can load MIDI inserts.

For further information, see the separate document **Plug-in Reference**.

RELATED LINKS

[Audio Effects](#) on page 391

Adding Insert Effects

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Inserts** to show the Inserts rack above the fader section.
2. Click one of the insert slots to open the insert selector.

3. Click an insert effect to select it.
-

RESULT

The selected insert effect is loaded and automatically activated. Its plug-in panel opens.

Moving Inserts to Post-Fader or Pre-Fader Position


For each audio-related channel, you can add pre-fader and post-fader inserts.

PROCEDURE

- Do one of the following:
 - Right-click an insert effect in a pre-fader position, and from the context menu, select **Set as last Pre-Fader Slot**.
 - Click and drag the separator for pre-/post-fader slots up or down.
-

RESULT

The number of pre-fader and post-fader slots is adjusted. The color and the separator line show which effect is pre-fader and which is post-fader.



Bypassing Insert Effects

- To bypass all inserts, click **Bypass** at the top of the **Inserts** rack.
- To bypass a single insert, click the button on the left of the inserts slot.
- To deactivate bypass, click the button again.

Activating Side-Chain for Inserts

Some of the inserts feature side-chain functionality.

PROCEDURE

1. Right-click an insert effect.
 2. From the context menu, select **Activate Side-Chain**.
-

Saving/Loading FX Chain Presets

You can save and load all insert rack settings using FX chain presets. FX chain presets have the file name extension `.fxchainpreset`.

PROCEDURE

- In the top right corner of the **Inserts** rack, open the **Presets** pop-up menu and perform one of the following actions:
 - To save the current settings as a preset, select **Save FX Chain Preset** and name your preset.
 - To load a preset, select **Load FX Chain Preset** and select a preset.

NOTE

You can also apply inserts together with EQ and channel strip settings from track presets. You can load, tag, and save FX chain presets in the **MediaBay**.

Equalizers (EQ)

The **Equalizers (EQ)** rack is only available for audio-related channels. It features a built-in parametric equalizer with up to 4 bands for each audio channel.


NOTE

This channel rack is only available in the **MixConsole** window.

Activating Equalizer Bands


PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Equalizers** to show the **EQ** rack above the fader section.
2. Click **Activate Band** to activate an EQ band.



Equalizer Settings

You can make equalizer settings for the 4 bands. These have different default frequency values and different Q names. However, they all have the same frequency range (20 Hz to 20 kHz). You can specify different filter types for each individual module.



- 1 **Bypass EQ**
Click to bypass all EQ bands.
- 2 **Curve Display**

Click on the display in a channel to show a larger version. The display is also available in the **Equalizers** section of the **Inspector** and in the **Channel Settings** dialog.

Hovering with the mouse over the display shows a cross-hair cursor. The current mouse position shows the frequency, note value, offset, and level at the top or bottom of the display.

- Click and hold to add a curve point and activate the corresponding EQ band.
- Double-click the curve point to deactivate it.
- Drag the curve point up or down to adjust the gain.
- Press **Ctrl/Cmd** to edit only the gain.
- Drag left or right to adjust the frequency.
- Press **Alt** to edit only the frequency.
- Press **Shift** while dragging to set the Q-factor.
- To invert the EQ curve, open the context menu and select **Invert EQ Settings**.

The final curve shows the EQ settings as well as active high-cut and low-cut filters of the **Pre** rack settings. Bypassed filter settings are shown in a different color than the active settings. Disabled filter settings are hidden from the display.

NOTE

You cannot edit the high-cut and low-cut filters in the curve display. To edit the filters, open the **Pre** rack.


3 Select Preset

Opens a pop-up menu where you can load/save a preset.

4 Activate Band

Click to activate/deactivate an EQ band.

Band Settings



1 Activate Band

Activates the equalizer band.

2 Gain

Set the amount of cut or boost. The range is ± 24 dB.

3 Frequency

Sets the center frequency of the frequency range to be cut or boosted. You can set the frequency either in Hz or as a note value. If you enter a note value, the frequency is automatically displayed in Hz. For example, a note value of A3 sets the frequency to 440 Hz. When you enter a note value, you can also enter a cent offset. For example, enter A5 -23 or C4 +49.

NOTE

Ensure that you enter a space between the note and the cent offset. Only in this case, the cent offsets are taken into account.

4 Q-Factor

Determines the width of the affected frequency range. Higher values give narrower frequency ranges.

5 Type

Opens a pop-up menu where you can select an EQ type for the band. Bands 1 and 4 can act as parametric, shelving, or high/low-cut filters. EQ bands 2 and 3 are always parametric filters.

RELATED LINKS

[Making Filter Settings](#) on page 346

Saving/Loading EQ Presets

You can save and load EQ presets.

PROCEDURE

- In the top right corner of the **EQ** rack, open the presets pop-up menu and perform one of the following actions:
 - To save the current settings as a preset, select **Save Preset** and name your preset.
 - To load a preset, select **Load Preset** and select a preset.

NOTE

You can also apply EQ together with insert and channel strip settings from track presets. You can load, tag, and save EQ presets in the **MediaBay**.

Channel Strips

The **Channel Strip** rack is only available for audio-related channels. It allows you to load built-in processing modules for separate channels.

NOTE

This channel rack is only available in the **MixConsole** window.

Channel Strip Modules

The channel strips allow you to apply modules directly to specific channels. You can change the position of specific modules in the signal flow via drag and drop.

Gate

Allows you to silence audio signals below a set threshold level. As soon as the signal level exceeds the set threshold, the gate opens to let the signal through.

Compressor

Allows you to create smooth compression effects. Drag the compressor up or down to change its position in the signal flow.

EQ

Allows you to make EQ settings.

Tools

Provides various tools.

Sat

Allows you to add warmth to the sound.

Limit

Allows you to avoid clipping even at high levels.

Noise Gate

Noise gating silences audio signals below a set threshold. As soon as the signal level exceeds the threshold, the gate opens to let the signal through.

Threshold (-60 to 0 dB)

Determines the level at which **Gate** is activated. Signal levels above the set threshold trigger the gate to open, and signal levels below the set threshold close the gate.

Side-Chain

Activates the external side-chain.

Release (10 to 1000 ms or Auto mode)

Sets the time after which the gate closes (after the set **Hold** time). If **Auto Release** is activated, **Gate** automatically finds the best release setting for the audio material.

State LED

Indicates whether the gate is open (LED lights up in green), closed (LED lights up in red), or in an intermediate state (LED lights up in yellow).

Attack (0.1 to 1000 ms)

Sets the time after which the gate opens when it is triggered.

Range

Adjusts the attenuation of the gate when it is shut. If **Range** is set to , the gate is completely shut. The higher the value, the higher the level of the signal that passes through the shut gate.

Activate Filter

Activates/Deactivates the internal side-chain and allows you to set up a filter to modify the signal detection.

Filter Frequency (50 to 20000 Hz)

If the internal side-chain is activated, this parameter sets the filter frequency for the signal detection.

Q-Factor (0.01 to 10000)

If the internal side-chain is activated, this parameter sets the resonance of the filter for the signal detection.

Listen Filter

Allows you to monitor the filtered signal.

Compressor

This channel strip module reduces the dynamic range of the audio, making softer sounds louder or louder sounds softer, or both. Open the pop-up menu to select between **Standard Compressor**, **Tube Compressor**, and **Vintage Compressor**.

Standard Compressor

Allows you to create smooth compression effects. Drag the compressor up or down to change its position in the signal flow.

Threshold (-60 to 0 dB)

Determines the level where the compressor kicks in. Only signal levels above the set threshold are processed.

Side-Chain

Activates the external side-chain.

Ratio (1:1 to 8:1)

Sets the amount of gain reduction that is applied to signals above the set threshold. A ratio of 3:1 means that for every 3 dB the input level increases, the output level increases by 1 dB.

Gain Reduction LED

Indicates the amount of compression of the signal.

Attack (0.1 to 100 ms)

Determines how fast the compressor responds to signals above the set threshold. If the attack time is long, more of the early part of the signal passes through unprocessed.

Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to the original level when the signal drops below the threshold. If **Auto** is activated, the compressor automatically finds the best release setting for the audio material.

Make-up (0 to 24 dB or Auto mode)

Compensates for output gain loss that is caused by compression. If **Auto** is activated, the knob becomes dark and the output is automatically adjusted for gain loss.

Tube Compressor

This versatile compressor with integrated tube-simulation allows you to achieve smooth and warm compression effects. The VU meter shows the amount of gain reduction. **Tube Compressor** features an internal side-chain section that lets you filter the trigger signal.

Input (-24.0 to 48.0 dB)

Determines the compression amount. The higher the input gain, the more compression is applied.

Side-chain

Activates the external side-chain.

Output (-12.0 to 12.0 dB)

Sets the output gain.

Gain Reduction LED

Indicates the amount of compression of the signal.

Attack (0.1 to 100.0 ms)

Determines how fast the compressor responds. If the attack time is long, more of the initial part of the signal passes through unprocessed.

Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to the original level. If **Auto** is activated, **Tube Compressor** automatically finds the best release setting for the audio material.

Drive (1.0 to 6.0)

Controls the amount of tube saturation.

Mix (0 to 100)

Sets the level balance between the dry signal and the wet signal.

VintageCompressor

VintageCompressor is modeled after vintage type compressors.

Input (-24 to 48 dB)

In combination with the **Output** setting, this parameter determines the compression amount. The higher the input gain setting and the lower the output gain setting, the more compression is applied.

Side-chain

Activates the external side-chain.

Output (-48 to 24 dB)

Sets the output gain.

Gain Reduction LED

Indicates the amount of compression of the signal.

Attack (0.1 to 100 ms)

Determines how fast the compressor responds. If the attack time is long, more of the early part of the signal passes through unprocessed.

Punch (On/Off)


If this option is activated, the early attack phase of the signal is preserved, retaining the original punch in the audio material, even with short **Attack** settings.

Release (10 to 1000 ms or Auto mode)

Sets the time after which the gain returns to its original level. If **Auto** is activated, **Vintage Compressor** automatically finds the best release setting for the audio material.

EQ

You can make equalizer settings for the 4 bands. These have different default frequency values and different Q names. However, they all have the same frequency range (20 Hz to 20 kHz). You can specify different filter types for each individual module.



1 Activate Band x

Activates the equalizer band.

2 Select EQ Band x Type

Opens a pop-up menu where you can select an EQ type for the band. Bands 1 and 4 can act as parametric, shelving, or high/low-cut filters. EQ bands 2 and 3 are always parametric filters.

3 Gain

Sets the amount of cut or boost.

4 Freq

Sets the center frequency of the frequency range to be cut or boosted.

5 Q

Determines the width of the affected frequency range. Higher values give narrower frequency ranges.

Tools

Provides various tools.

DeEsser

This channel strip module reduces excessive sibilance, primarily for vocal and speech recordings. Basically, it is a special type of compressor that is tuned to be sensitive to the frequencies produced by the s-sound. Close proximity microphone placement and equalizing can lead to situations where the overall sound is just right, but there is a problem with sibilants.

Reduction

Controls the intensity of the de-essing effect.

Side-Chain

Activates the internal side-chain filter. The input signal can then be shaped according to the filter parameters. Internal side-chaining can be useful for tailoring how the gate operates.

Release

Sets the time after which the de-essing effect returns to zero when the signal drops below the threshold.

Gain Reduction LED

Indicates the amount of compression of the signal.

Threshold

If **Auto** is deactivated, you can use this control to set a threshold for the incoming signal level above which the plug-in starts to reduce the sibilants.

Auto

Automatically and continually chooses an optimum threshold setting independent of the input signal. The **Auto** option does not work for low-level signals (<-30 db peak level). To reduce the sibilants in such a signal, set the threshold manually.

Low-Frequency

Allows you to set the low frequency band.

High-Frequency

Allows you to set the high frequency band.

Solo

Allows you to solo the frequency band to find the appropriate position and width of that band.

Diff

Allows you to listen to the sounds that the de-esser removes from the signal.

EnvelopeShaper

This channel strip module can be used to attenuate or boost the gain of the attack and release phase of audio material. You can use the knobs to change parameter values. Be careful with levels when boosting the gain and if needed reduce the output level to avoid clipping.

Attack (-20 to 20 dB)

Changes the gain of the attack phase of the signal.

SC (Side-Chain)

Activates the external side-chain.

Release (-20 to 20 dB)

Changes the gain of the release phase of the signal.

Length (5 to 200 ms)

Determines the length of the attack phase.

Output (-24 to 12 dB)

Sets the output level.

Sat

Allows you to add warmth to the sound. Open the pop-up menu to select between **Magneto II**, **Tape Saturation**, and **Tube Saturation**.

Magneto II

This channel strip module simulates the saturation and compression of recording on analog tape machines.

Saturation

Determines the amount of saturation and the generation of overtones. This leads to a small increase in input gain.

Dual Mode

Simulates the use of two tape machines.

Saturation On/Off

Activates/Deactivates the saturation effect.

Output

Allows you to adjust the output level.

Saturation Amount LED

Indicates the amount of saturation of the signal.

Low-Frequency

Sets the frequency range of the spectrum band to which the tape effect is applied.
To avoid the saturation of lower frequencies, set the value to 200 Hz or 300 Hz.

High-Frequency

Sets the frequency range of the spectrum band to which the tape effect is applied.
To avoid the saturation of very high frequencies, set the **Freq Hi** parameter to values below 10 kHz.

Solo

Allows you to hear only the set frequency range including the tape simulation effect.
This helps you to determine the appropriate frequency range.

HF-Adjust

Sets the amount of high frequency content of the saturated signal.

HF-Adjust On/Off

Activates/Deactivates the **HF-Adjust** filter.

Tape Saturation

This channel strip module simulates the saturation and compression of recording on analog tape machines.

Drive

Controls the amount of tape saturation.

Dual Mode

Simulates the use of two tape machines.

Auto Gain

Adjusts the gain automatically.

Output

Sets the output gain.

Drive Amount LED

Indicates the amount of drive of the signal.

Low-Frequency

This is a low shelving filter with fixed frequency.

High-Frequency

This is a Hi Cut filter. Use the frequency fader to reduce harshness of the output signal.

Tube Saturation

This channel strip module simulates the saturation and compression of recording of analogue tube compressors.

Drive

Controls the amount of tube saturation.

Output Gain

Sets the output gain.

Drive Amount LED

Indicates the amount of drive of the signal.

Low-Frequency

This is a low shelving filter with fixed frequency.

High-Frequency

This is a Hi Cut filter. Use the frequency fader to reduce harshness.

Limit

Allows you to avoid clipping even at high levels. Open the pop-up menu to select between **Brickwall Limiter**, **Maximizer**, and **Standard Limiter**.

Brickwall Limiter

Brickwall Limiter ensures that the output level never exceeds a set limit.

Due to its fast attack time, **Brickwall Limiter** can reduce even short audio level peaks without creating audible artifacts. However, this channel strip module creates a latency of 1 ms.

Threshold (-20 to 0 dB)

Determines the level where the limiter kicks in. Only signal levels above the set threshold are processed.

Release (ms)

Sets the time after which the gain returns to the original level when the signal drops below the threshold. If **Auto** is activated, **Brickwall Limiter** automatically finds the best release setting for the audio material.

Gain Reduction LED

Displays the amount of gain reduction.

Maximizer

This channel strip module raises the loudness of audio material without the risk of clipping.

Optimize

Determines the loudness of the signal.

Output (-24 to 6 dB)

Determines the maximum output level. Set this to 0 dB to avoid clipping.

Gain Reduction LED

Displays the amount of gain reduction.

Mix (0 to 100)

Sets the level balance between the dry signal and the wet signal.

Standard Limiter

This channel strip module is designed to ensure that the output level does not exceed a set output level, to avoid clipping in following devices. **Limiter** can adjust and optimize the **Release** parameter automatically according to the audio material, or it can be set manually.

Input (-24 to 24 dB)

Adjusts the input gain.

Output (-24 to 6 dB)

Determines the maximum output level.

Gain Reduction LED

Displays the amount of gain reduction.

Release (0.1 to 1000 ms or Auto mode)

Sets the amount of time it takes for the gain to return to its original level. If **Auto** is activated, **Limiter** automatically finds the best release setting for the audio material.

Saving/Loading Strip Presets

You can save and load strip presets. Strip presets have the file name extension `.stripreset`.

PROCEDURE

- In the top right corner of the **Channel Strip** rack, open the **Presets** pop-up menu and perform one of the following actions:
 - To save the current settings as a preset, select **Save Strip Preset** and name your preset.
 - To load a preset, select **Load Strip Preset** and select a preset.

NOTE

You can also apply channel strip settings together with insert and EQ settings from track presets. You can load, tag, and save strip presets in the **MediaBay**.

RELATED LINKS

[Loading Strip Presets](#) on page 577

Sends

The **Sends** rack for audio-related channels features send effect slots that allow you to load send effects and value sliders that allow you to determine the send level for a channel. For MIDI channels the **Sends** rack features send effect slots that allow you to load send effects.

Adding Send Effects

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Sends** to show the rack above the fader section.
 2. Click one of the send slots to open the send selector.
 3. Click a send effect to select it.
The selected send effect is loaded.
 4. Click on the left of the slot to activate the send.
-

Bypassing Send Effects

- To bypass all sends, click the bypass button at the top of the **Sends** rack.
- To deactivate bypass, click the button again.

Adding FX Channels to a Send

PROCEDURE

1. Right-click on the send slot to open the context menu.
 2. Select **Add FX Channel to <send name>**.
 3. In the **Add FX Channel Track** window, select the effect and configuration.
 4. Click **Add Track**.
-

RESULT

The FX channel track is added in the **Project** window, and the send is automatically routed to it.

Cue Sends (Cubase Pro only)

Cue sends allow you to create discrete cue mixes that performers can listen to during recording. Essentially, cue sends are stereo aux sends that are routed to cue channel outputs in the **Control Room**.

NOTE

This channel rack is only available in the **MixConsole** window.

For every cue channel defined in the **Audio Connections** window, each channel in the **MixConsole** has a cue send, with level, pan, and pre/post-fader selection.

Adding Cue Sends (Cubase Pro only)

PREREQUISITE

Create a cue channel in the **Audio Connections** window and activate the **Control Room**.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Cue Sends** to show the rack above the fader section.

2. Click one of the slots to open the send selector.
The cue sends are displayed.
 3. Click on the left of the slot to activate the cue send.
-

RESULT

You can now change the level and pan settings.

Direct Routing (Cubase Pro only)

In addition to the main output, the **Direct Routing** rack allows you to set up 7 routing destinations that are positioned post-fader and post-panner in the signal path. This way, you can switch the destination of channels and create different mix versions in one go.

In the **Direct Routing** rack, the first routing slot mirrors the routing of the main output.

NOTE

The **Direct Routing** rack is not available in the **Channel Settings** window.

Direct routing is available for audio, instrument, sampler, FX channel tracks, groups, and output busses. You can also set and activate outputs for several selected channels at once.

RELATED LINKS

[Setting Up Direct Routing](#) on page 360

[Automatic Downmixing](#) on page 361

Setting Up Direct Routing

In the **Direct Routing** rack you can assign up to 8 routing destinations to each channel.

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Direct Routing**.
The **Direct Routing** rack is shown above the fader section.
2. Select all channels for which you want to set up the same destinations, press **Shift-Alt** and click in the first slot of the **Direct Routing** rack.
3. In the routing selector, select the main output for the selected channels.

NOTE

We recommend that you choose the same set of destinations for all channels that belong together. The main output should also have the widest channel configuration, since it is used as a reference for all additional output destinations.

IMPORTANT

The routing of the main output in the first **Direct Routing** slot defines the channel width. For several functions in Cubase, for example, **Export Audio Mixdown** or surround panning, to work as expected, the main output routing must be set correctly.

4. Click in the next destination slot and select another output.
 5. Do this for as many destination slots as required (up to 8).
After routing your audio tracks to groups, you can route the groups to output busses.
 6. For each channel, you can now activate the appropriate routing destination by clicking on the corresponding slot.
The active routing destination lights up.
-

Automating Destination Switches

PROCEDURE

1. Play back your project and take note of the positions where routing changes are necessary.
2. Write-enable the corresponding track.
3. At the right moment, click on the routing destination to which you want to switch. The new destination is now active, and the switch has been recorded as automation data.
4. Continue to record destination changes for your project.

NOTE


To switch destinations for multiple channels simultaneously, select these channels and keep **Shift-Alt** pressed when activating a different destination.

Feeding Signals to Multiple Destinations

Direct routing offers a summing mode, allowing you to feed your signals to several outputs at the same time. This is useful if you want to apply an effect to several stems at the same time, for example.

PROCEDURE

1. Set up your output busses as routing destinations.
2. In the **Direct Routing** rack, open the context menu and activate **Summing Mode** for all channels that you want to sum.



NOTE

To activate this setting for all channels at once use the **Link** function.

3. Activate all outputs to which you want to route the selected channels.
-

RELATED LINKS

[Setting up Routing](#) on page 344

Automatic Downmixing

The output in the first **Direct Routing** slot defines the channel width. Since the other destinations are positioned post-panner in the signal path, they have the same channel width to start with, and the signal needs to be converted accordingly by downmixing. Cubase does that automatically.

NOTE

Always select the output with the widest channel configuration in the first slot. It is not recommended to use a setup where the main output has less channels than the direct routing destination even though it is technically possible. Upmixing might lead to unexpected side effects.

When performing an automatic downmix from 5.1 to stereo, the levels are adjusted as follows:

Automatic Downmixing from 5.1 to stereo

	L	R	C	Lfe	Ls	Rs
L	0.0		-3.01	-3.01	-6.02	
R		0.0	-3.01	-3.01		-6.02

Center and Lfe signals are split to L and R channels, Ls and Rs are sent to L and R respectively, but reduced in volume.

When performing an automatic downmix from 7.1 Music (Dolby) to 5.1 the levels are adjusted as follows:

Automatic Downmixing from 7.1 Music (Dolby) to 5.1

	L	R	C	Lfe	Ls	Rs	Sl	Sr
L	0.0						-3.01	
R		0.0						-3.01
C			0.0					
Lfe				0.0				
Ls					0.0		-3.01	
Rs						0.0		-3.01

Sl and Sr signals are split to L/R and Ls/Rs respectively, but reduced in volume.

Track Quick Controls

Track Quick Controls give you instant access to up to 8 different parameters, for example, track, effect, or instrument controls.

This saves you from having to click your way through the various windows and sections pertaining to your track.

NOTE

This channel rack is only available in the **MixConsole** window.

Adding Track Quick Controls in the MixConsole

PROCEDURE

1. On the **MixConsole** toolbar, click **Racks** and activate **Track Quick Controls** to show the rack above the fader section.
 2. Click one of the slots to open a selector.
 3. Select a parameter from the list.
-

RESULT

The selected parameter is loaded and automatically activated as **Track Quick Control**.

RELATED LINKS

[Assigning MixConsole Parameters to Quick Controls](#) on page 648

Device Panels

You can display device panels, for example, for external MIDI devices, audio track panels, or VST insert effect panels.

NOTE

This channel rack is only available in the **MixConsole** window.

For information on how to create or import MIDI device panels, see the separate document **MIDI Devices**.

RELATED LINKS

[About Device panels \(Cubase Pro only\)](#) on page 687

Adding Notes to a MixConsole Channel

PROCEDURE

1. Position the mouse pointer at the top edge of the **MixConsole**, and activate **Notepad**. The **Notepad** section is shown above the fader section.
 2. Select the channel for which you want to add notes, click in the notepad section and type in your notes.
 3. To close the notepad, press **Esc**, or click in another section of the **MixConsole**.
-

Keyboard Focus in the MixConsole

The channel selector section, the channel rack section, and the fader section can be controlled with the computer keyboard.

For this to work, the section must have the focus. If a section has the keyboard focus, the border that surrounds it is highlighted in a specific color.

Activating Keyboard Focus

PROCEDURE

1. Click in an empty area of the section to activate the keyboard focus.
 2. Press **Tab** to activate the next section. This allows you to cycle forward through the sections.
 3. Press **Shift-Tab** to activate the previous section.
-

Navigating in a Section

Once you have activated the focus for a section, you can control it with the computer keyboard. In the channel racks section and in the fader section, controls that are selected for keyboard control are indicated by a red border.

- To navigate through the controls, use the **Up Arrow**, **Down Arrow**, **Left Arrow**, **Right Arrow** keys.

- To activate or deactivate a switch, press **Return**.
- To expand or collapse an active rack, to open or close a value field in a slot, or to open the plug-in panel for a loaded plug-in, press **Return**.
- To access the controls in the left zone, press **Ctrl/Cmd-Return**.
- To access the controls in the middle zone, press **Return**.
- To access the controls in the right zone, press **Alt-Return**.
- To close a pop-up menu or a plug-in panel, press **Esc**.
- To enable or disable the loaded plug-in, press **Ctrl/Cmd-Alt-Return**.

VCA Faders (Cubase Pro only)

VCA faders serve as remote controls for groups of channel faders in the **MixConsole**.

VCA stands for Voltage-Controlled Amplifier. VCA faders were originally found on hardware mixing desks. They allowed the user to control the volume levels of several mixer channels with only one fader. To assign channel faders to a VCA fader, the respective channels must be physically connected with the VCA fader.

In Cubase, the VCA fader function is based on the same concept. VCA faders are assigned to a group of linked channels, a link group. The VCA faders control the following parameters of the link group: volume, mute, solo, listen, monitor, and record.

When you assign VCA faders, they become part of the link group.

IMPORTANT

If a VCA fader controls a link group, it cannot control another link group. If you assign a VCA fader to another group, the VCA fader is automatically removed from the former group.

You can create several VCA faders without assigning them to link groups straight away.

From a technical perspective, moving a VCA fader to a different dB level adds or subtracts the new value to or from the original values of the channels in the link group.


EXAMPLE

A channel in a link group has a level of -6 dB, the VCA fader is at the 0 position. If you move the VCA fader to a level of +3 dB, this value is added to the level of the linked channel. The linked channel now has a level of -3 dB.

VCA Fader Settings

VCA fader channels are different from the default fader channels.

Instead of the panner, the VCA faders display the link group to which they are assigned. The VCA faders also provide a pop-up menu that allows you to change the VCA fader settings.



- 1 Link group number
- 2 Link group name
- 3 VCA fader pop-up menu
- 4 Peak meter that displays the summed up level of all channel meters in the link group
- 5 Fader cap

The VCA fader pop-up menu provides the following options:

Edit Link Group Settings

Allows you to change the link group settings.

VCA Fader Controls Link Group: <link group name>

Shows the link group that the VCA fader controls. You can assign the VCA fader to a different link group. This removes the VCA fader from the current group. You can also remove the VCA fader assignment altogether. In this case, select **None**. In all cases, you must specify if you want the linked channels to revert to their original automation.

Combine Automation of VCA and Linked Channels

Combines the automation curves of VCA fader and linked channels in the **Project** window. This has the effect that the original automation curves of the linked channels are no longer used. In the **Project** window, the automation of the VCA fader is reset to the static value line. In the **MixConsole**, the VCA fader is reset to the 0 position.

NOTE

If you use this function together with bézier automation curves, the combined automation curve will consist of linear ramps with varying resolution. These should emulate the bézier curves as precisely as possible.

Linked Channels

Shows which channels are linked in the link group.

RELATED LINKS

[VCA Fader Automation](#) on page 369

[Creating Smooth Transitions Between Automation Events \(Bézier Automation Curves\)](#) on page 610
[Link Group Settings \(Cubase Pro only\)](#) on page 331

Creating VCA Faders

You can create VCA faders in several ways.

VCA faders can be created in the **MixConsole** and in the **Project** window.

In the **MixConsole**, you have the following options:

- You can create unassigned VCA faders in the fader section. They are placed at the right end of the fader section in front of the output channels and display no fader cap. The VCA faders can be assigned to link groups at a later stage. To create unassigned VCA faders in the **MixConsole**, right-click in the fader section and select **Add VCA Fader**.
- You can create VCA faders while creating link groups. The VCA faders are automatically added to the right of the link groups.

In the **Project** window, you can create VCA fader tracks in the track list. The VCA faders are placed in a **VCA Tracks** folder at the end of the track list. The VCA faders can be assigned to link groups in the **MixConsole** at a later stage.

NOTE

You can delete VCA faders only in the **Project** window.

RELATED LINKS

[Assigning VCA Faders to Link Groups](#) on page 368
[VCA Fader Track \(Cubase Pro only\)](#) on page 146
[Adding Tracks](#) on page 151

Creating VCA Faders for a Selection of Channels

You can select several channels and automatically connect the channels to a new link group, create a VCA fader, and assign the VCA fader to this link group.

PROCEDURE

1. Select several channels in the **MixConsole**.
 2. Right-click one of the selected channels.
 3. In the context menu, select **Add VCA Fader to Selected Channels**.
-

RESULT

The channels are linked in a link group. A VCA fader is created, placed to the right of the selected faders, and assigned to the link group. In the **Project** window, the VCA track is placed below the selected tracks.

NOTE

If a VCA fader is created for a selection of channels, the **Selection** option is deactivated for the link group by default. You can change this setting in the **Link Group Settings** dialog.

RELATED LINKS

[Linking Channels](#) on page 330
[Changing the Link Group Settings \(Cubase Pro only\)](#) on page 333

[Link Group Settings \(Cubase Pro only\)](#) on page 331

Assigning VCA Faders to Link Groups

You can link channels and assign VCA faders to control them.

PREREQUISITE

You have selected channels.

PROCEDURE

1. Click **Link** on the **MixConsole** toolbar.
2. In the **Link Group Settings** dialog, click in the **Name** field to enter a name for the link group.
3. Activate **Use VCA Fader**.
The **Volume** parameter is automatically deactivated.
4. Specify if you want to create a new VCA fader or select an existing VCA fader from the pop-up menu.
5. Click **OK**.

RESULT

The channels are now linked to the VCA fader. At the top of the fader section, the display line shows the number and the name of the link group. The VCA fader also displays the link group name.

NOTE

- If you want to assign the VCA fader to a different link group, you can open the pop-up menu of the VCA fader, select **VCA Fader Controls Link Group: <name of group>**, and select a different group from the list of available link groups.
- If you want to add a VCA fader quickly, select **Add VCA Fader to Selected Channels**. This automatically creates a VCA fader with a default name.

RELATED LINKS

[Link Group Settings \(Cubase Pro only\)](#) on page 331

Removing VCA Faders from Link Groups

You can remove VCA faders from link groups.

PREREQUISITE

You have selected the VCA fader that you want to remove.

PROCEDURE

1. Click **Edit Link Group Settings** on the **MixConsole** toolbar.
2. In the **Link Group Settings** dialog, deactivate **Use VCA Fader**.
The **Volume** parameter is automatically reactivated.
3. Click **OK**.
4. Specify if the channels in the link group keep the combined automation.

RESULT

The VCA fader is removed from the link group and is deleted from the list of channels.

NOTE

You can keep the VCA fader in the fader section. In this case, open the VCA fader pop-up menu, select **VCA Fader Controls Link Group: <name of group>**, and select **None**. This removes only the VCA fader assignment.

RELATED LINKS

[Link Group Settings \(Cubase Pro only\)](#) on page 331

Nested VCA Faders

VCA faders can control other VCA faders.

If you use several VCA faders that control different link groups, you can create another VCA fader that controls the VCA faders. This allows you to control the volume level of several link groups at the same time.

Technically, a VCA fader that controls other VCA faders affects the volume level of all VCA faders and linked channels.

EXAMPLE

A VCA fader (main fader) controls a nested VCA fader that has been set to -10 dB. The latter VCA fader controls a linked channel that had an original level of -3 dB and that is set to -13 dB. If you change the main fader level from 0 to +4 dB, the controlled VCA fader is set to a level of -6 dB, and the linked channel is set to a level of -9 dB.

VCA Fader Automation

VCA fader automation influences the automation of link groups.


When you create VCA faders, their tracks in the **Project** window contain the static value line that is default for all automation tracks and that turns into an automation curve once you start writing automation.

Whenever you write automation for a VCA fader of a link group, it affects the volume automation of the linked channels. This has different effects:

- If a linked channel has no automation, the VCA fader automation curve is automatically added to the automation tracks of the linked channels. The automation tracks of the linked channels show the automation that is applied through the VCA fader.
 - If a linked channel has volume automation, the VCA fader automation modifies the existing volume automation of the linked channel. The VCA fader automation and the linked channel automation are combined. The automation tracks show the original automation and the combined automation of VCA fader and linked channels.
-

EXAMPLE

The VCA fader track automation affects all channels in a link group.



For the channels, the original automation is adjusted by the volume level of the VCA fader track.

EXAMPLE

The VCA fader track automation affects an existing volume automation of an audio track.



The lighter static value line displays the VCA fader automation that has not been written yet.




The VCA fader track has a different automation curve that affects the automation of the audio track.



The underlying darker automation curve displays the original automation of the audio track. The overlaying lighter automation curve displays the combined automation.

EXAMPLE

The following illustration shows how the VCA fader automation affects the automation of the connected channels.



- 1 Automation curve of the VCA fader
- 2 Automation curve of the connected channel

3 Combined automation of VCA fader and connected channel. This is what you hear.

RELATED LINKS

[VCA Fader Settings](#) on page 365

[Creating Smooth Transitions Between Automation Events \(Bézier Automation Curves\)](#) on page 610

Control Room (Cubase Pro only)

The Control Room allows you to divide the studio environment into the performing area (studio) and the engineer/producer area (control room).

To open the **Control Room** you have the following options:

- To open the **Control Room** in a separate window, select **Studio > Control Room**.
- To open the **Control Room** section in the **MixConsole** window, click **Show/Hide Right Zone**  in the **MixConsole** toolbar.
- To open the **Control Room** section in the **Project** window, click **Show/Hide Right Zone**  in the **Project** window toolbar.

The **Control Room** is divided into 2 sections.

- The **Main** tab contains all controls that you use regularly during recording, mixing, and mastering, for example.
- The **Inserts** tab contains settings that you most probably use only once for a project.

Adding Channels to the Control Room

To be able to use the Control Room, you must add the channels that you need first.

PROCEDURE

1. Select **Studio > Audio Connections**.
2. Click **Control Room**.
3. Click **Add Channel**.

A pop-up menu lists all available channel types and shows how many instances of each type are available.

4. Select a channel type.
For most channel types, a dialog opens that allows you to choose the channel configuration.
5. Click the **Audio Device** column to set an audio device for the channel type.
6. Click the **Device Port** column to assign a port for the channel.

IMPORTANT

You cannot assign the same device port to a bus or channel and a Control Room channel at the same time.

RESULT

The Control Room functions are available for use. If you disable the Control Room, the configuration is saved and will be restored when you reenables the Control Room.

Output Routing

For the Control Room to function correctly, you must assign the Main Mix bus to the set of outputs that contains the mix that you want to hear.

If you only have one output bus, it automatically becomes the Main Mix. All other outputs are not routed through the Control Room.

Exclusive Assignment of Monitor Channels

Generally, the port assignment to the Control Room channels is exclusive. However, it can be useful to create monitor channels that share device ports with each other as well as inputs and outputs. This can be helpful if you use the same speakers as a stereo pair and also as the left and right channels of a surround speaker configuration, for example.

Switching between monitors that share device ports is seamless, multi channel audio is mixed down to stereo as needed. Only one monitor set can be active at a time.

If your scenario does not require you to assign ports to several monitor channels, it is recommended to activate the **Exclusive Device Ports for Monitor Channels** option in the **Preferences** dialog (**VST—Control Room** page). This way, you make sure that you do not accidentally assign ports to inputs/outputs and monitor channels at the same time.

IMPORTANT

The state of the **Exclusive Device Ports for Monitor Channels** preference is saved together with the Control Room presets. Therefore, if you recall a preset, your current setting in the **Preferences** dialog might be overwritten.

Control Room Channels

Each Control Room channel type that you create defines an input or output of the **Control Room**.

Monitor Channels

A monitor channel represents a set of outputs that are connected to monitor speakers in the Control Room.

You can create up to 4 monitor channels for a mono, stereo, or surround speaker configuration. Each monitor can have its own custom downmix settings, input gain, and input phase settings.

NOTE

Monitor channels can share hardware inputs or outputs with another bus or channel. When you create the connections for the monitor channels, device ports that are already used for other busses or channels are shown in red on the **Device Port** pop-up menu. If you select a used port, its previous connection is lost.

Phones Channel

You can use the phones channel in the Control Room to listen to cue mixes.

You can create 1 phones channel for a stereo configuration. It allows you to listen to the main mix or cue mixes or to external inputs on a pair of headphones. You can also use it for previewing.

Cue Channels

You can use cue channels for sending cue mixes, also known as headphone mixes, to performers in the studio during recording.

You can create up to 4 cue channels in mono or stereo for 4 discrete cue mixes. Cue channels have talkback and click functions. They allow you to monitor the main mix, external inputs, or a dedicated cue mix.

EXAMPLE

If you have 2 available headphone amplifiers for performers, you can create 1 cue channel for each cue mix and name them according to their function: vocalist mix, bass player mix, etc.

Cue Channels and Cue Sends

For every cue channel that you define in the **Audio Connections** window, each channel in the **MixConsole** has a cue send with level, pan, and pre/post-fader selection. These cue sends can be used to create discrete cue mixes that performers can listen to.

- To show the cue sends, open the **MixConsole** and activate **Racks > Cue Sends**.

External Inputs

You can use external inputs for monitoring external devices, such as CD players, multi-channel recorders, or any other audio source.

You can create up to 6 external inputs for a mono, stereo, or surround speaker configuration.

NOTE

If you select external inputs as input source of an audio channel, you can record them. In this case, you do not need to assign the device ports to the input channel.

Talkback Channels

You can use talkback channels for communication between the Control Room and performers in the studio.

You can create 1 talkback channel and assign a mono input channel to each one of them.

You can also use talkback channels as input source for audio tracks and record them. You can route them to each cue channel and use different levels.

You can insert effects like a compressor or limiter on talkback channels. This ensures that erratic levels do not disturb performers and that clear communication with everyone is possible.

NOTE

The **Auto Disable Talkback Mode** option in the **Preferences** dialog (**VST—Control Room** page) allows you to specify how talkback works during playback and recording.

Control Room - Main Tab

The **Control Room Main** tab displays information and controls for the channels that you define on the **Control Room** tab in the **Audio Connections** window.

The **Control Room Main** tab is divided into a number of sections that you open by clicking their header. To open several sections simultaneously, use **Ctrl/Cmd-click**.



External

The **External** section allows you to use external inputs for monitoring external devices. It is only shown if you have added more than one external input in the **Audio Connections** window.



To switch to another external input, click the input name and select a new external input from the pop-up menu.

Cue Channel

The **Cue Channel** section allows you to set up cue channels for sending cue mixes.



1 Activate Cue Channel

Allows you to activate/deactivate the cue channel.

2 Source Selectors

Allow you to select the source for the cue channel: monitor mix (**Mix**), external inputs (**Ext**), or the cue sends (**Cues**). The signal presence indicators in the upper left corner light up when the source channel is sending data to the cue channel.

3 Enable Talkback to Cue Channel

Allows you to activate talkback for communication between the Control Room and the performers in the studio. You can set the level of the talkback signal with the slider.

4 Activate Metronome Click

Activates the metronome click. Use the **Click Level** and **Click Pan** controls to set the volume and the pan position of the metronome click.


5 Signal Level

Allows you to set the signal level.

Channels

The **Channels** section shows the speaker arrangement of the Main Mix bus.

You can use the solo functions to listen to individual channels of the Main Mix. You can also use this to test your multi channel speaker system and make sure that the correct channels are routed to the speakers.



1 Solo Left and Right Channels

Allows you to solo the left and right channels.

2 Solo Front Channels

Allows you to solo the front channels.

3 Solo Surround Channels

Allows you to solo the surround channels.

4 Listen to Solo Channels on Center Channel

Allows you to listen to all soloed speakers in the center channel. If the center channel is not available, the channels are distributed equally to the left and right.

5 Listen to Surround Channels on Front Channels

Allows you to solo the surround channels and route them to the front speakers.

6 Solo LFE Channel

Allows you to solo the LFE channel.

To open the Main Mix bus in the **MixConvert V6** plug-in, double-click the channel display.

RELATED LINKS

[MixConvert V6](#) on page 601

Monitors

The **Monitors** section allows you to select and configure the monitor sets.



Downmix Presets

The **Downmix Presets** section allows you to configure downmix presets.



1 Assign Downmix Preset

Allows you to configure a downmix preset for the monitor that is selected in the **Monitors** section.

2 Select Output Configuration


Allows you to select an output channel configuration. You can also select **Open/Close MixConvert** to open the **MixConvert V6** plug-in.

RELATED LINKS

[MixConvert V6](#) on page 601

Phones

The **Phones** section allows you to use the phones channel in the Control Room to listen to cue mixes.




- 1 Activate Phones Channel**
Allows you to activate/deactivate the phones channel.
- 2 Activate Metronome Click**
Activates the metronome click.
- 3 Source Selectors**
Allow you to select the source for the phones channel: monitor mix (**Mix**), external inputs (**Ext**), or the cue sends (**Cues**). The signal presence indicators in the upper left corner light up when the source channel is sending data to the Phones channel.
- 4 Phones Level**
Allows you to set the phones level. **Ctrl/Cmd**-click to set the level to the reference level specified in the **Preferences** dialog (**VST—Control Room** page).
- 5 Click Level and Click Panning**
Use the **Click Level** and **Click Panning** controls to set the volume and the pan position of the metronome click.
- 6 Enable Listen for Output**
Enables the listen bus function.
- 7 Listen Level**
Allows you to set the listen level.

Control Room Channel

The Control Room channel is the representation of the bus that is set up as the Main Mix bus on the **Outputs** tab in the **Audio Connections** window.



The following section contains a description of the individual controls.



1 Activate Control Room Channel


Allows you to activate/deactivate the Control Room channel.

2 Signal Level

Allows you to set the volume for the Control Room output. This does not affect the recording input level or the Main Mix level for exporting mixdowns. **Ctrl/Cmd**-click to set the level to the reference level specified in the **Preferences** dialog (**VST—Control Room** page).

3 Signal Meter

Shows the volume for the Control Room output.



1 Source Selectors

Allow you to select the source for the Control Room channel. The available sources depend on the channels that you added to the Control Room. The signal presence indicators in the upper left corner light up when the source channel is sending data to the Control Room channel.

2 Dim Signal


Activate this to lower the Control Room level by a fixed amount. This allows a quick reduction in monitor volume without disturbing the current monitor level. Clicking **DIM** again returns the monitor level to the previous setting.

3 Use Reference Level

Enable this button to set the Control Room level to the reference level specified in the **Preferences** dialog (**VST—Control Room** page). The reference level is the level that is used in calibrated mixing environments, such as film dubbing stages.

4 Activate Metronome Click

Activates the metronome click.



1 Monitor Selectors


Allow you to select another monitor source.

2 Downmix Preset Selectors

Allow you to select another downmix preset.

3 Activate Talkback

Allows you to activate talkback for communication between the Control Room and the performers in the studio. Click to activate, click and hold for momentary mode.



1 Click Level and Click Pan

Use the **Click Level** and **Click Pan** controls to set the volume and the pan position of the metronome click for the Control Room channel.

2 AFL/PFL

Allows you to determine whether the signal of a listen-enabled channel is routed to the Control Room channel after applying the fader and pan settings (AFL) or before applying the fader and pan settings (PFL).

3 Enable Listen for Output

Enables the listen bus function for the Control Room output.

4 Listen Level

Allows you to adjust the volume of listen bus signals that are routed to the Control Room output.

5 Listen Dim

Allows you to adjust the volume of the Main Mix when channels are in listen mode. This keeps listen-enabled channels in context with the Main Mix. If the **Listen DIM** level is set to the minimum value, you only hear the listen-enabled channels.

6 Talk Dim

When **Talkback** is active, this slider controls how much the output of all the channels in the Control Room is reduced, to prevent unwanted feedback.

Control Room - Inserts Tab

The **Control Room Inserts** tab contains additional settings for the channels.

The **Control Room Inserts** tab is divided into a number of sections that you open by clicking their headers.



Input Gain



Setting up the input gain can be useful in the following situations:


- To balance the level of external inputs, for example, CD players and other sources to the Main Mix level, for A/B comparisons.
- To balance the level of your monitor systems, so that switching between sets of speakers does not change the playback volume.

Input Phase



Reversing the input phase can be useful for external inputs and monitor speaker outputs.

Insert Effects



Each Control Room channel has a set of insert effect slots.

- Use the inserts on the Control Room channel for metering and spectral analysis plug-ins. All solos including the Listen bus will come through the Control Room channel and allow analysis of individual sounds. A brickwall limiter in the last insert slot of the Control Room channel can prevent accidental overloads and damage to speaker systems.
- Use the inserts for the talkback channel to control the dynamics of the talkback microphone. This helps protect performers' hearing and ensures that everyone can be heard over the talkback microphone.
- Use the monitor inserts for surround decoding or brickwall limiting to protect sensitive monitor speakers. Each monitor channel has a set of eight inserts, all of which are post Control Room fader.


Setting Up a Cue Mix

You can create a cue mix from the fader and pan levels that are used in the **MixConsole** and change them to meet the needs of the individual performers.

PROCEDURE

1. In the **MixConsole**, select the channels from which you want to copy the settings.
2. In the **Control Room**, do one of the following:
 - To apply the function only to this cue channel, right-click on a cue channel to open the context menu.
 - To apply the function to all cue channels, click anywhere but on a cue channel to open the context menu.

3. Select **From selected mixer channels** and select one of the functions.



Cue Mix Context Menu

Change Cue Sends Levels

Allows you to adjust multiple send levels at the same time.

Use Current Mix Levels

Allows you to copy the fader levels of the selected tracks to the cue sends. This sets all cue send levels for the selected tracks to the level of the main channel fader. It also changes the cue send status to pre-fader, so that changes in the main mix do not affect the cue sends.

Use Current Pan Settings

Allows you to copy pan information from the main mix to the cue sends of the selected tracks. If the cue send is mono, the pan setting is copied, but the output of the cue send is the sum of the left and right channels.

Enable Cue Sends

Allows you to activate the cue sends of the selected channels. To be able to hear the cue mix for a cue channel, the cue sends must be enabled.

Disable Cue Sends

Allows you to disable the cue sends of the selected channels.

Reset Cue Sends

Allows you to deactivate the cue sends, to change the send level of all selected channels to 0 dB, and to set the signal source to post-fader. This way, any changes to the main mix also change the cue mix. To raise the level of individual cue channels, raise the level on that channel.

Adjusting the Overall Cue Send Level

You can adjust multiple send levels at the same time for the cue send mix, keeping the blend intact while lowering the overall volume. This is sometimes necessary, because the levels in the main mix are often optimized for the loudest possible signal level without clipping.

This means that when you create a “more me” mix, you may find that there is not enough headroom available in the cue send to raise levels without introducing clipping.

PROCEDURE

1. In the **MixConsole**, select the channels that you want to modify.
2. In the **Control Room**, right-click a cue channel to open the context menu.
3. Select **From selected mixer channels > Change Cue Sends Levels**.
4. Activate **Relative Mode**.
This way, you adjust the existing levels. By deactivating **Relative Mode**, all cue sends are set to the same absolute level.

5. Adjust the level as necessary.
The level of all selected cue sends is adjusted by the set amount.
 6. Click **OK**.
-

Metering and Loudness (Cubase Pro only)


Cubase provides a master meter that works as a multichannel true peak meter, and a loudness meter that allows you to measure the loudness in compliance with the loudness recommendation R 128 of the European Broadcasting Union (EBU).

Metering

Cubase provides a master meter and a loudness meter that can be shown in the right zone of the **Project** window and the **MixConsole**, or in a separate window in the **Control Room**.

Master Meter

The master meter is a multichannel true peak meter.



- 1 **Activate Control Room View**
Shows/Hides the **Control Room** section.
- 2 **Scales**

Allows you to select a scale according to different broadcast standards (Digital, DIN, EBU, British, Nordic, K-20, K-14, or K-12). The headroom is indicated by red lines in the meter scale.

3 Alignment level standards

Allows you to select an alignment level (offset) for your scale. This is unavailable for digital and K-System scales. The broadcast meter scales DIN, EBU, Nordic, and British have a default alignment level of -18 dBFS.

4 Reset RMS and PPM Max

Resets the measurement.

5 AES17 standard

Activates the AES17 standard that adds an offset of 3 dB to the RMS value.

6 RMS/Peak meter

Shows the RMS and peak hold values as blue lines and the peak values as gray lines.

7 RMS Max

Shows the maximum RMS value.

8 Peak Max

Shows the maximum peak value.

RELATED LINKS

[Control Room \(Cubase Pro only\)](#) on page 372

Displaying Meters

PROCEDURE

1. In the **Project** window or in the **MixConsole**, click **Show/Hide Right Zone** to show the right zone with the **Control Room/Meter**.
 2. Click the **Meter** tab at the top of the **Control Room/Meter** section.
By default, the master meter is displayed.
-

Loudness Measurement

Loudness measurements that correspond to the recommendation R 128 of the European Broadcasting Union (EBU) consider loudness, loudness range, and maximum true peak level values.

Loudness Measurement

The following measurements are performed:

- **Integrated Loudness**
Average loudness that is measured over the whole track in LUFS (Loudness Unit, referenced to Full Scale).
According to the loudness recommendation R 128, audio should be normalized at -23 LUFS (± 1 LU).
- **Short-Term Loudness**
Loudness that is measured every second on an audio block of 3 seconds. This gives information about the loudest audio passages.
- **Momentary Loudness**
Maximum value of all momentary loudness values that are measured every 100 ms in an audio range of 400 ms.

Loudness Range

The loudness range measures the dynamic range over the whole title in LU (Loudness Units). It reports the ratio between the loudest and the quietest non-silent sections. The audio is divided into small blocks. Every second there is one audio block, and each block lasts 3 seconds so that the analyzed blocks overlap.

The top 10 % of the quiet blocks and the top 5 % of the loud blocks are excluded from the final analysis. The calculated loudness range is the ratio between the loudest and quietest remaining audio blocks. This measurement helps you to decide if and how much compression or expansion you can or should apply to the audio.

True Peaks

When a digital signal is converted to an analog signal, EBU R 128 recommends that you rather measure an estimation of the real peaks instead of relying on digital peaks. This avoids clipping and distortion.

Naming and Units

EBU R 128 proposes the following naming and units conventions:

- A relative measurement, such as a value that is relative to a reference level, LU as Loudness Unit (1 LU is 1 dB).
- An absolute measurement, LUFS as loudness unit referenced to full scale. 1 LUFS can be understood as 1 dB in the AES-17 scaling.

Scales


The loudness meter offers two different scales:

- The EBU +9 scale has a range from -18.0 LU to +9.0 LU (-41.0 LUFS to -14.0 LUFS).
- The EBU +18 scale has a range from -36.0 LU to +18 LU (-59.0 LUFS to -5.0 LUFS).

Loudness Meter

The **Loudness** meter allows you to analyze, measure, and monitor the loudness of your project in real time during playback or mixing.

- To open the loudness meter, select the **Loudness** tab at the bottom of the meter display in the right zone of the **Project** window or the **MixConsole**, or in the **Control Room**.



- 1 **Activate Control Room View**
Shows/Hides the **Control Room** section.
- 2 **Loudness meter**
Shows the **Integrated** value as a triangle in the left meter scale and the **Short-Term** value as a triangle in the right meter scale.
- 3 **Measure Loudness**
Activates the loudness measurement.
- 4 **Switch between LU and LUFS**
Switches the meter scale between LUFS (absolute values) and LU (relative values).
- 5 **Configure Loudness Settings**
Allows you to specify a threshold value for the **Momentary Max**, the **Short-Term**, the **Integrated**, and the **True Peak** clipping indicators. If values above the set thresholds are detected, the corresponding indicators turn red.
You can switch the loudness meter between the EBU +9 scale and the EBU +18 scale.
To reset all values on playback start, activate the **Reset on Start** option.
- 6 **Reset Loudness**
Resets all loudness values.
- 7 **Momentary Max**
Shows the maximum loudness measured over a duration of 400 ms.
- 8 **Short-Term**
Shows the loudness measured over a duration of 3 s.
- 9 **Integrated**

Shows the average loudness measured from start to stop. The period of measurement is shown in the **Time** display. The recommended value for the integrated loudness is -23 LUFS. This absolute value is the reference point for the relative LU scale where -23 LUFS equals 0 LU.

10 Range

Shows the dynamic range of the audio measured from start to stop. This value helps you to decide how much dynamic compression you can apply. The range that is recommended for highly dynamic audio such as film music is 20 LU.

11 True Peak

Shows the true peak level of the audio. The maximum permitted true peak level in production is -1 dB.

12 Time

Shows the duration of the integrated loudness measurement.

RELATED LINKS

[Displaying Meters](#) on page 386


[Control Room \(Cubase Pro only\)](#) on page 372

[Metering and Loudness \(Cubase Pro only\)](#) on page 385

[Loudness Settings](#) on page 389

Loudness Settings

- To open the **Loudness Settings** dialog, click **Configure Loudness Settings** on the **Loudness** tab.



The following parameters are available:

- 1 Select Preset**
Allows you to create, load, and remove loudness presets.
- 2 Momentary Max**
Allows you to specify a reference value and a tolerance value for the maximum momentary loudness. If higher values are detected, the clipping indicator in the loudness meter turns red.
- 3 Short-Term**
Allows you to specify a reference value and a tolerance value for the short-term loudness. If higher values are detected, the clipping indicator in the loudness meter turns red.
- 4 Integrated**

Allows you to specify a reference value and a tolerance value for the integrated loudness. If higher values are detected, the clipping indicator in the loudness meter turns red.

5 True Peak

Allows you to specify a reference value and a tolerance value for the true peak level. If higher values are detected, the clipping indicator in the loudness meter turns red.

6 Switch between LU and LUFS

Allows you to switch the meter scale between LUFS (absolute values) and LU (relative values).

7 Switch between EBU +9 Scale and EBU +18 Scale

Allows you to switch the meter between the EBU +9 scale and the EBU +18 scale.

8 Reset on Start

Activate this option to reset all values on playback start.

RELATED LINKS

[Loudness Meter](#) on page 387

Audio Effects

Cubase comes with a number included of effect plug-ins that you can use to process audio, group, instrument, and ReWire channels.

This chapter contains general details about how to assign, use, and organize effect plug-ins. The effects and their parameters are described in the separate document **Plug-in Reference**.

Insert Effects and Send Effects

You can apply effects to audio channels by using insert effects or send effects.

NOTE

To apply audio effects to individual audio events, use **Direct Offline Processing** (Cubase Pro only).

Insert Effects

Insert effects are inserted in the signal chain of an audio channel. This way, the whole channel signal passes through the effect.

You can add up to 16 different insert effects per channel.


Use insert effects for effects such as distortion, filters, or other effects that change the tonal or dynamic characteristics of the sound.

To add and edit insert effects, you can use the following inserts sections:


- The **Inserts** rack in the **MixConsole**.



- The **Inserts** section in the **Channel Settings** window.



- The **Inserts** section in the **Inspector**.



Send Effects

Send effects can be added to FX channel tracks, and the audio data to be processed can be routed to the effect. This way, the send effects remain outside the audio channel's signal path.

Each audio channel has 8 sends, each of which can be freely routed to an effect (or to a chain of effects).

Use send effects in the following cases:


- To control the balance between the dry and wet sound individually for each channel.
- To use the same effect for several different audio channels.

To edit send effects, you can use the following sends sections:

- The **Sends** rack in the **MixConsole**.



- The **Sends** section in the **Channel Settings** window.



- The **Sends** section in the **Inspector**.



RELATED LINKS

[Direct Offline Processing](#) on page 416

VST Standard

Audio effects can be integrated in Cubase thanks to the VST standard. At the moment, the VST 3 and VST 2 standards are supported.

The VST 3 plug-in standard offers improvements like smart plug-in processing and side-chain inputs. Yet, it retains full backwards compatibility to VST 2.

Smart Plug-In Processing

Smart plug-in processing is a technology that allows to disengage the processing for plug-ins when no signal is present. This reduces the CPU load on silent passages and allows you to load more effects.

To activate smart plug-in processing, activate **Suspend VST 3 plug-in processing when no audio signals are received** in the **Preferences** dialog (**VST—Plug-ins** page).

NOTE

Check the processor for the passage with the largest number of events playing simultaneously to make sure that your system offers the required performance at every time position.

Side-Chain Inputs

Several VST 3 effects feature side-chain inputs. These allow you to control the operation of the effect via external signals that are routed to the side-chain input.

The effect processing is still applied to the main audio signal.

RELATED LINKS

[Side-Chain Input](#) on page 405

Plug-In Delay Compensation

Some audio effects, especially dynamics processors that feature a look-ahead functionality, may take a brief time to process the audio fed into it. As a result, the output audio will be slightly delayed. To compensate for this, Cubase provides plug-in delay compensation.

Plug-in delay compensation is featured throughout the entire audio path maintaining the sync and timing of all audio channels.

VST 3 dynamics plug-ins with look-ahead functionality feature a **Live** button that allows you to disengage the look-ahead. This minimizes latency during real-time recording. For details, see the separate document **Plug-in Reference**.

To avoid latency during realtime recording or realtime playback of VST instruments, you can also use **Constrain Delay Compensation**.

RELATED LINKS

[Constrain Delay Compensation](#) on page 636

Tempo Sync

Plug-ins can receive timing and tempo information from Cubase. This is useful to synchronize plug-in parameters, such as modulation rates or delay times, to the project tempo.

Timing and tempo information is provided to plug-ins of the standard VST 2.0 or later.

To set up tempo sync you must specify a base note value. Straight, triplet or dotted note values (1/1 to 1/32) are supported.

For details about the included effects, see the separate document **Plug-in Reference**.

Insert Effects

Insert effects can be inserted in the signal chain of an audio channel. This way, the whole channel signal passes through the effect.

You can add up to 16 different insert effects independently for each audio-related channel (audio track, group channel track, FX channel track, instrument channel, or ReWire channel) or output bus.

The signal passes through the insert effects corresponding to their slot position from top to bottom.

You can define post-fader insert slots for any channel. Post-fader insert slots are always post-EQ and post-fader.

NOTE

To show all post-fader slots in the **MixConsole**, open the **Rack Settings** and activate **Fixed Number of Slots**.

Use post-fader slots for insert effects where you want the level to remain unchanged after the effect. Dithering and maximizers are typically used as post-fader insert effects for output busses, for example.

NOTE

If you want to use an effect with identical settings on several channels, set up a group channel and apply your effect as a single insert for this group.

RELATED LINKS

[Dither Effects](#) on page 407

[Moving Inserts to Post-Fader or Pre-Fader Position](#) on page 348

[Adding Insert Effects to Group Channels](#) on page 395


[Rack Settings](#) on page 329

Adding Insert Effects

If you add insert effects to audio channels, the audio is routed through the insert effects.

PROCEDURE

1. Select the audio track.
2. In the track list, click **Edit Channel Settings** .
The **Channel Settings** window for the audio channel opens.
3. In the **Inserts** section, click the first insert slot on the **Inserts** tab, and select an effect from the selector.



RESULT

The selected insert effect is loaded and activated, and the audio is routed through it. The effect control panel is opened.

RELATED LINKS

[Effect Control Panel](#) on page 408

Adding Insert Effects to Busses

If you add insert effects to input busses, the effects become a permanent part of the recorded audio file. If you add insert effects to output busses, all audio routed to that bus is affected. Insert effects that are added to output busses are sometimes referred to as master effects.

PROCEDURE

1. Select **Studio > MixConsole** to open the MixConsole.
2. In the fader section, perform one of the following actions:

- Locate the input channel and click **Edit Channel Settings** to edit the input bus.
- Locate the output channel and click **Edit Channel Settings** to edit the output bus.

The **Channel Settings** window for the selected channel opens.

3. In the **Inserts** section, click the first insert slot on the **Inserts** tab, and select an effect from the selector.
-

RESULT

The selected insert effect is added to the bus and activated. The effect control panel is opened.

Adding Insert Effects to Group Channels

If you add insert effects to group channels, you can process several audio tracks through the same effect.

PROCEDURE

1. Select **Project > Add Track > Group Channel** to add a group channel track.
 2. In the **Inspector** for the group track, open the **Output Routing** pop-up menu, and select the desired output bus.
 3. In the **Inspector** for the group track, open the **Inserts** section.
 4. Click the first effect slot and select an effect from the selector.
 5. In the **Inspector** for the audio tracks, open the **Output Routing** pop-up menus and select the group.
-

RESULT

The signal from the audio track is routed through the group channel and passes through the insert effect.

Copying Insert Effects

You can add insert effects to audio channels by copying them from other audio channels or from other slots of the same audio channel.

PREREQUISITE

You have added at least one insert effect to an audio channel.

PROCEDURE

1. Select **Studio > MixConsole**.
 2. In the **Inserts** rack, locate the insert effect that you want to copy.
 3. Hold down **Alt**, drag the insert effect, and drop it on an insert slot.
-

RESULT

The insert effect is copied. If the destination slot already contains an insert effect, it is replaced.

Rearranging Insert Effects

You can change the position of an insert effect in the signal chain of the audio channel by moving it to a different slot of the same channel. You can also move an insert effect to another audio channel.

PREREQUISITE

You have added at least one insert effect to an audio channel.

PROCEDURE

1. Select **Studio > MixConsole**.
 2. In the **Inserts** rack, locate the insert effect that you want to rearrange.
 3. Drag the insert effect and drop it on an insert slot.
-

RESULT

The insert effect is removed from the source slot and placed on the destination slot. If the destination slot already contains an insert effect, this effect is moved to the next insert slot.

Deactivating Insert Effects


If you want to listen to a track without having it processed by an effect, but do not want to remove this effect completely from the insert slot, you can deactivate it.

PREREQUISITE

You have added an insert effect to an audio channel.


PROCEDURE

1. In the track list, select the audio track with the insert effect that you want to deactivate.
2. In the **Inspector**, open the **Inserts** section, and **Alt-click Bypass Insert**.



RESULT

The effect is deactivated and all processing is terminated, but the effect is still loaded.



Bypassing Insert Effects


If you want to listen to the track without having it processed by a particular effect, but do not want to remove this effect completely from the insert slot, you can bypass it. A bypassed effect is still processing in the background. This allows for crackle-free comparison of the original and the processed signal.

PREREQUISITE

You have added an insert effect to an audio channel.


PROCEDURE

1. In the track list, select the audio track with the insert effect that you want to bypass.
2. In the **Inspector**, open the **Inserts** section, and click **Bypass Insert**.



RESULT

The effect is bypassed, but still processing in the background.



Removing Insert Effects

PROCEDURE

1. Select the audio track that contains the insert effect that you want to remove.
 2. In the **Inspector**, click **Select Insert**.
 3. In the effect selector, select **No Effect**.
-

RESULT

The insert effect is removed from the audio channel.

Freezing Insert Effects

Freezing an audio track and its insert effects allows you to reduce processor power. However, frozen tracks are locked for editing. You cannot edit, remove or add insert effects for the frozen track.

PREREQUISITE

You have made all settings for the track and you are sure that you do not need to edit it anymore.

PROCEDURE

1. In the **Inspector** for the audio track that you want to freeze, click **Freeze Audio Channel**.



2. In the **Freeze Channel Options** dialog, specify a **Tail Size** in seconds.
This adds time at the end of the rendered file. This way, reverb and delay tails can fully fade out.
-

RESULT

The output of the track including all pre-fader insert effects is rendered to an audio file.

NOTE

Post-fader inserts cannot be frozen.

The frozen audio track is saved in the **Freeze** folder that can be found in the following location:

- Windows: within the **Project** folder
- macOS: User/Documents

In the **MixConsole**, the frozen audio channel is indicated by a snow flake symbol above the channel name. You can still adjust the level and panning, make EQ settings and adjust the effect sends.

AFTER COMPLETING THIS TASK

To unfreeze a frozen track, click **Freeze** again.

Insert Effects in Multi-Channel Configurations (Cubase Pro only)

You can insert VST 2 and VST 3 effects on tracks with a multi-channel configuration. However, not all effect plug-ins support multi-channel processing.

Mono or stereo effects can only process 1 or 2 channels, whereas surround-capable plug-ins are applied to all speaker channels, or to a subset of these.

- To set up to what speaker channels the insert effect is applied, use the **Routing Editor**.

RELATED LINKS


[Routing Editor](#) on page 399

Routing Insert Effects through Specific Audio Channels

If you insert a stereo insert effect on a multi channel track, the first speaker channels of the track are routed through the available effect channels. The other channels remain unprocessed. However, you can route the effect through different speaker channels.


PROCEDURE

1. In the track list, click **Edit Channel Settings** to open the **Channel Settings** window for the track on which the effect is inserted.
2. On the **Inserts** section, click **Routing** to open the **Routing** tab.
3. Double-click the signal diagram for the insert effect to open the **Routing Editor**.



The first speaker channels of the track are routed through the available effect channels.

4. Optional: Activate **Link** to link the input and output channel assignment.
5. Click the arrow buttons to route different speaker channels through the effect.



RESULT

The effect is routed through different channels of the audio.

NOTE

To route a stereo plug-in through all 6 channels of a 5.1 track, add 3 instances of it and use different speaker channels for each instance.


RELATED LINKS

[Routing Editor](#) on page 399

Routing Editor

The **Routing Editor** allows you to set up, to what speaker channels the effect is applied to.

The **Routing Editor** shows the channels in the current configuration, with signals passing from top to bottom.



- 1 Outputs**
The lower squares represent the outputs from the effect plug-in.
- 2 Effect plug-in**
The field in the middle represents the effect plug-in.
- 3 Inputs**
The upper squares represent the inputs to the effect plug-in.
- 4 Connections**
The lines represent the connections.
- 5 Input channel assignment**
These buttons allow you to assign the input channels.
- 6 Link**
Activate this to link the input and output channel assignment.
- 7 Output channel assignment**
These buttons allow you to assign the output channels.
- 8 Reset**
This button allows you to reset the original channel setup.

Routing Connections

In the Routing Editor, you can set up the routing connections.

NOTE

You can only make settings in the **Routing Editor** if you route multi channel audio through an effect that supports fewer channels.

The following connections are possible:

Routing Connection



The audio on the speaker channel is routed through the effect channel and processed by the effect.

Bypass Connection




The audio on the speaker channel passes the effect without being processed.

Broken Connection



The audio on the speaker channel is not sent to the output.

Cross Connection



The audio on the specific channels is processed by the effect and output on other channels.

In this example, the audio on the Ls-Rs channels is output on the L-R channels. Since the L-R channels are bypassed, the final L-R output contains both the original L-R signals and the processed Ls-Rs signals.

Send Effects

Send effects are outside the signal path of an audio channel. The audio data that is to be processed must be sent to the effect.

- You can select an FX channel track as routing destination for a send.
- You can route different sends to different FX channels.
- You can control the amount of signals sent to the FX channel by adjusting the effect send level.

To do this, you must create FX channel tracks.

RELATED LINKS

[FX Channel Tracks](#) on page 400

FX Channel Tracks

You can use FX channel tracks as routing destinations for audio sends. The audio is sent to the FX channel and through any insert effects set up for it.

- You can add several insert effects to an FX channel.
The signal passes through the effects in series, from the top downward.
- You can rename FX channel tracks as any other tracks.
- You can add automation tracks to FX channel tracks.
This allows for automating various effect parameters.
- You can route the effect return to any output bus.
- You can adjust the FX channel in the **MixConsole**.
This includes adjusting the effect return level, the balance, and the EQ.

When you add an FX channel track, you can select if FX channel tracks are created inside or outside a dedicated folder. If you select **Create Inside Folder**, FX channel tracks are shown in a dedicated folder.



This allows for better overview and editing of the FX channel tracks.

NOTE

By folding FX channel folders, you can save screen space.

RELATED LINKS

[Adding FX Channel Tracks](#) on page 401

Adding FX Channel Tracks

PROCEDURE

1. Select **Project > Add Track > FX Channel**.
 2. Open the **Configuration** pop-up menu to select a channel configuration for the FX channel track.
 3. Open the **Effect** pop-up menu and select an effect from the selector.
 4. Open the **FX Channels Folder** pop-up menu and select if you want to create fx channel tracks inside or outside a dedicated folder.
 5. Click **Add Track**.
-

RESULT

An FX channel track is added to the track list and the selected effect is loaded into the first insert effect slot of the FX channel.

Adding Insert Effects to FX Channel Tracks

You can add insert effects to FX channel tracks.

PREREQUISITE

You have added an FX channel track and set up the correct output bus in the **Output Routing** pop-up menu.

PROCEDURE

1. In the track list for the FX channel track, click **Edit Channel Settings**.
The **Channel Settings** window for the FX channel track opens.
 2. In the **Inserts** section, click an insert slot on the **Inserts** tab, and select an effect from the selector.
-

RESULT


The selected effect is added as an insert effect to the FX channel track.

Routing Audio Channels to FX Channels


If you route an audio channel send to an FX channel, the audio is routed through the insert effects that you have set up for the FX channel.

PROCEDURE

1. Select the audio track.
2. In the track list, click **Edit Channel Settings** to open the **Channel Settings** window.
3. In the **Sends** section on the **Destinations** tab, click **Select Destination** for an effect slot, and select the FX channel track from the selector.



4. On the send slot, click **Activate/Deactivate Send**.



RESULT

The audio is routed through the FX channel.

AFTER COMPLETING THIS TASK

In the **Channel Settings** window for the audio channel, you can hold down **Alt** and double-click to show the send destination. If you have routed the send to an FX channel, the effect control panel is opened.


RELATED LINKS

[Adding FX Channel Tracks](#) on page 401


Pre/Post Fader Sends

You can send the signal from the audio channel to the FX channel before or after the audio channel volume fader.


- **Pre-fader sends**
The audio channel signal is sent to the FX channel before the audio channel volume fader.
- **Post-fader sends**
The audio channel signal is sent to the FX channel after the audio channel volume fader.
- To move a send to pre-fader position, open the **Channel Settings** window for the audio channel, right-click a send and select **Move to Pre-Fader**.




The **Pre-/Post-Fader** button indicates that the send is in pre-fader position.



- To move a send to post-fader position, open the **Channel Settings** window for the audio channel, right-click a send and select **Move to Post-Fader**.



The **Pre-/Post-Fader** button indicates that the send is in post-fader position.



NOTE

If you activate **Mute Pre-Send when Mute** in the **Preferences** dialog (**VST** page), sends in pre-fader mode are muted if you mute their channels.

Setting Pan for the Sends (Cubase Pro only)


PROCEDURE

1. Select the audio track.
2. In the track list, click **Edit Channel Settings** to open the **Channel Settings** window.
3. On the **Sends** tab, click **Panning**.
For each send, a pan fader is shown.

NOTE

Depending on the routing, different pan controls are available for the sends.

4. Optional: Open the **Functions Menu** and activate **Link Panners**.




The send panners will then follow the pan for the channel, making the stereo imaging as clear and true as possible.

NOTE

In the **Preferences** dialog (**VST** page), you can set this as a default behavior for all channels.

5. Click and drag the pan control for the send.



NOTE

You can reset the pan control to the center position by **Ctrl/Cmd**-clicking on the pan control.

RELATED LINKS


[Surround Sound \(Cubase Pro only\)](#) on page 584

Setting Level for the Sends

PROCEDURE

1. In the track list, select the FX channel track that contains the effect for which you want to set the level.
2. Open the **Inserts** section of the Inspector and click the effect slot to open the effect control panel.
3. In the effect control panel, set the **Mix** control to 100.
This allows for full control of the effect level when you use the effect sends to control the signal balance later.

4. In the track list, select the audio track that is routed through the effect for which you want to set the level.
5. Click **Edit Channel Settings** to open the **Channel Settings** window for the audio track.
6. In the **Sends** section on the **Destinations** tab, locate the effect slot and drag to the left or right to set the send level.



This determines how much of the signal from the audio channel is routed to the FX channel.

RESULT

The effect level is adjusted according to your settings.

NOTE

To determine how much of the signal from the FX channel is sent to the output bus, open the **Channel Settings** window for the FX channel track and adjust the effect return level.

Side-Chain Input

Many VST 3 effects feature a side-chain input. Side-chaining allows you to use the output of one track to control the action of an effect on another track.

Effects from the following categories feature side-chain:

- Modulation
- Delay
- Filter

By activating the side-chain input you can:

- Use the side-chain signal as a modulation source.
- Apply ducking to the instrument, that is, reduce the volume of the instrument track when a signal is present on the audio track.
- Compress the signals on one audio track when a second audio track starts.
This is typically used to add compression on a bass sound when the drums are hit.

NOTE

For detailed descriptions of the plug-ins that feature side-chaining, see the separate document **Plug-in Reference**.

NOTE

- Certain combinations of tracks and side-chain inputs may lead to feedback loops and added latency. If this is the case, the side-chain options are not available.
 - Side-chain connections are only kept when you move an effect within a channel. When you drag and drop an effect between channels, or when you copy an effect into another effect slot, the side-chain connections are lost.
-

Side-Chain and Modulation


Side-chain signals bypass the built-in LFO modulation and apply modulation according to the envelope of the side-chain signal. Since each channel is analyzed and modulated separately, this allows for creating astonishing spatial modulation effects.

Triggering a Delay Effect with Side-Chain Signals

You can use side-chain signals to create a ducking delay effect. This is useful if you want to apply a delay effect that is audible only when no signal is present on a track.

PROCEDURE

1. Select the audio track that contains the audio you want to delay.
2. Select **Project > Duplicate Tracks**.
The events on the duplicated track are only used to reduce the volume of the effect that is added to the original track.
3. Select the original track.
4. In the **Inspector**, open the **Inserts** section and select **Delay > PingPongDelay**, for example.
The control panel for the effect opens.
5. Make the desired effect settings for the effect, and activate **Activate Side-Chain**.



6. In the track list, select the duplicated track.
7. In the Inspector, click **Output Routing** and select the side-chain node for the **PingPongDelay** effect that you set up.



RESULT

The signals from the duplicated track are routed to the effect. Every time the audio signals on the track set in, the delay effect is deactivated.

NOTE

To ensure that audio signals of low or middle volume also silence the delay effect, you can adjust the volume of the duplicated track.

Triggering a Compressor with Side-Chain Signals

Compression, expansion, or gating can be triggered by side-chain signals exceeding a specified threshold. This allows you to lower the volume of one audio signal every time another audio signal sets in.

PREREQUISITE

You have set up a project with a bass guitar and a bass drum track, for example, and you want to lower the bass guitar volume each time the bass drum hits.

PROCEDURE

1. Select the bass guitar track.
2. In the **Inspector**, open the **Inserts** section.
3. Click the first effect slot, and from the selector, select **Dynamics > Compressor**. The effect is loaded and the effect control panel opens.
4. Make the desired effect settings for the effect and activate **Activate Side-Chain**.
5. Select the bass drum track.
6. In the **Inspector**, open the **Sends** section.
7. Click the first effect slot and select the side-chain node for the **Compressor** effect that you set up for the bass guitar track.
8. Click **Activate Send** and adjust the **Send** level.

RESULT

The bass drum signal triggers the **Compressor** on the bass guitar track. When you now play back the project, the bass guitar will be compressed whenever the signals on the bass drum track exceed the set threshold.

Dither Effects

Dither effects allow you to control the noise that is produced by quantization errors that can occur when you mix down to a lower bit depth.

Dithering adds a special kind of noise at an extremely low level to minimize the effect of quantization errors. This is hardly noticeable and preferable to the distortion that otherwise occurs.

Applying Dither Effects

PROCEDURE

1. Select **Studio > MixConsole**.
2. Open the **Rack Settings** and activate **Fixed Number of Slots**.
3. Click **Edit Channel Settings** for the output channel.
4. In the **Inserts** section, click a post-fader effect slot, and select **Mastering > UV22HR**.
5. On the plug-in panel, select a bit depth for the mixdown file you want to create.

RELATED LINKS

[Export Audio Mixdown](#) on page 920
[Rack Settings](#) on page 329

External Effects (Cubase Pro only)

You can integrate external effect devices into the sequencer signal flow by setting up external FX busses.

An external FX bus is a combination of outputs (sends) and inputs (returns) on your audio hardware, along with a few additional settings.

All external FX busses you have created are available on the effect pop-up menus. If you select an external effect as an insert effect for an audio track, the audio is sent to the corresponding audio output, processed in your hardware effect and returned via the specified audio input.

RELATED LINKS

[Audio Connections](#) on page 21

[External Instruments and Effects \(Cubase Pro only\)](#) on page 30

Effect Control Panel

The effect control panel allows you to set up the parameters of the selected effect. The contents, design, and layout of the control panel depend on the selected effect.

- To open the control panel for a plug-in, double-click the effect slot.

The following controls are available for all effects:



- 1 Activate Effect**
Activates/Deactivates the effect.
- 2 Bypass Effect**
Allows you to bypass the effect.
- 3 Read/Write Automation**
Allows you to read/write automation for the effect parameter settings.
- 4 Switch between A/B Settings**
Switches to setting B when setting A is active, and to setting A when setting B is active.
- 5 Copy A to B**
Copies the effect parameters of effect setting A to effect setting B.
- 6 Activate Side-Chain**
Activates the side-chain functionality.
- 7 Preset browser**
Opens the preset browser where you can select another preset.
- 8 Preset Management**
Opens a pop-up menu that allows you to save, rename, or remove a preset.
- 9 Functions menu**

Opens a menu with specific functions and settings.

NOTE

For detailed information about the included effects and their parameters, see the separate document **Plug-in Reference**.

Fine-Tuning Effect Settings

You can take your effect parameter settings as a starting point for further fine-tuning and then compare the new settings with the original settings.

PREREQUISITE

You have adjusted the parameters for an effect.

PROCEDURE

1. On the control panel for the effect, click **Switch between A/B Settings**.
This copies the initial parameter setting A to setting B.
 2. Fine-tune the effect parameters.
These parameter settings are now saved as setting B.
-

RESULT

You can now switch between both settings by clicking **Switch between A/B Settings**. You can compare them, make further adjustments or just go back to setting A. Settings A and B are saved with the project.

AFTER COMPLETING THIS TASK

You can copy the settings between A and B by clicking **Copy A to B**. You can take these settings as a starting point for further fine-tuning.

Effect Presets

Effects presets store the parameter settings of an effect. The included effects come with a number of presets that you can load, adjust, and save.

The following effect preset types are available:

- VST presets for a plug-in.
These are plug-in parameter settings for a specific effect.
- Inserts presets that contain insert effect combinations.
These can contain the whole insert effects rack with settings for each effect.

Effect presets are saved in the following location:

- Windows: \Users\\My Documents\VST 3 Presets\\- macOS: /Users/<user name>/Library/Audio/Presets/<company>/<plug-in name>

RELATED LINKS

[Loading Effect Presets](#) on page 410

[Loading Insert Presets](#) on page 413

Preset Browser

The preset browser allows you to select a VST preset for the loaded effect.

- To open the preset browser, click the preset browser field in the effect control panel.

NOTE

The preset browser contains the **Results** and the **Previewer** sections. To open the **Filters** and the **Location Tree** sections, click **Set up Window Layout** and activate the corresponding options.



- 1 Location Tree**
Shows the folder that is searched for preset files.
- 2 Filters**
Shows the available preset attributes for the selected effect.
- 3 Results**
Lists the available presets for the selected effect.
- 4 Previewer**
Allows you to preview the files shown in the results list.

Loading Effect Presets


Most VST effect plug-ins come with a number of useful presets that you can instantly select.

PREREQUISITE

You have loaded an effect, either as a channel insert or into an FX channel, and the effect control panel is open.

PROCEDURE

1. Perform one of the following actions:
 - Click the preset browser field at the top of the control panel.
 - In the **Inspector** or the **Channel Settings** window, open the **Inserts** section and click **Select Preset** for the loaded effect.



2. In the **Results** section, select a preset from the list.
3. Optional: Activate playback to audition the selected preset and step through the presets until you find the right sound.

NOTE

You can set up cycle playback of a section to make comparisons between different preset settings easier.

4. Double-click to load the preset that you want to apply.

RESULT

The preset is loaded.

AFTER COMPLETING THIS TASK

You can return to the preset that was selected when you opened the preset browser by clicking **Revert to Last Setting**.

Saving Effect Presets

You can save your effect settings as presets for further use.

PROCEDURE

1. Open the **Preset Management** pop-up menu.



2. Select **Save Preset**
The **Save <plug-in name> Preset** pane opens.
3. In the **New Preset** section, enter a name for the new preset.
4. Optional: Click **New Folder** to add a subfolder inside the effect preset folder.

- Optional: Click **Show Attribute Inspector** in the bottom left corner of the pane and define attributes for the preset.
 - Click **OK**.
-

RESULT

The effect preset is saved.

RELATED LINKS

[Attribute Inspector](#) on page 570

Saving Default Effect Presets

You can save your effect parameter settings as default effect preset. This allows you to load your parameter settings automatically, every time you select the effect.

PROCEDURE

- Open the **Preset Management** pop-up menu.



- Select **Save as Default Preset**.
You are asked if you want to save the current settings as default preset.
 - Click **Yes**.
-

RESULT

The effect settings are saved as default preset. Every time you load the effect, the default preset is loaded automatically.

Copying and Pasting Presets Between Effects

You can copy and paste effect presets between different instances of the same plug-in.

PROCEDURE

- Open the control panel for the effect that you want to copy.
 - Right-click the control panel and select **Copy <plug-in name> Setting** from the context menu.
 - Open another instance of the same effect.
 - Right-click the control panel and select **Paste <plug-in name> Setting** from the context menu.
-

Saving Insert Presets

You can save the inserts of the inserts effect rack for a channel, together with all parameter settings as an inserts preset. Insert presets can be applied to audio, instrument, FX channel, or group tracks.

PREREQUISITE

You have loaded a combination of insert effects and the effect parameters are set up for each effect.

PROCEDURE

1. Select the track.
2. In the **Inspector**, open the **Inserts** section.
3. On the **Inserts** tab, click **Preset Management** and select **Save FX Chain Preset**.



4. In the **Save FX Chain Preset** pane, enter a name for the new preset in the **New Preset** section.
 5. Click **OK**.
-

RESULT

The insert effects and their effect parameters are saved as insert preset.

Loading Insert Presets


You can load insert presets to audio, group, instrument, and FX channels.

PREREQUISITE

You have saved a combination of insert effects as insert presets.

PROCEDURE

1. Select the track to which you want to apply the new preset.
2. In the **Inspector**, open the **Inserts** section.
3. On the **Inserts** tab, click **Preset Management** and select **Load FX Chain Preset**.
4. Select an insert preset.



5. Double-click to apply the preset and close the pane.
-

RESULT

The effects of the insert effect preset are loaded and any plug-ins that were previously loaded for the track are removed.

Loading Insert Effect Settings from Track Presets

You can extract the effects that are used in a track preset and load them into your inserts rack.

PROCEDURE

1. Select the track to which you want to apply the new preset.
2. In the **Inspector**, open the **Inserts** section.
3. On the **Inserts** tab, click **Preset Management** and select **From Track Preset**.
4. In the track preset pane, select the preset that contains the insert effects you want to load.
5. Double-click to load the effects and close the pane.

RESULT

The effects used in the track preset are loaded.


RELATED LINKS

[Track Presets](#) on page 179

System Component Information Window

The **System Component Information** window lists all the available MIDI plug-ins, audio-codec plug-ins, program plug-ins, project import-export plug-ins, and the virtual file system plug-ins.

- To open the **System Component Information** window, select **Studio > More Options > System Component Information**.



The screenshot shows the 'System Component Information' window with the 'MIDI Plug-ins' tab selected. The window has a title bar with tabs for 'MIDI Plug-ins', 'Audio-Codec Plug-ins', 'Program Plug-ins', 'Project Import-Export Plug-ins', and 'Virtual File System Plug-ins'. Below the tabs is an 'Update' button. The main area contains a table with the following columns: 'Instances', 'Name', 'Vendor', and 'File'. The table lists several Steinberg Media Technologies plug-ins, all with 'Cubase8.5.exe' as the file path.

A	Instances	Name	Vendor	File
✓	-	Arpache 5	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Arpache SX	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Auto LFO	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Beat Designer	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Chorder	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Compressor	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Context Gate	Steinberg Media Technologies	Cubase8.5.exe
✓	-	Density	Steinberg Media Technologies	Cubase8.5.exe

Update (only available for MIDI Plug-ins)

Re-scans the designated plug-in folders for updated system component information.

The following columns are available:

Active

Allows you to activate or deactivate a plug-in.

Instances

The number of plug-in instances that are used in Cubase.

Name

The name of the plug-in.

Vendor

The manufacturer of the plug-in.

File

The name of the plug-in, including its file name extension.

Path

The path in which the plug-in file is located.

Category

The category of each plug-in.

Version

The version of the plug-in.

SDK

The version of the VST protocol with which the plug-in is compatible.

Managing System Components in the System Component Information Window

- To make a plug-in available for selection, activate the checkbox in the left column. Only the activated plug-ins appear in the effect selectors.
- To see where a plug-in is used, click in the Instances column.

NOTE

A plug-in may be in use even if it is not activated in the left column. The left column only determines whether or not the plug-in is visible on the effect selectors.

Exporting System Component Information Files

You can save system component information as an XML file, for example, for archiving purposes or troubleshooting.

- The system component information file contains information on the installed/available plug-ins, their version, vendor, etc.
- The XML file can then be opened in any editor application supporting the XML format.

NOTE

The export function is not available for program plug-ins.

PROCEDURE

1. In the **System Component Information** window, right-click in the middle of the window and select **Export**.
 2. In the dialog, specify a name and location for the system component information export file.
 3. Click **Save** to export the file.
-

Direct Offline Processing

Direct Offline Processing allows you to instantly add plug-in effects (Cubase Pro only) and audio processes to the selected audio events, clips, or ranges, without destructing the original audio.

Applying offline effects is common practice in dialogue editing and sound design. Offline processing has several advantages over applying realtime mixer effects:

- The workflow is clip-based. This allows you to apply different effects to events on the same track.
- The **MixConsole** can be kept clean from insert effects and parameter changes. This facilitates later mixing by another person, on a different system.
- Less CPU load is used.

Direct Offline Processing allows you to undo any changes regarding plug-in effects and audio processes, at any point and in any order. You can always revert to the original version. This is possible because processing does not affect the actual audio files.

If you process an event, a clip, or a selection range, the following happens:

- A new audio file is created in the **Edits** folder within your project folder. This file contains the processed audio, and the processed section of the audio clip refers to it.
- The original file remains unaffected. The unprocessed sections still refer to it.

All applied offline processing is saved with the project and can still be modified after reopening the project. **Direct Offline Processing** operations on the selected audio are persistent in track archives (Cubase Pro only) and project backups.

Processing is always applied to the selection. This can be one or multiple events in the **Project** window or in the **Audio Part Editor**, an audio clip in the **Pool**, or a selection range on one or multiple events in the **Project** window or in the **Sample Editor**. If a selection is shorter than the audio file, only the selected range is processed.

If you select an event that is a shared copy, and therefore refers to a clip that is used by other events in the project, you can decide how to proceed:

- Select **Continue** to process all shared copies.
- Select **New Version** to process the selected event only.

NOTE

This only works if **Open Options Dialog** is selected for the **On Processing Shared Clips** setting in the **Preferences** dialog (**Editing—Audio** page).

RELATED LINKS

[Modifying Processes](#) on page 422

[Applying Offline Processing Permanently](#) on page 424

[Editing - Audio](#) on page 1015

[Direct Offline Processing Workflow](#) on page 417
[Direct Offline Processing Window](#) on page 417

Direct Offline Processing Workflow

You can perform offline processing operations in the **Direct Offline Processing** window. The window always shows the processing of the selected audio.

For the **Direct Offline Processing** window, the following applies:

- Only one instance of the window can be open.
- The window size is determined by the displayed plug-in (Cubase Pro only) or process.
- The window is non-modal and remains open, even if you edit in the **Project** window.
- The window is always on top of your application. You can change this by activating/deactivating the **Always on Top** option in the context menu.
- Cubase Pro only: If **Auto Apply** is activated, you can use offline processing even if the **Direct Offline Processing** window is in the background or minimized.

When you add or modify offline processing, the following applies:

- All changes are instantly applied to the audio.

NOTE

Cubase Pro only: You can change this by deactivating **Auto Apply** in the **Direct Offline Processing** window. This can be necessary if you work with long events or if you use plug-ins that have a learning function.

- If you modify parameters or remove processing, these changes are instantly applied to the audio.
- You get a visual feedback while a process is running.

NOTE

You can add, modify, or delete plug-in effects (Cubase Pro only) or audio processes at any time, even if a process is running. A new rendering process is instantly started.

- You can undo and redo all **Direct Offline Processing** operations by using **Ctrl/Cmd-Z** or **Shift-Ctrl/Cmd-Z**.
- If you load a project with offline processing of plug-in effects (Cubase Pro only) or audio processes that are not available on your computer, these processes are shown as **Not available** in the **Direct Offline Processing** window.

RELATED LINKS

[Direct Offline Processing Window](#) on page 417
[Deactivating Auto Apply \(Cubase Pro only\)](#) on page 421
[Applying Direct Offline Processing Using Key Commands](#) on page 433
[Applying Offline Processing Permanently](#) on page 424

Direct Offline Processing Window

The **Direct Offline Processing** window allows you to add, modify, or delete audio processing instantly for one or multiple events, clips, or selection ranges in one window. Furthermore, you can undo any audio processing, at any point and in any order.


To open the **Direct Offline Processing** window, do one of the following:

- Select **Audio > Direct Offline Processing**.

- Use a key command, by default F7.
- On the **Project** window toolbar, click **Open Direct Offline Processing Window**.
- Select **Audio > Processes**, and from the submenu, select a process.

NOTE

Processes without adjustable parameter settings, for example, **Silence**, do not open the **Direct Offline Processing** window.



In the **Direct Offline Processing** window, the following options and settings are available:

1 Process list

Lists all plug-in effects and built-in audio processes that you add to the selected event, clip, or range. You can bypass items in this list. An icon at the right of each process shows the status.

If only a range of a selected event is processed, this is indicated by a waveform icon in the **Range** column.

If more than one processed event or clip is selected, the **Count** column shows how many instances of each process are used on the whole selection.

You can copy or cut processes with all settings and paste them to other events, clips, or ranges, delete them, and make offline processing permanent by using the context menu.

If a process is not available on your computer, it is shown as **Not available**.

2 Process panel

Allows you to modify or delete the selected plug-in effect (Cubase Pro only) or audio process.

The **Apply** and **Discard** buttons allow you to apply a new plug-in effect (Cubase Pro only) or audio process or a parameter change manually to the audio or to discard it. They become available if you deactivate **Auto Apply** (Cubase Pro only).

NOTE

- If **Auto Apply** is activated, the **Apply** and **Discard** buttons are not available.
 - Cubase Pro only: The effect parameters for plug-ins are described in the separate document **Plug-in Reference**.
-

3 Toolbar

Allows you to add audio processing, to audition the audio with the current edits, and to make global settings for offline processing.

RELATED LINKS

[Applying Processing](#) on page 420

[Bypass Processes](#) on page 424

[Applying Offline Processing Permanently](#) on page 424

[Applying Processing to Multiple Events](#) on page 421

[Deactivating Auto Apply \(Cubase Pro only\)](#) on page 421

[Direct Offline Processing Toolbar](#) on page 419

Direct Offline Processing Toolbar

The **Direct Offline Processing** toolbar allows you to add audio processing, to audition the audio with the current edits, and to make global settings for offline processing.

On the toolbar, the following options and settings are available:

Add Plug-in (Cubase Pro only)

Allows you to add a plug-in effect to the selected event or clip.

Add Process

Allows you to add a built-in audio process to the selected event or clip.

Auto Apply (Cubase Pro only)

If this option is activated and you add or modify a plug-in effect (Cubase Pro only) or an audio process, it is instantly rendered into the audio and added to the process list in the left zone of the **Direct Offline Processing** window.

If this option is deactivated, you can make your settings on the process panel without rendering your changes instantly into the audio. To add the plug-in effect or the audio process to the process list, or to apply parameter changes of a process that you already added, click **Apply**. To discard a plug-in effect, an audio process, or a parameter change, click **Discard**.

NOTE

The **Auto Apply** function for instant rendering is suited for most workflows. However, if you work with long events or if you use plug-ins that have a learning function, you might want to deactivate it.

Audition

Allows you to audition the selected audio with all processing from the top of the process list up to the selected process in the list. All processes below are ignored during playback.

Audition Loop loops the playback until you deactivate the **Audition** button. The **Audition Volume** slider allows you to adjust the volume.

Extend Process Range in ms

Allows you to extend the process range over the left and right of the event borders. This allows you to enlarge the event at a later stage with all applied processing.

Tail in ms (Cubase Pro only)

Allows you to add time at the end of the rendered files. This way, reverb and delay effects can fully fade out.

Show/Hide Left Zone

Shows/Hides the left zone of the **Direct Offline Processing** window that contains the process list.

NOTE

This setting is saved globally.

RELATED LINKS

[Deactivating Auto Apply \(Cubase Pro only\)](#) on page 421

[Extend the Process Range](#) on page 422

[Tail \(Cubase Pro only\)](#) on page 422

Applying Processing

You can add processing to one or multiple events, clips, or ranges in the **Direct Offline Processing** window. This includes plug-in effects (Cubase Pro only), audio processes, and **Sample Editor** operations, such as **Cut**, **Paste**, **Delete**, and using the **Draw** tool.

Cubase Pro only: The **Auto Apply** function for instant rendering is suited for most workflows. However, if you work with long events or if you use plug-ins that have a learning function, you might want to deactivate it.

PROCEDURE

1. Do one of the following:
 - Select an event or a range in the **Project** window.
 - Select a clip in the **Pool**.
 - Select a range in the **Sample Editor**.
 - Select an event or a range in the **Audio Part Editor**.
2. Select **Audio > Direct Offline Processing**.
3. On the **Direct Offline Processing** toolbar, click **Add Plug-in** (Cubase Pro only) or **Add Process** and select a plug-in effect or an audio process.

IMPORTANT

- You can select all installed VST plug-ins for offline processing. However, not every plug-in is suited for offline processing.
 - If you apply a stereo effect to mono audio material, the left side of the effect's stereo output is used.
-

The selected plug-in effect or audio process is added to the process list in the left zone.

4. Activate **Audition** and make your settings on the process panel.
You get a visual feedback while a process is running. However, even if the processing is not finished, you can activate **Audition** at any time.
 5. Optional (Cubase Pro only): If **Auto Apply** is deactivated, choose whether you want to apply the processing to the audio or to discard it.
 - Click **Apply** to add the plug-in effect or audio process to the process list and render it into the audio.
 - Click **Discard** to discard the plug-in effect or audio process. The process panel is emptied.
-

RESULT

The plug-in effect (Cubase Pro only) or audio process is rendered into the audio.

In the **Project** window, the **Pool** or the **Audio Part Editor**, the processed events show a waveform symbol.

Applying Processing to Multiple Events

Direct Offline Processing allows you to add plug-in effects (Cubase Pro only) or built-in audio processes to multiple events at once. You can also modify or delete processing on multiple events simultaneously.

- To apply plug-ins (Cubase Pro only) or audio processes to multiple events at once, select the audio and add, modify, or delete the processing.

If you select multiple events, the **Count** column of the process list shows how many instances of each process are used on the whole audio selection. The processes in the process list are ordered alphabetically.

NOTE

Cubase Pro only: Applying plug-in effects to multiple events that have different channel configurations may lead to unwanted results depending on the plug-in used.

NOTE

In the **Direct Offline Processing** window, you can also edit the audio processing of multiple clips in the **Pool** simultaneously.

RELATED LINKS

[Built-In Audio Processes](#) on page 425

[Direct Offline Processing Window](#) on page 417

Deactivating Auto Apply (Cubase Pro only)

When you add or modify plug-in effects or audio processes, the processing is by default automatically applied to the audio. If you work with long events or if you use plug-ins with learning function, you can deactivate **Auto Apply**.

If **Auto Apply** is deactivated, the following applies:

- You must click **Add** to apply processing to the audio.
- You must click **Discard** to cancel processing.

RELATED LINKS

[Applying Plug-in Effects with Learning Function \(Cubase Pro only\)](#) on page 421

Applying Plug-in Effects with Learning Function (Cubase Pro only)

You can train a plug-in effect that has a learning function, for example a plug-in for noise reduction.

PROCEDURE

1. Select an audio range that you want to use for training the plug-in about the noise spectrum. For example, you can use a pause that only contains noise and no dialog.
2. In the **Direct Offline Processing** window, deactivate **Auto Apply**.
3. Add the noise reduction plug-in and activate its learning mode.
4. On the **Direct Offline Processing** window toolbar, activate **Audition** in loop mode.
5. When you have trained the plug-in, deactivate its learning mode.
6. Deactivate **Audition**.

7. Click **Discard**.
Noise reduction is not applied at this point but the plug-in keeps the parameter settings for the learned noise spectrum.
 8. Select the whole event.
 9. In the **Direct Offline Processing** window, add the noise reduction plug-in and click **Apply**.
Noise reduction is applied with the current parameter settings.
-

RESULT

Noise reduction is applied to the whole event.

Extend the Process Range

You can extend the process range over the left and right borders of the audio event.

This setting allows you to enlarge the event even after applying the processing.

- To extend the process range, click **Extend Process Range in ms** on the **Direct Offline Processing** toolbar and specify a value in milliseconds.

NOTE

- For this to work, audio must be available outside the event borders.
 - This setting works globally for all events.
-

Tail (Cubase Pro only)

You can add time at the end of the rendered audio when applying plug-in effects.

Adding tail avoids that a reverb tail or a delay effect is cut off. Tail is added at the end of the event and the event is automatically resized.

- To add tail when applying a plug-in effect, click **Tail in ms** on the **Direct Offline Processing** toolbar and specify a value in milliseconds.

NOTE

- This setting works globally for all events.
 - Tail is added only if you add plug-in effects. If you add audio processes, for example **Gain**, no tail is added.
 - If you add tail to an event that you have manually resized before, the tail is added but the event length is not adjusted automatically. Therefore, you must adjust the event manually. In this case, the tail is mixed with the underlying audio clip.
-

RELATED LINKS

[Resize Events](#) on page 194

Modifying Processes

You can delete or modify some or all processing from a clip in the **Direct Offline Processing** window. This includes the audio processes on the **Processes** menu, any applied plug-in effects (Cubase Pro only), and **Sample Editor** operations, such as **Cut**, **Paste**, **Delete**, and drawing with the **Draw** tool.

Cubase Pro only: The **Auto Apply** function for instant rendering is suited for most workflows. However, if you work with long events or if you use plug-ins that have a learning function, you might want to deactivate it.

PROCEDURE

1. Do one of the following:
 - Select the processed event in the **Project** window or in the **Audio Part Editor**.

NOTE

In the **Project** window or in the **Audio Part Editor**, processed events are indicated by a waveform symbol in the upper right corner.

 - Select the processed clip in the **Pool**.

NOTE

In the **Pool**, processed clips are indicated by a waveform symbol in the **Status** column.

 - Select the processed range in the **Sample Editor**.
 2. Select **Audio > Direct Offline Processing**.
 3. In the process list, select the process that you want to edit by clicking on it.
 4. Do one of the following:
 - Activate **Audition** and modify the settings of the process.
 - Delete the process by clicking **Delete**  on the process panel.

NOTE

Alternatively, you can right-click the process list and select **Delete**.

 - To delete all processing applied to the event, right-click the process list and select **Delete All**.
 5. Optional (Cubase Pro only): If **Auto Apply** is deactivated, choose whether you want to apply your parameter changes to the audio or to discard them.
 - Click **Apply** to apply the parameter changes to the audio.
 - Click **Discard** to discard the parameter changes.
-

RELATED LINKS

[Direct Offline Processing Window](#) on page 417
[Pool Window Columns](#) on page 528

Reordering the Process List

You can reorder the operations in the **Direct Offline Processing** process list by dragging.

PROCEDURE

- Click a plug-in effect or an audio process and move it by dragging.
-

RESULT

The offline processing operations are rendered into the audio in the specified order.

Bypass Processes

In the **Direct Offline Processing** window, you can bypass processes. This allows you to hear the audio without the processes.

- To activate/deactivate bypass for a process, click the **Bypass Process** button on the left of the process.

NOTE

- If you activate/deactivate **Bypass Process**, the complete process chain is recalculated. Depending on the length of the audio and number of processes, this may take some time. In the process list, you get a visual feedback while a process is running.
 - The bypass status is saved with the project.
-

Applying Offline Processing Permanently

You can apply all offline processing permanently to the audio.

PREREQUISITE

You have applied plug-in effects (Cubase Pro only) or audio processes to an event, clip, or range and you are sure that you do not need to edit the processing anymore.

IMPORTANT

Making offline processing permanent cannot be undone.

PROCEDURE

1. Select the processed event, clip, or range.
2. Select **Audio > Make Direct Offline Processing Permanent**.

NOTE

Alternatively, select **Make All Permanent** in the context menu of the **Direct Offline Processing** process list.

3. In the dialog that opens, select **OK**.
-

RESULT


- All processing and applied effects are permanently added to the selected event, clip, or range.
- The process list is emptied.
- The event or clip is no longer marked as offline-processed by a waveform symbol.

Built-In Audio Processes

Cubase provides several built-in audio processes that can be used for **Direct Offline Processing**.

Envelope

Envelope allows you to apply a volume envelope to the selected audio.



Curve Kind buttons

Determine whether the corresponding envelope uses **Spline Interpolation**, **Damped Spline Interpolation**, or **Linear Interpolation**.

Envelope display

Shows the shape of the envelope. The resulting waveform shape is shown in a dark tone, with the current waveform shape in a light tone.

- To add a curve point, click the curve.
- To move a curve point, click and drag.
- To remove a curve point, click and drag it outside the display.


Presets

Allow you to set up presets that you want to apply to other events or clips.

- To save a preset, click **Store**, type in a name, and click **OK**.
- To apply a preset, select it from the pop-up menu.
- To remove a preset, select it from the pop-up menu, and click **Remove**.

Fade In/Fade Out

Fade In and **Fade Out** allow you to apply a fade to the selected audio.



Curve Kind buttons

Determine whether the corresponding envelope uses **Spline Interpolation**, **Damped Spline Interpolation**, or **Linear Interpolation**.

Fade display

Shows the shape of the fade curve. The resulting waveform shape is shown in a dark tone, with the current waveform shape in a light tone.

Click the curve to add points, and click and drag existing points to change the shape. To remove a point from the curve, drag it outside the display.

Presets

Allow you to set up presets that you want to apply to other events or clips.


- To save a preset, click **Store**, type in a name, and click **OK**.
- To apply a preset, select it from the pop-up menu.
- To remove a preset, select it from the pop-up menu, and click **Remove**.

Shape buttons

These buttons give you quick access to some common curve shapes.

Gain

Gain allows you to change the gain, that is, the level of the selected audio.



Gain

Allows you to set a gain value between -50 dB and +20 dB.

Clipping Detection text

This text is displayed if you use **Audition** and the gain setting results in audio levels above 0 dB.

NOTE


In case of clipping, lower the **Gain** value and use the **Normalize** audio process instead. This allows you to increase the level of the audio as much as possible without causing clipping.

RELATED LINKS

[Normalize on page 427](#)

Normalize

Normalize allows you to raise the level of audio that was recorded at too low an input level.



Normalize

Allows you to set a maximum level for the audio, between -50 dB and 0 dB. From this maximum level, the current maximum level of the selected audio is subtracted, and the gain is raised or lowered by the resulting amount.


Phase Reverse

Phase Reverse allows you to reverse the phase of the selected audio.

For stereo audio files, a pop-up menu is available. It allows you to specify which channels are phase-reversed: the left channel, the right channel, or both.

Pitch Shift

Pitch Shift allows you to change the pitch of the audio with or without affecting its length. You can also create harmonies by specifying several pitches or apply pitch shift based on an envelope curve.



On the **Transpose** tab, the following options are available:

Keyboard display

Shows a graphic overview of the transposition where the root note is indicated in red and the transposed key is indicated in blue.

NOTE

The indicated root note has nothing to do with the key or pitch of the original audio, it just provides a way to display transpose intervals.

- To change the root note, use the settings in the **Pitch Shift Base** section, or hold **Alt**, and click the keyboard display.
- To specify a transpose interval, click one of the keys.
- To specify a chord, activate **Multi Shift** and click several keys.
To remove a transpose interval, click a blue key.

Pitch Shift Settings

Transpose

Allows you to specify the amount of pitch shift in semitones.

Fine-Tune

Allows you to specify the amount of pitch shift in cents.

Volume

Allows you to lower the volume of the pitch-shifted sound. This is not available if **Time Correction** is activated.

Listen Key Level

Allows you to adjust the level of the pitch-shifted sound. Click **Listen Key/Listen Chord** to play a test tone of the pitch-shifted sound.

Pitch Shift Base

Root Note/Pitch

Allows you to set the root note.

NOTE

The indicated root note has nothing to do with the key or pitch of the original audio, it just provides a way to display transpose intervals.

Multi Shift

Activate this to specify several transpose keys and create multi-part harmonies. If the intervals you add make up a standard chord, this chord is displayed to the right.

- To include the original, untransposed sound, click the root key in the keyboard display so that it is displayed in blue.

NOTE

In **Multi Shift** mode, **Audition** is not available.

Algorithm Settings

Time Correction

Activate this option to shift the pitch without affecting the length of the audio. If this is deactivated and you raise the pitch, the audio section is shortened.

MPEX 4 Preset


Allows you to select an MPEX 4 algorithm.

RELATED LINKS

[Time Stretch and Pitch Shift Algorithms](#) on page 435

Envelope-Based Pitch Shift

On the **Envelope** tab, you can specify an envelope curve as a base for the pitch shift.



Curve Kind buttons

Determine whether the corresponding envelope uses **Spline Interpolation**, **Damped Spline Interpolation**, or **Linear Interpolation**.

Envelope display

Shows the shape of the envelope curve over the waveform image of the audio selected for processing. Envelope curve points above the center line indicate a positive pitch shift, curve points below the center line indicate a negative pitch shift. Initially, the envelope curve is a horizontal, centered line, indicating zero pitch shift.

- To add a curve point, click the curve.
- To move a curve point, click and drag.
- To remove a curve point, click and drag it outside the display.
- To remove all curve points, click **Reset** above the envelope display.

Pitch Shift Settings

Range

Allows you to determine the vertical pitch range of the envelope. Moving a curve point to the top of the display shifts the pitch by this value.

Transpose

Allows you to specify the amount of pitch shift in semitones.

Fine-Tune

Allows you to specify the amount of pitch shift in cents.

Algorithm Settings

Time Correction

Activate this option to shift the pitch without affecting the length of the audio. If this is deactivated, raising the pitch will shorten the audio section and vice versa, much like changing the playback speed on a tape recorder.

MPEX 4 Preset

Allows you to select an MPEX 4 algorithm.

RELATED LINKS

[MPEX](#) on page 436

Remove DC Offset

Remove DC Offset allows you to remove any DC offset in the audio selection.

If your audio signal contains too large a component of direct current, you may notice that it is not centered around the zero level axis. This is called DC offset.

- To verify if your audio contains DC offsets, select the audio and select **Audio > Statistics**.

IMPORTANT

DC offset is normally present throughout the entire recording. Therefore, always apply **Remove DC Offset** to complete audio clips.

There are no adjustable parameters for this audio process.


RELATED LINKS

[Statistics](#) on page 443

Resample

Resample allows you to change the length, tempo, and pitch of an event.

If you resample to a higher sample rate, the event gets longer and the audio plays back at a slower speed with a lower pitch. If you resample to a lower sample rate, the event gets shorter and the audio plays back at a faster speed with a higher pitch.



File Sample Rate

Shows the original sample rate of the event.

New Sample Rate

Allows you to resample the event by specifying a sample rate.

Difference

Allows you to resample the event by specifying the difference between the original sample rate and the new sample rate.

Reverse

Reverse allows you to reverse the audio selection so that it sounds as if you play back a tape backwards. There are no adjustable parameters for this audio process.

Silence

Silence allows you to replace the selection with silence. There are no adjustable parameters for this audio process.

Stereo Flip

Stereo Flip allows you to manipulate the left and right channels of stereo audio selections.

In the **Mode** pop-up menu, the available options are:

Flip Left-Right

Swaps the left and right channel.

Left to Stereo

Copies the left channel sound to the right channel.

Right to Stereo

Copies the right channel sound to the left channel.

Merge


Merges both channels on each side for mono sound.

Subtract

Subtracts the left channel information from the right. This function is typically used for karaoke background as it removes the centered mono material from a stereo signal.

Time Stretch

Time Stretch allows you to change the length and tempo of the selected audio without affecting the pitch.



Define Bars

You can set the length of the selected audio and the time signature in this section.

Bars

Allows you to set the length of the selected audio in bars.

Beats

Allows you to set the length of the selected audio in beats.

Signature

Allows you to set the time signature.

Original Length

This section contains information and settings regarding the audio that is selected for processing.

Length in Samples

Shows the length of the selected audio in samples.

Length in Seconds

Shows the length of the selected audio in seconds.

Tempo in BPM

Allows you to enter the actual tempo of the audio in beats per minute. This option allows you to time-stretch the audio to another tempo, without having to compute the actual time stretch amount.

Resulting Length

These values change automatically if you adjust the **Time Stretch Ratio** to stretch the audio so that it fits within a specific time span or tempo.

Samples

Shows the resulting length in samples.

Seconds

Shows the resulting length in seconds.

BPM

Shows the resulting tempo in beats per minute. For this to work, the **Original Length** must be specified.

Seconds Range

These settings allow you to set a range for the time stretch.

Arbitrary Range Start Time

Allows you to set a start position for the range.

Arbitrary Range End Time

Allows you to set an end position for the range.

Use Locators

Allows you to set the **Range** values to the left and right Locator positions, respectively.

Algorithm

Allows you to select a time stretch algorithm.

Time Stretch Ratio

Allows you to set the amount of time stretch as a percentage of the original length. If you use the settings in the **Resulting Length** section to specify the amount of time stretch, this value changes automatically.

RELATED LINKS

[Time Stretch and Pitch Shift Algorithms](#) on page 435

Applying Direct Offline Processing Using Key Commands

You can apply offline processing by using key commands.

If you add plug-in effects (Cubase Pro only) or audio processes using key commands, the following applies:

- The current settings are used.
- The **Direct Offline Processing** window opens. This does not apply if the selected process does not feature any adjustable parameters, or if the window is in the background or minimized.

NOTE

The **Direct Offline Processing** window is only effective in background or minimized if **Auto Apply** is activated.

RELATED LINKS

[Key Commands for Direct Offline Processing](#) on page 433

Key Commands for Direct Offline Processing

If the corresponding section in the **Direct Offline Processing** window has the focus, the following default key commands apply:

Option	Key command
Open/Close Direct Offline Processing window	F7
Set focus within Direct Offline Processing window	Tab
Navigate in the process list	Up Arrow/Down Arrow
Activate/Deactivate Audition (Playback Toggle triggers Local Preview must be activated in the Preferences dialog)	Space
Cubase Pro only: Apply process in process panel (only available if Auto Apply is deactivated)	Enter
Cubase Pro only: Discard process in process panel (only available if Auto Apply is deactivated)	Delete
Delete selected item from process list	Delete
Select all items in process list	Ctrl/Cmd-A
Copy selected items in process list	Ctrl/Cmd-C

Option	Key command
Paste items to process list	Ctrl/Cmd-V
Undo	Ctrl/Cmd-Z

To define key commands for further **Direct Offline Processing** operations, and for directly adding particular plug-in effects (Cubase Pro only) and audio processes, use the **Key Commands** dialog.

RELATED LINKS

[Direct Offline Processing Window](#) on page 417

[Transport](#) on page 1035

[Deactivating Auto Apply \(Cubase Pro only\)](#) on page 421

[Key Commands](#) on page 973

Time Stretch and Pitch Shift Algorithms

In Cubase, time-stretching and pitch-shifting algorithms are used for offline processes, in the **Sample Editor**, or for the **Flattening Realtime Processing** function. Depending on the feature, **élastique**, **MPEX**, or **Standard** algorithm presets are available.

RELATED LINKS

[Time Stretch](#) on page 431

[Pitch Shift](#) on page 427

[Sample Editor](#) on page 445

[Flattening Realtime Processing](#) on page 481

[élastique](#) on page 435

[MPEX](#) on page 436

[Standard](#) on page 436

[Limitations](#) on page 437

élastique

The **élastique** algorithm is suited for polyphonic and monophonic material.

The following modes are available:

élastique Pro

For best audio quality, without formant preservation.

élastique Pro Formant

For best audio quality, but including formant preservation.

élastique efficient

Requires less computing power, but has a lower audio quality than the **Pro** modes.

The modes support the following variants:

Time

Favors timing accuracy over pitch accuracy.

Pitch

Favors pitch accuracy over timing accuracy.

Tape

Locks the pitch shift to the time stretch as if playing back a tape with varying speed. If you stretch the audio material, the pitch decreases automatically. This variant has no effect if you use it with event transpose or the transpose track.

MPEX

MPEX is an alternative high-quality algorithm.

You can choose between the following quality settings:

MPEX – Preview Quality

For preview purposes.

MPEX – Mix Fast

A very fast mode for preview. This mode works best with composite music signals (mono or stereo material).

MPEX – Solo Fast

For single instruments (monophonic material) and voice.

MPEX – Solo Musical

Higher quality for single instruments (monophonic material) and voice.

MPEX – Poly Fast

For monophonic and polyphonic material. This is the fastest setting that still gives very good results. You can use this for drum loops, mixes, and chords.

MPEX – Poly Musical

For monophonic and polyphonic material. This is the recommended **MPEX** quality setting. You can use this for drum loops, mixes, or chords.

MPEX – Poly Complex

For complex material or for stretch factors above 1.3. This high-quality setting is quite CPU-intensive.

NOTE

If you apply **Pitch Shift** as an offline process, you can choose between the regular setting and a setting where the formants are preserved for each quality setting.

Standard

The **Standard** algorithm is optimized for CPU-efficient realtime processing.

The following presets are available:

Standard – Drums

For percussive sounds. This mode does not change the timing of your audio. If you use it with certain tuned percussion instruments, you may experience audible artifacts. In this case, try the **Mix** mode as an alternative.

Standard – Plucked

For audio with transients and a relatively stable spectral sound character like plucked instruments.

Standard – Pads

For pitched audio with slower rhythm and a stable spectral sound character. This minimizes sound artifacts, but the rhythmic accuracy is not preserved.

Standard – Vocals

For slower signals with transients and a prominent tonal character like vocals.

Standard – Mix

For pitched material with a less homogenous sound character. This mode preserves the rhythm and minimizes the artifacts.

Standard – Custom

Allows you to set the time-stretching parameters manually.

Standard – Solo

For monophonic material like solo woodwind/brass instruments or solo vocals, monophonic synths or string instruments that do not play harmonies. This mode preserves the timbre of the audio.

Custom Warp Settings

If you select the **Standard – Custom** mode, a dialog opens where you can manually adjust the parameters that govern the sound quality of the time stretching:

Grain Size

Allows you to determine the size of the grains in which the standard time-stretching algorithm splits the audio. Low grain size values lead to good results for material that has many transients.

Overlap

This is the percentage of the whole grain that will overlap with other grains. Use higher values for material with a stable sound character.

Variance

This is a percentage of the whole length of the grains, and sets a variation in positioning, so that the overlapping area sounds smooth. A variance setting of 0 produces a sound akin to time stretching used in early samplers, whereas higher settings produce more rhythmic smearing effects but fewer audio artifacts.

Limitations

Applying time stretching or pitch shifting to audio material can lead to a degradation in audio quality and to audible artifacts. The result depends on the source material, the particular stretch and pitch operations applied, and the selected audio algorithm preset.

As a rule of thumb, smaller changes in pitch or duration cause less degradation. However, there are additional issues one should be aware of when working with time stretching and pitch shifting algorithms.

NOTE

In rare cases, editing warped audio events may cause discontinuities at the edit points. You can then try to move the edit point to a different position or bounce the audio event prior to editing.

Reverse Playback and Scrubbing

Most of the algorithms used for time stretching and pitch shifting only support forward playback. Reverse playback or scrubbing of warped audio events can lead to recurring artifacts in playback.

Pitch and Stretch Factor

Some algorithms may put limitations on the maximum degree of time stretching or pitch shifting supported. However, with *élastique* there are no limitations.

Audio Functions

Cubase offers particular functions for analyzing the audio in your project.

RELATED LINKS

[Detect Silence](#) on page 438


[Spectrum Analyzer](#) on page 440

[Statistics](#) on page 443

Detect Silence

Detect Silence allows you to search for silent sections in events.

You can split events and remove the silent parts from the project, or create regions corresponding to the non-silent sections.



- To open the **Detect Silence** dialog, select one or multiple audio events or a range in the **Project** window or the **Audio Part Editor**, and select **Audio > Advanced > Detect Silence**.

NOTE

If you select multiple events, you can process the selected events successively with individual settings or apply the same settings to all selected events simultaneously.

The following options are available:

Waveform Display

Allows you to zoom in on and out of the waveform by using the zoom slider to the right, by clicking in the waveform, and moving the mouse up or down.

You can scroll the waveform by using the scrollbar, or by using the mouse wheel.

You can adjust the **Open Threshold** and **Close Threshold** values by moving the squares at the beginning and at the end of the audio file.

Open Threshold

When the audio level exceeds this value, the function opens and lets the sound pass. Audio material below the set level is detected as silence.

Close Threshold

When the audio level drops below this value, the function closes and detects sounds below this level as silence. This value cannot be higher than the **Open Threshold** value.

Linked

Activate this option to set the same values for **Open Threshold** and **Close Threshold**.

Min. Time Open

Determines the minimum time that the function remains open after the audio level has exceeded the **Open Threshold** value.

NOTE

If your audio contains repeated short sounds, and this results in too many short open sections, try raising this value.

Min. Time Closed

Determines the minimum time that the function remains closed after the audio level has dropped below the **Close Threshold** value. Set this to a low value to make sure that you do not remove sounds.

Pre-Roll

Causes the function to open slightly before the audio level exceeds the **Open Threshold** value. Use this option to avoid removing the attack of sounds.

Post-Roll

Causes the function to close slightly after the audio level drops below the **Close Threshold** value. Use this option to avoid removing the natural decay of sounds.

Add as Regions

Creates regions of the non-silent sections, and allows you to specify a name for them in the **Region Name** field. A number is appended on each region name, starting with the number specified in the **Auto Number Start** field.

Strip Silence

Splits the event at the beginning and end of each non-silent section, and removes the silent sections in between.

Process All Selected Events

Applies the same settings to all selected events. This option is only available if you selected more than one event.

Compute

Analyzes the audio event and redraws the waveform display to indicate which sections are considered silent. The number of detected regions is displayed above the **Compute** button.

Auto

Activate this option to analyze the audio event and update the display automatically every time you change the settings.

NOTE

If you are working with very long files, consider deactivating the **Auto** option as this may slow down the process.

Removing Silent Sections


The **Detect Silence** dialog allows you to detect and remove silent sections of your audio.

PROCEDURE

1. Select one or multiple audio events with silent sections in the **Project** window.
 2. Select **Audio > Advanced > Detect Silence**.
 3. In the **Detect Silence** dialog, make your settings.
 4. Click **Compute** to analyze the audio.
The audio is analyzed and the waveform redrawn to indicate which sections are considered silent according to your settings. The number of detected regions is displayed.
 5. Optional: Click **Preview** to listen to the result.
The event is played back and the sections are silenced according to your settings.
 6. Optional: In the **Detection** section, readjust the settings until you are satisfied with the result.
 7. Optional: In the **Output** section, activate **Add as Regions**.
 8. In the **Output** section, activate **Strip Silence**.
 9. Click **Process**.
-

RESULT

The event is split and the silent sections are removed.



AFTER COMPLETING THIS TASK

If you have selected more than one event and did not activate **Process all selected Events**, the **Detect Silence** dialog opens again after processing, allowing you to make separate settings for the next event.


Spectrum Analyzer

The **Spectrum Analyzer** analyzes the selected audio, computes the average spectrum, and displays it in a two-dimensional graph, with frequency range on the x-axis and level distribution on the y-axis.

- To open the **Spectrum Analyzer**, select **Audio > Spectrum Analyzer**.

Spectrum Analyzer Settings

The **Spectrum Analyzer** shows the following settings:



Size in Samples

Allows you to set a size for the analysis blocks of the audio. The higher this value, the higher the frequency resolution of the resulting spectrum.

Size of Overlap

Allows you to set the overlap between each analysis block.

Window Used

Allows you to select which window type is used for the fast Fourier transform, the mathematical method used for computing the spectrum.

Normalized Values

Activate this option to scale the resulting level values, so that the highest level is displayed as 1. This corresponds to 0 dB.

From Stereo


Allows you to specify which channel is analyzed.

Process

Starts the analysis of the spectrum and opens the spectrum display.

Spectrum Display

The **Spectrum Display** shows the following settings:



Frequency Display

Allows you to compare the levels between frequencies. Move the pointer to one of the frequencies, right-click and move the pointer to the second frequency. The difference in level between the positions is displayed and labeled **D** in the upper right corner.

NOTE

For stereo audio, the display in the upper right corner shows the values for the left channel. To show the right channel values, hold down **Shift**.

dB

Activate this option to show dB values on the vertical axis. Deactivate this option to show values between 0 and 1.

Freq. Log

Activate this option to display the frequencies on the horizontal axis on a logarithmic scale. Deactivate this option to show a linear frequency axis.

Precision

Indicates the frequency resolution of the graph. This value is governed by the **Size in Samples** setting in the spectrum analyzer settings.

Frequency (Hz)/Note (C)

Allows you to select if frequencies are displayed in Hertz or with note names.

Min.

Allows you to set the lowest frequency shown in the graph.

Max.

Allows you to set the highest frequency shown in the graph.

Active

Activate this option to open the next **Spectrum Analysis** dialog in the same window. Deactivate this option to show the next dialog in a separate window.

Analyzing the Audio Spectrum

PROCEDURE

1. Select an audio event, clip, or a selection range.
 2. Select **Audio > Spectrum Analyzer**.
 3. Adjust the settings or use the default values.
The default values give good results in most situations.
 4. Click **Process**.
-

RESULT

The spectrum is computed and displayed as a graph.

AFTER COMPLETING THIS TASK

Adjust the settings in the spectrum display and move the mouse pointer over the graph to display the frequency/note and level at the current position in the upper right corner.

Statistics

The **Statistics** function analyzes the selected audio events, clips, or selection ranges.

Channel	Left	Right
Min. Sample Value	-0.30 dB	-0.30 dB
Max. Sample Value	-0.52 dB	-0.30 dB
Peak Amplitude	-0.30 dB	-0.30 dB
True Peak	0.30 dB	0.08 dB
DC Offset	0.38 %	0.34 %
	-74.84 dB	-73.03 dB
Bit Depth	24 bit	24 bit
Estimated Pitch	286.7Hz/D3	470.1Hz/A#3
Sample Rate	44.100 kHz	
Average RMS (AES-17)	-28.25 dB	-25.92 dB
Max. RMS	-9.00 dB	-8.20 dB
Max. RMS All Channels	-8.20 dB	
EBU R 128		
Max. Momentary Loudness	-8.56 LUFS	
Max. Short-Term Loudness	-16.51 LUFS	
Integrated Loudness	-14.75 LUFS	
Loudness Range	14.80 LU	
Max. True Peak Level	0.30 dBTP	
Copy to Clipboard		
Close		

The **Statistics** window shows the following information:

Channel

Shows the name of the analyzed channel.

Min. Sample Value

Shows the lowest sample value in dB.

Max. Sample Value

Shows the highest sample value in dB.

Peak Amplitude

Shows the largest amplitude in dB.

True Peak

Shows the maximum absolute level of the audio signal waveform in the continuous time domain.

DC Offset

Shows the amount of DC offset as a percentage and in dB.

Bit Depth

Shows the current calculated bit depth.

Estimated Pitch

Shows the estimated pitch.

Sample Rate

Shows the sample rate.

Average RMS (AES-17)

Shows the average loudness in accordance with the AES-17 standard.

Max. RMS

Shows the highest RMS value.

Max. RMS All Channels

Shows the highest RMS value of all channels.

Max. Momentary Loudness (Cubase Pro only)

Shows the maximum value of all momentary loudness values, based on a time window of 400 ms. The measurement is not gated.

Max. Short-Term Loudness (Cubase Pro only)

Shows the maximum value of all short-term loudness values, based on a time window of 3 s. The measurement is not gated.

Integrated Loudness (Cubase Pro only)

Shows the average loudness over the whole title in LUFS (Loudness Unit, referenced to Full Scale) in accordance with EBU R-128 that recommends to normalize audio at -23 LUFS (± 1 LU).

Loudness Range (Cubase Pro only)

Shows the dynamic range over the whole title in LU (Loudness Units). This value allows you to see if dynamic processing is needed.

Max. True Peak Level (Cubase Pro only)

Shows the maximum value of the audio signal waveform in the continuous time domain.

RELATED LINKS

[Remove DC Offset](#) on page 430

Sample Editor

The **Sample Editor** provides an overview of the selected audio event. It allows you to view and edit audio by cutting and pasting, removing, or drawing audio data, and by processing audio. Editing is non-destructive so that you can undo modifications at any time.

You can open the **Sample Editor** in a separate window or in the lower zone of the **Project** window. This is useful if you want to access the **Sample Editor** functions from within a fixed zone of the **Project** window.


To open an audio event in the **Sample Editor**, do one of the following:

- Double-click an event in the **Project** window.
- Select an event in the **Project** window and press **Return** or **Ctrl/Cmd-E**.
- Select an event in the **Project** window and select **Audio > Open Sample Editor**.
- In the **Key Commands dialog** in the **Editors** category, assign a key command for **Open Sample Editor**. Select an event in the **Project** window and use the key command.

NOTE

If you select **Audio > Set up Editor Preferences**, the **Preferences** dialog opens on the **Editors** page. Make your settings to specify if you want the **Sample Editor** to open in a separate window or in the lower zone of the **Project** window.

The **Sample Editor** window:



The **Sample Editor** in the lower zone of the **Project** window:



The **Sample Editor** is divided into several sections:

- 1 **Toolbar**
Contains tools for selecting, manipulating, and playing back audio.
- 2 **Info Line**
Shows information about the audio.
- 3 **Overview Line**
Shows an overview of the whole audio clip and indicates which part of the clip is shown in the waveform display.
- 4 **Inspector**
Contains audio editing tools and functions.

NOTE

The **Editor Inspector** for the lower zone editor is shown in the left zone of the **Project** window.

- 5 **Ruler**
Shows the timeline and the display format of the project.
- 6 **Waveform Display**
Shows the waveform image of the edited audio clip.
- 7 **Regions**
Allows you to add and edit regions.

NOTE

The info line, the overview line, and the regions can be activated/deactivated by clicking **Set up Window Layout** on the toolbar and activating/deactivating the corresponding options.

RELATED LINKS

[Opening the Editor in the Lower Zone](#) on page 64

[Opening the Editor Inspector](#) on page 54

[Toolbar](#) on page 447

[Info Line](#) on page 451

[Overview Line](#) on page 451

[Sample Editor Inspector](#) on page 452

[Ruler](#) on page 455

[Waveform Display](#) on page 455

[Regions List](#) on page 461

Toolbar

The toolbar contains tools for selecting, editing, and playing back audio.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

The following options are available:

Static Buttons

Solo Editor



Solos the selected audio during playback.

Left Divider

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

View Options

Show Audio Event



Highlights the section corresponding to the edited event in the waveform display and the overview line.

NOTE

This button is not available if you opened the audio event from the **Pool**. You can adjust the start and end of the event in the clip by dragging the event handles in the waveform display.

Show Regions




Opens a section where you can view and edit regions.

Edit Active Audio Event Only (Cubase Pro only)



Restricts editing operations to the active audio event.

Currently Edited Audio Event



Lists all audio events that are opened in the **Sample Editor**, and allows you to activate an audio event for editing.

Auto-Scroll

Auto-Scroll



Keeps the project cursor visible during playback. The **Switch Auto-Scroll Settings** pop-up menu allows you to activate **Page Scroll** or **Stationary Cursor** and to activate **Suspend Auto-Scroll When Editing**.

Preview

Audition



Plays back the edited audio. **Audition Loop** loops the playback until you deactivate the **Audition** icon. The **Audition Volume** slider allows you to adjust the volume.

Tool Buttons

Range Selection



Allows you to select ranges.

Zoom



Allows you to zoom in the waveform display. To zoom out, hold **Alt** while clicking.

Draw



Allows you to edit audio.

Play



Allows you to play back the clip from the position where you click until you release the mouse button.

Scrub



Allows you to locate positions.

Time Warp (Cubase Pro only)



Allows you to drag a musical position to a certain position in time.

Acoustic Feedback

Acoustic Pitch Feedback (Cubase Pro only)



Automatically plays back a VariAudio segment when you modify the pitch.

Snap

Snap to Zero Crossings



Restricts editing to zero crossings, that is, positions where the amplitude is zero.

Snap



Restricts horizontal movement and positioning to certain positions.

Musical Information

Musical Mode



Locks audio clips to the project tempo by using realtime time stretching.


Musical Information



Displays the estimated length of your audio file, the estimated tempo, the time signature, and the warp algorithm. These values are important for using **Musical Mode**.

VariAudio Segment Colors

VariAudio Segment Colors



Allows you to select a color scheme for VariAudio segments. This makes it easier to see which segments belong to which event when working with several audio events.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls

Open in Separate Window



This button is available in the lower zone editor. It opens the editor in a separate window.

Open in Lower Zone



This button is available in the editor window. It opens the editor in the lower zone of the **Project** window.

Set up Window Layout



Allows you to activate/deactivate the info line, the overview line, and the regions.

Set up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.

RELATED LINKS

[Auto-Scroll](#) on page 221

[Suspend Auto-Scroll When Editing](#) on page 221

Locating Positions with the Scrub Tool

The Scrub tool allows you to locate positions in the audio.

PROCEDURE

1. On the toolbar, activate the **Scrub** tool.
 2. Click in the waveform display and keep the mouse button pressed.
The project cursor moves to the position where you clicked.
 3. Drag to the left or right.
-

RESULT

The audio is played back, and you can hear at which position the cursor is located.

NOTE


You can determine the speed and pitch of the playback by dragging faster or slower.

Editing Audio Samples with the Draw Tool

You can edit the audio clip at sample level with the **Draw** tool. This way, you can remove audio clicks manually, for example.

PROCEDURE

1. On the audio waveform, locate the sample position that you want to edit and zoom in to the lowest zoom level.
2. Select the **Draw** tool.



- Click at the beginning of the section that you want to correct and draw in the new curve.

RESULT

A range selection covering the edited section is automatically applied.



NOTE

Cubase Pro only: The **Draw** tool cannot be used when the **VariAudio** section is open.

Info Line

The info line shows information about the audio clip, such as the audio format and the selection range.

Sample Rate	Bit Depth	Length	Global Transpose	Processing	Domain	Offline Edits
48000 kHz	24 bit	59.906	Follow	None	Seconds	0
Zoom	Selection	Current Pitch	Original Pitch			
1918.2836	57.039 [2:06:13.574 - 2:07:10.613]	-	-			


- To show or hide the info line, click **Set up Window Layout** on the toolbar and activate or deactivate the **Info Line** option.
The on/off status of the info line in the **Sample Editor** window and in the lower zone editor are independent of each other.

NOTE

Initially, length and position values are displayed in the format specified in the **Project Setup** dialog.

Overview Line

The overview line displays the whole clip, and indicates which part of the clip is shown in the waveform display.



- To show or hide the overview line, click **Set up Window Layout** on the toolbar and activate or deactivate the **Overview Line** option.
The on/off status of the overview line in the **Sample Editor** window and in the lower zone editor are independent of each other.

- 1 Event Start**
Shows the start of the audio event if **Show Audio Event** is activated on the toolbar.
- 2 Selection**
Shows which section is selected in the waveform display.
- 3 Event End**
Shows the end of the audio event if **Show Audio Event** is activated on the toolbar.
- 4 Waveform display**
Shows the section of the audio that is displayed in the waveform display.
 - You can specify which section of the audio is shown by clicking in the lower half of this display and dragging to the left or right.
 - You can zoom in or out horizontally by dragging the left or right edge of this display.
 - You can show a different section of the audio by clicking in the upper half of this display and dragging a rectangle.
- 5 Snap Point**
Shows the start of the audio event if **Show Audio Event** is activated on the toolbar.

Sample Editor Inspector

The **Inspector** shows controls and parameters that allow you to edit the audio event that is opened in the **Sample Editor**.

- In the **Sample Editor** window you can show or hide the **Inspector** by clicking **Set up Window Layout** on the toolbar and activating or deactivating **Inspector**.

NOTE

In the lower zone editor, the **Inspector** is always shown in the left zone of the **Project** window.

- To open or close the **Inspector** sections, click their names.



RELATED LINKS

[Opening the Editor Inspector](#) on page 54

Definition

The **Definition** section allows you to adjust the audio grid and define the musical context of your audio. You can use the available functions to match an audio file or audio loop to the project tempo.

- To open the **Definition** section, click its tab in the **Inspector**.



AudioWarp

The **AudioWarp** section allows you to perform timing settings for your audio. This includes applying **Swing** and manually changing the rhythm of the audio by dragging beats to time positions on the grid.

- To open the **AudioWarp** section, click its tab in the **Inspector**.



VariAudio (Cubase Pro only)

The **VariAudio** section allows you to edit single notes of your audio file and change their pitch or timing. Furthermore, you can extract MIDI from your audio.


- To open the **VariAudio** section, click its tab in the **Inspector**.



Hitpoints

The **Hitpoints** section allows you to edit hitpoints to slice your audio. Here you can create groove quantize maps, markers, regions, events, and warp markers based on hitpoints.


- To open the **Hitpoints** section, click its tab in the **Inspector**.



Range

The **Range** section allows you to edit ranges and selections or create a sampler track from the selected range.

- To open the **Range** section, click its tab in the **Inspector**.



Select

Opens a menu with functions to select ranges.

Start

Shows the start position of the selection range.

End

Shows the end position of the selection range.

Length

Shows the length of the selection range.

Zoom

Opens a menu with the zoom functions for ranges.

Create Sampler Track

Allows you to create a sampler track from the range selection.

Process

The **Process** section regroups the most important audio editing commands from the **Audio** and **Edit** menus.


- To open the **Process** section, click its tab in the **Inspector**.




Ruler

The ruler shows the timeline and display format of the project, the project tempo grid.

The ruler is located above the waveform display. It is always shown.




When the **Definition** section is open, an additional ruler is shown below the project tempo grid. It displays the musical structure of the audio file, the audio tempo grid.



Waveform Display

The waveform display shows the waveform image of the edited audio clip.



1 Level Scale

Indicates the amplitude of the audio.

2 Level Scale options

Allow you to select whether the level is shown as percentage or in dB.

3 Ruler

Shows the project tempo grid.

4 Audio waveform

Shows the waveform image of the selected audio.

5 Half Level Axis

To show the half level axis, open the audio waveform context menu and select **Show Half Level Axis**.

NOTE

You can set up a wave image style in the **Preferences** dialog (**Event Display—Audio** page).

Zooming in the Waveform

You can zoom in the waveform according to the standard zoom techniques.

The following applies:

- The vertical zoom slider changes the vertical scale relative to the height of the **Sample Editor**.
- The vertical zoom is also affected if **Zoom Tool Standard Mode: Horizontal Zooming only** is deactivated in the **Preferences** dialog (**Editing—Tools** page) and you drag a rectangle with the **Zoom** tool.
- You can zoom in by holding down **Alt** while drawing a selection rectangle around the segments that you want to zoom in on. You can zoom out by holding down **Alt** and clicking in an empty area of the waveform.
- The current zoom setting is shown on the info line as samples per pixel.

NOTE

You can zoom in horizontally to a scale of less than one sample per pixel. This is required for drawing with the **Draw** tool.

- If you have zoomed in to one sample per pixel or less, the appearance of the samples depends on the **Interpolate Audio Waveforms** option in the **Preferences** dialog (**Event Display—Audio** page).

Zoom Submenu

The **Zoom** submenu of the **Edit** menu contains options for zooming in the **Sample Editor**.

- To open the **Zoom** submenu, select **Edit > Zoom**.

The following options are available:

Zoom In

Zooms in one step, centering on the project cursor.

Zoom Out

Zooms out one step, centering on the project cursor.

Zoom Full

Zooms out so that the whole clip is visible in the waveform display.

Zoom to Selection

Zooms in horizontally and vertically so that the current selection fills the waveform display.

Zoom to Selection (Horiz.)

Zooms in horizontally so that the current selection fills the waveform display.

Zoom to Event

Zooms in so that the waveform display shows the section of the clip corresponding to the edited audio event. This is not available if you have opened the **Sample Editor** from the **Pool**.

Zoom In Vertically

Zooms in one step vertically.

Zoom Out Vertically

Zooms out one step vertically.

Undo/Redo Zoom

Allows you to undo/redo the last zoom operation.

Range Editing

In the **Sample Editor** you can edit selection ranges. This option is useful if you want to quickly edit or process a specific section in the audio waveform, or if you want to create a new event or clip.

You can only select one range at a time. The selection is indicated in the **Selection** field on the **Info Line**.

The **Range** section in the **Inspector** contains functions for working with regions.

RELATED LINKS

[Range](#) on page 454

[Shared Copies](#) on page 199

Selecting a Range

PREREQUISITE

Snap to Zero Crossings is activated on the toolbar. This option ensures that the start and the end of the selection are always at zero crossings.

PROCEDURE

1. On the toolbar, activate the **Range Selection** tool.
2. Click at the position in the waveform display where you want the range to start and drag to the position, where you want the range to end.
3. Optional: Perform one of the following actions to resize the selection range:
 - Drag the left or the right edge of the selection to a new position.
 - Hold down **Shift** and click at a new position.

RESULT

The selected range is highlighted in the waveform display.

NOTE

You can also use the functions in the **Select** menu to select ranges.

RELATED LINKS

[Select Menu](#) on page 458

Select Menu

Select Menu in the Range Section

On the **Select** menu in the **Range** section in the **Sample Editor** Inspector, the following functions are available:

Select All

Selects the whole clip.

Select None

Deselects everything.

Select in Loop

Selects the audio between the left and the right locator.

Select Event

Selects only the audio that is included in the edited event. Cubase Pro only: If the **VariAudio** section is open and you segmented the audio, all segments that start or end within the event boundaries are selected.

Locators to Selection

Sets the locators to encompass the current selection. This option is available if you have selected one or several events or made a selection range.

Locate Selection

Moves the project cursor to the beginning or end of the current selection. This option is available if you have selected one or several events or made a selection range.

Loop Selection

Activates playback from the start of the selection and keeps starting over again at the selection end.

Select Menu on the Edit Menu

If you select **Edit > Select**, the following functions are available:

All

Selects the whole clip.

None

Deselects everything.

In Loop

Sets the audio between the left and the right locators.

From Start to Cursor

Selects the audio between the clips start and the project cursor.

From Cursor to End

Selects the audio between the project cursor and the end of the clip. This option is available if the project cursor is positioned between the clip boundaries.

Equal Pitch - all Octaves/same Octave (Cubase Pro only)

Selects all notes that have the same pitch as the selected note, in any octave or in the current octave. This option is available if the **VariAudio** section is open and the **Pitch & Warp** tool is activated.

Left Selection Side to Cursor

Moves the left side of the selection range to the project cursor position. This option is available if the project cursor is positioned between the clip boundaries.

Right Selection Side to Cursor

Moves the right side of the selection range to the project cursor position or the end of the clip if the project cursor is positioned to the right of the clip.

Creating Events from Selection Ranges

You can create a new event that contains only the selected range.

PROCEDURE

1. Select a range.
 2. Drag the selection range to an audio track in the **Project** window.
-

RELATED LINKS

[Selecting a Range](#) on page 457

Creating Clips from Selection Ranges

You can create a new clip that contains only the selected range.

PROCEDURE

1. Select a range.
 2. Right-click the selected range and select **Audio > Bounce Selection**.
 3. Perform one of the following actions:
 - Click **Replace** if you want to replace the original.
 - Click **No** if you want to keep the original.
-

RESULT

A new **Sample Editor** window opens with the new clip. It refers to the same audio file as the original clip, but it contains the audio corresponding to the selection range only.

Creating Sampler Tracks from Selection Ranges

You can create a sampler track that contains only the selected range.

PROCEDURE

1. Select a range.
If you select no range, the event Start/End is used.
 2. Open the **Range** inspector tab.
 3. Click **Create Sampler Track** .
-

RESULT

A new **Sampler Track** is created and added to the track list. The new sampler track contains your range selection.

Edit Functions for Ranges

You can edit selection ranges.

- To edit a selection range, open the **Process** section in the **Sample Editor** Inspector, and select one of the **Edit** menu functions.

NOTE

If you edit ranges of events that are shared copies, you are asked whether you want to create a new version of the clip. Select **New Version** if you want to edit the event, select **Continue** if all shared copies should be edited.

The following options are available:

Cut

Cuts the selected range from the clip and saves it in the clipboard. The section to the right of the range is moved to the left to fill the gap.

Copy

Copies the selected range to the clipboard.

Paste

Replaces the selected range with the data from the clipboard.

Delete

Removes the selected range from the clip. The section to the right of the range is moved to the left to fill the gap.

Insert Silence

Inserts a silent section with the same length as the current range selection at the selection start. The selected range is not replaced, but moved to the right.

Event or Range as Region

Creates a region from the selected range.

Make Direct Offline Processing Permanent

Allows you to apply all offline processing permanently to the audio.

RELATED LINKS

[Shared Copies](#) on page 199

[Applying Offline Processing Permanently](#) on page 424

Direct Offline Processing for Ranges

You can apply plug-in effects (Cubase Pro only) and audio processes to selection ranges.

- To apply a plug-in effect or an audio process to a selection range, open the **Process** section in the **Sample Editor**, and select one of the functions in the **Add Plug-in** (Cubase Pro only) menu or in the **Add Process** menu.

NOTE

If you apply offline processing to ranges of events that are shared copies, you are asked whether you want to create a new version of the clip. Select **New Version** if you want to edit the event, select **Continue** if all shared copies should be edited.

RELATED LINKS

[Direct Offline Processing](#) on page 416


[Applying Processing](#) on page 420

[Shared Copies](#) on page 199

Regions List

Regions are sections within an audio clip that allow you to mark important sections in the audio. You can add and edit regions for the selected audio clip in the regions zone.

- To show or hide the **Regions**, click **Set up Window Layout** on the toolbar and activate or deactivate **Regions**.



The following controls are available:

- Region Start/Region End**
Shows the start and end of the region in the audio waveform.
- Add Region**
Allows you to create a region of the current range selection.
- Remove Region**
Allows you to remove the selected region.
- Select Region**
If you select a region in the list and click this button above, the corresponding section of the audio clip is selected (as if you had selected it with the **Range Selection** tool) and zoomed. This is useful if you want to apply processing to the region only.
- Play Region**
Plays back the selected region.
- Regions list**
Allows you to select and display regions in the audio waveform.

Creating Regions

PREREQUISITE

You have clicked **Set up Window Layout** on the toolbar and activated the **Regions** option.

PROCEDURE

1. On the **Sample Editor** toolbar, activate the **Range Selection** tool and in the waveform display, select the range that you want to convert into a region.
 2. Perform one of the following actions:
 - Above the regions list, click **Add Region**.
 - Select **Audio > Advanced > Event or Range as Region**.A region is created, corresponding to the selected range.
 3. Optional: Double-click the region name in the list and enter a new name.
-

RESULT

The region is added to the regions list.

AFTER COMPLETING THIS TASK

Click the region in the regions list to instantly display it in the **Sample Editor**.

RELATED LINKS

[Creating Regions](#) on page 471

Creating Regions from Hitpoints

You can create regions from hitpoints. This is useful to isolate specific sounds.

PREREQUISITE

The audio event from which you want to create regions is opened in the **Sample Editor** and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Regions**.
-

RESULT

Regions are created between two hitpoint positions and shown in the **Sample Editor**.

Adjusting Start and End Positions of Regions

PREREQUISITE

You have clicked **Set up Window Layout** on the toolbar and activated the **Regions** option. You have created regions.

PROCEDURE

- Perform one of the following actions:
 - Drag the **Region Start** or **Region End** handle in the waveform display.
 - Double-click the **Start** or **End** field in the regions list and enter a new value.

NOTE

The positions are shown in the display format selected for the ruler and info line, but are relative to the start of the audio clip.

Removing Regions

PREREQUISITE

You have clicked **Set up Window Layout** on the toolbar and activated the **Regions** option. You have created regions.

PROCEDURE

1. In the regions list, select the region that you want to remove.
 2. Above the regions list, click **Remove Region**.
-

RESULT

The region is removed from the regions list.

Creating Audio Events from Regions

You can create new audio events from regions using drag and drop.

PREREQUISITE

You have clicked **Set up Window Layout** on the toolbar and activated the **Regions** option. You have created regions.

PROCEDURE

1. Select the region in the regions list.
 2. Drag the region to the desired position in the **Project** window.
-

RESULT

An event is created from the region.


Snap Point

The snap point is a marker within an audio event that can be used as a reference position.

- To show the snap point, activate **Show Audio Event** on the toolbar.



The snap point is set at the audio event start. But you can move it to another relevant position in the audio.



The snap point is used when **Snap** is activated on the **Project** window toolbar and you insert a clip from the **Sample Editor** in the event display. It is also used when you move or copy events in the event display.

In the **Sample Editor**, you can edit the following snap points:

- Event Snap Point
This is shown in the **Sample Editor** if you open a clip from within the **Project** window.
- Clip Snap point
This is shown in the **Sample Editor** if you open a clip from the **Pool**.

NOTE

The clip snap point serves as a template for the event snap point. However, it is the event snap point that is taken into account when snapping.

IMPORTANT

When you set the grid start in the **Definition** section, the snap point is moved to the grid start.

Adjusting the Snap Point

PREREQUISITE

The audio event is opened in the **Sample Editor** and **Show Audio Event** is activated on the toolbar.

PROCEDURE

1. Optional: On the **Sample Editor** toolbar, select the **Scrub** tool.
This allows you to audition the audio while setting the snap point.
 2. Move the mouse pointer over the snap point, and drag it to the desired position in the audio event.
The mouse pointer becomes a hand symbol and a tooltip indicates that you can set the snap point.
-

RESULT

The event snap point is adjusted to the position where you dragged it.



NOTE

You can also adjust the snap point by setting the project cursor at the desired position and selecting **Audio > Snap Point To Cursor**.

Hitpoints

Hitpoints mark musically relevant positions in audio files. Cubase can detect these positions and create hitpoints automatically by analyzing onsets and melodic changes of the audio.

NOTE

All hitpoint operations can be performed in the **Sample Editor** window and in the lower zone editor.

When you add an audio file to your project by recording or by importing, Cubase automatically detects hitpoints. In the **Project** window, hitpoints are shown for the selected event, provided that the zoom factor is high enough.

The hitpoint functions are available in the **Hitpoints** section of the **Sample Editor**.

You can use hitpoints for the following purposes:

- Create slices of the audio
Slices allow you to change tempo and timing of the audio without affecting its pitch and quality, or to replace or extract individual sounds from loops.
- Quantize audio
- Extract the groove from the audio
The timing is extracted from the audio and a groove map is created. You can use this groove map to quantize other events.
- Create markers from the audio
- Create regions from the audio
- Create events from the audio
- Create warp markers from the audio
- Create MIDI notes from the audio

NOTE

Hitpoints work best with drums, rhythmic recordings, or loops.

Calculating Hitpoints

When you add an audio file to your project by recording or by importing, Cubase automatically detects hitpoints.

PROCEDURE

1. Import or record an audio file.
Cubase automatically detects hitpoints.

NOTE

If your audio file is very long, this may take a while.

2. Select the audio event in the **Project** window and make sure the zoom factor is high enough.

RESULT

The calculated hitpoints for the selected event are shown in the **Project** window.


NOTE

You can disable automatic hitpoint detection by deactivating **Enable Automatic Hitpoint Detection** in the **Preferences** dialog (**Editing—Audio** page).

Hitpoint Filters

Cubase automatically detects and filters hitpoints. However, you can filter hitpoints manually if the result does not meet your expectations.

- To filter hitpoints, open the audio event in the **Sample Editor** and open the **Hitpoints** section.



Threshold

Filters hitpoints by their peaks. This option allows you to discard hitpoints of quieter crosstalk signals, for example.

Minimum Length

Filters hitpoints by their distance between two hitpoints. This option allows you to avoid creating slices that are too short.

Beats

Filters hitpoints by their musical position. This option allows you to discard hitpoints that do not fit within a certain range of a defined beat value.

Editing Hitpoints Manually


It is absolutely crucial for any further editing that the hitpoints are set at the correct positions. Therefore, if the automatic hitpoint detection does not meet your expectations, you can edit hitpoints manually.

PREREQUISITE


The audio event is opened in the **Sample Editor** and in the **Hitpoints** section hitpoints are filtered by their peaks, by their distance, or by their musical position.

PROCEDURE


1. In the **Hitpoints** section, activate the **Edit Hitpoints** tool.



2. Move the mouse to the waveform display and click between two hitpoints. The mouse pointer changes to a speaker icon and the tooltip **Play back Slice** is shown. The slice is played back from the beginning to the end.



3. To disable a hitpoint that you do not need, press **Shift** and click on the line that represents the hitpoint. The mouse pointer changes to a cross icon and the tooltip **Disable Hitpoint** is shown. Disabled hitpoints are not taken into account for further operations.



4. Press **Tab** to navigate to the next slice.
5. To insert a hitpoint, press **Alt** and click at the position where you want to insert the hitpoint. The mouse pointer changes to a draw icon and the tooltip **Insert Hitpoint** is shown.
6. To move a hitpoint, move the mouse pointer on the vertical line that represents the hitpoint, and drag to the left or to the right. The mouse pointer changes to a double arrow and the tooltip **Move Hitpoint** is shown. Moved hitpoints are locked by default.
7. To make sure that a hitpoint is not accidentally filtered out, lock it by pointing at it and clicking. The tooltip **Lock Hitpoint** is shown.

RESULT

The hitpoints are edited according to your settings.

NOTE

To reset a hitpoint to its original state, press **Ctrl/Cmd-Alt** until the tooltip **Enable/Unlock Hitpoints** is shown and click.

RELATED LINKS

[Hitpoint Filters](#) on page 466

Locating to Hitpoints in the Project Window

You can navigate through the hitpoints of an audio event in the **Project** window.

PREREQUISITE

Enable Automatic Hitpoint Detection is activated in the **Preferences** dialog (**Editing—Audio** page).

PROCEDURE

1. Select the audio track that contains the audio event for which you want to locate hitpoints.
2. Perform one of the following actions:
 - Press **Alt-N** to navigate to the next hitpoint.
 - Press **Alt-B** to navigate to the previous hitpoint.

RESULT

The project cursor jumps to the respective hitpoint.

Slices

You can create slices from hitpoints, where each slice ideally represents an individual sound or beat of the audio.

You can use these slices to change tempo and timing of the audio without affecting its pitch and quality.

NOTE

Slices are created in the **Sample Editor** and edited in the **Audio Part Editor**.

Audio that meets the following characteristics is suitable:

- Individual sounds have a noticeable attack.
- The recording quality is good.
- The recording is free of crosstalk signals.
- The audio is free of smearing effects like delays, for example.

Slicing Audio

Slicing audio is useful if you want to change tempo and timing of the audio without affecting its pitch and quality.

PREREQUISITE

The audio event is opened in the **Sample Editor** and the hitpoints are set at the correct positions.

NOTE

When slicing audio, all events referring to the edited clip are also replaced.

PROCEDURE

- Perform one of the following actions:

- In the **Hitpoints** section, click **Create Slices**.
 - Select **Audio > Hitpoints > Create Audio Slices from Hitpoints**.
-

RESULT

The areas between the hitpoints are sliced and become separate events. The original audio event is replaced by an audio part containing the slices.



On playback, the audio plays back seamlessly at the project tempo.

AFTER COMPLETING THIS TASK

Change the project tempo. The slices are moved accordingly, keeping their relative positions within the part.

Double-click the sliced audio part and replace or extract individual slices in the **Audio Part Editor**.

RELATED LINKS

[Slices and the Project Tempo](#) on page 469

[Audio Part Editor](#) on page 503

Slicing Multi-Track Drum Recordings

You can slice all tracks of a multi-track drum recording at once.

PREREQUISITE

You have created a multi-track drum recording and set up an edit group for all the tracks.

PROCEDURE

- Select the folder track, and select **Audio > Hitpoints > Divide Audio Events at Hitpoints**.
-

RESULT

The audio of all tracks in the folder track is sliced.

RELATED LINKS

[Quantizing Multiple Audio Tracks \(Cubase Pro only\)](#) on page 267

[Group Editing Mode \(Cubase Pro only\)](#) on page 201

Slices and the Project Tempo

The project tempo affects how the sliced audio is played back.

NOTE

To ensure that the loop follows any further tempo changes, activate **Musical Mode**.

Project Tempo Is Slower Than the Original Audio

If the project tempo is slower than the tempo of the original audio event, there may be audible gaps between the slice events in the part. If this is the case, you have the following options:

- Select **Audio > Advanced > Close Gaps (Timestretch)**.
This applies time stretch to each slice and closes the gaps. Consider activating auto fades for the corresponding audio track. Fade-outs set to 10 ms help eliminate clicks.

- Select **Audio > Advanced > Close Gaps (Crossfade)**.
This applies crossfades to the slices and closes the gaps.

NOTE

If you decide to change the tempo again, undo your actions and use the original, unstretched file.

Project Tempo Is Higher Than the Original Audio

If the project tempo is higher than the tempo of the original audio event, the slice events in the part may overlap.

If this is the case, right-click the track in the track list and from the context menu, select **Auto Fades Settings** to smooth out the sound.

Furthermore, you can select the overlapping events in the part and select **Audio > Advanced > Delete Overlaps**.

RELATED LINKS

[Musical Mode](#) on page 475

[Making Global Auto Fade Settings](#) on page 287

[Making Auto Fade Settings for Individual Tracks](#) on page 287

Creating a Groove Quantize Map

You can use hitpoints to create a groove quantize map.

PREREQUISITE

The audio event from which you want to extract the timing is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Groove**.
-

RESULT

The groove is extracted from the audio event and automatically selected in the **Quantize Presets** pop-up menu on the **Project** window toolbar.

AFTER COMPLETING THIS TASK

Open the **Quantize Panel** and save the groove as a preset.

Creating Markers

You can create markers at hitpoint positions. This allows you to snap to hitpoint positions.

PREREQUISITE

The audio event from which you want to create markers is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Markers**.
-

RESULT

If your project has no marker track, a marker track is added and activated automatically, and a marker is created at every hitpoint position.

RELATED LINKS

[Markers](#) on page 307

Creating Regions

You can create regions at hitpoint positions. This allows you to isolate recorded sounds.

PREREQUISITE

The audio event from which you want to create regions is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Regions**.

RESULT

Regions are created between two hitpoint positions and shown in the **Sample Editor**.

RELATED LINKS

[Creating Regions](#) on page 461

Creating Events

You can create events at hitpoint positions.

PREREQUISITE

The audio event from which you want to create events is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Events**.

RESULT

Events are created between two hitpoint positions.

Creating Warp Markers

You can create warp markers at hitpoint positions. This allows you to quantize audio based on hitpoint positions.

PREREQUISITE

The audio event from which you want to create warp markers is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

- In the **Hitpoints** section, click **Create Warp Markers**.
-

RESULT

Warp markers are created at every hitpoint position.

AFTER COMPLETING THIS TASK

Open the **AudioWarp** section to show and edit the warp markers.

RELATED LINKS

[Tempo Matching Audio](#) on page 474

Creating MIDI Notes

You can export hitpoints to a MIDI part containing a MIDI note for each hitpoint. This allows you to double, replace, or enrich drum hits by triggering sounds of a VST instrument.

PREREQUISITE

The audio event from which you want to create MIDI notes is opened in the **Sample Editor**, and the hitpoints are set at the correct positions.

PROCEDURE

1. In the **Hitpoints** section, click **Create MIDI Notes**.
2. In the **Convert Hitpoints to MIDI Notes** dialog, set up the parameters.
3. Click **OK**.

RESULT


A MIDI track is added to your project, and MIDI notes are created at every hitpoint position.

AFTER COMPLETING THIS TASK

Assign a VST instrument to the MIDI track, and select a sound to enrich the audio.

Convert Hitpoints to MIDI Notes

When exporting hitpoints to MIDI notes, you can specify, how the hitpoints are converted.



The following options are available:

Velocity Mode

Allows you to select a velocity mode:

- If you want the velocity values of the created MIDI notes to vary according to the peak levels of the corresponding hitpoints, select **Dynamic Velocity Value**.
- If you want to assign the same velocity value to all created MIDI notes, select **Fixed Velocity Value**.

Velocity

Sets the **Fixed Velocity Value**.

Pitch

Sets a note pitch for all created MIDI notes.

Length

Sets a note length for all created MIDI notes.

Destination

Allows you to select a destination:

- To place the MIDI part on the first selected MIDI or instrument track, select **First Selected Track**.

NOTE

Any MIDI parts from previous conversions on this track will be deleted.

- To create a new MIDI track for the MIDI part, select **New MIDI Track**.
- To copy the MIDI part to the clipboard, select **Project Clipboard**.

Tempo Matching Audio

You can tempo match audio to adapt its tempo to the project tempo, for example.

NOTE

All tempo matching operations can be performed in the **Sample Editor** window and in the lower zone editor.

The following functions are described:


- **Stretch to Project Tempo**
Stretches the selected event to match the project tempo.
- **Musical Mode**
Applies realtime time stretching to audio clips, so that they match the project tempo.
- **Auto Adjust**
Extracts a definition grid from your audio. After that, you can match the audio with the project tempo by using **Musical Mode**.
- **Manual Adjust**
Allows you to manually modify the grid and tempo of your audio file. After that, you can match the audio with the project tempo by using **Musical Mode**.
- **Free Warp**
Allows you to change the timing of individual positions in your audio.

Algorithm Presets

You can select an algorithm preset that is applied for realtime playback and time stretching.

The **Algorithm** pop-up menu on the **Sample Editor** toolbar contains various presets that determine the audio quality of the realtime time stretching.

These presets are sorted into the categories **élastique** and **Standard** according to the technology used.



The algorithm preset affects warp changes in **Musical Mode**, **FreeWarp**, and **Swing**. Cubase Pro only: For the VariAudio warping and pitching features **Standard - Solo** is applied automatically.

RELATED LINKS

[Time Stretch and Pitch Shift Algorithms](#) on page 435

Stretching Audio Events to the Project Tempo

You can stretch audio loops to the project tempo.

PROCEDURE

1. Select **File > Import > Audio File**, select the audio loop that you want to import, and click **OK**.
 2. Select the audio loop in the project.
 3. Select **Audio > Advanced > Stretch to Project Tempo**.
-

RESULT

The audio loop is stretched to match the project tempo.

Musical Mode

The **Musical Mode** allows you to tempo-match audio loops to the project tempo.

If you activate **Musical Mode** for an audio clip, realtime time stretching is applied to the clip so that it matches the project tempo. The audio events adapt to any tempo changes in Cubase, just like MIDI events.

In the **Sample Editor**, you can activate **Musical Mode** in the **AudioWarp** section, the **Definition** section, and the toolbar.

NOTE


- You can also activate/deactivate **Musical Mode** from within the **Pool** by clicking the corresponding checkbox in the **Musical Mode** column.
 - Cubase supports ACID® loops. These loops are standard audio files but with embedded tempo/length information. When ACID® files are imported into Cubase, **Musical Mode** is automatically activated and the loops will adapt to the project tempo.
-

Matching Audio to the Project Tempo

You can use **Musical Mode** to adjust audio loops. Loops are short audio files containing a defined number of bars with straight beats, to the project tempo.

PROCEDURE

1. Select **File > Import > Audio File**, and select an audio loop in the file dialog.
2. In the **Project** window, double-click the imported audio loop to open it in the **Sample Editor**.
3. Open the **Definition** section and verify the rulers.
The project tempo grid shown in the upper ruler and the grid of your audio shown in the lower ruler do not match.



4. On the toolbar, verify that the length in bars corresponds to the length of the imported audio file. If necessary, listen to your audio and enter the correct length in bars and beats.
 5. On the toolbar, open the **Algorithm** pop-up menu, and select a preset.
 6. Listen to the loop and if necessary correct the **Bars** and **Beats** values on the toolbar.
 7. Activate **Musical Mode**.
-

RESULT

The loop is warped and stretched to the project tempo. The rulers reflect the change.

In the **Project** window, the audio event shows a note symbol and a warp symbol. This indicates that time stretching has been applied.

Applying Swing

The **Swing** function allows you to add swing to audio that sounds too straight.


PREREQUISITE

You have opened your audio in the **Sample Editor** and **Musical Mode** is activated.

PROCEDURE

1. On the toolbar, open the **Algorithm** pop-up menu, and select a preset.
2. Open the **AudioWarp** section, and from the **Resolution** pop-up menu select a grid resolution.

This defines the positions that the swing is applied to. If you select **1/2**, the swing is applied in steps of half notes, for example.



3. Move the **Swing** fader to the right.
-

RESULT

This offsets the grid positions and creates a swing or shuffle feel. If you selected **1/2**, every second position in the grid is offset.

Auto Adjust

The **Auto Adjust** function is useful if you do not know the tempo of your audio file, or if its beat is not straight. It allows you to extract a definition grid from your audio before tempo matching it to the project tempo with the **Musical Mode**.

The **Auto Adjust** function extracts a local definition grid that you can match with the project tempo using **Musical Mode**.

RELATED LINKS

[Musical Mode](#) on page 475

Extracting a Tempo Definition Grid from Audio

If you want to match audio with an unknown tempo or a beat that is not straight to the project tempo, you need to extract its tempo definition grid first. This is done with the **Auto Adjust** function in the **Definition** section of the **Sample Editor**.

PREREQUISITE

You have defined a range in your audio clip or event that starts and ends at a barline.

PROCEDURE

1. Double-click the audio clip or event in the **Project** window to open it in the **Sample Editor**.
2. Open the **Definition** section, and select a value from the **Grid** pop-up menu. This determines the grid resolution for your audio.
3. With the **Range Selection** tool, select the section that you want to use in your project, and that covers one or several bars.

NOTE

If you do not select a range, the grid is calculated for the audio event. If no audio event is defined, the grid is calculated for the clip. Make sure that the event or clip starts and ends on a barline.

-
4. Click **Auto Adjust**.
-

RESULT

The definition grid is calculated for the selected section. The snap point moves to the start of the selected range. The audio tempo definition ruler changes to reflect your edits, and bars and beats positions are marked with vertical lines.

Manual Adjust

The **Manual Adjust** function is useful if you need to manually modify the grid and tempo of your audio file. This is the case if the extraction of a definition grid with the **Auto Adjust** function did not bring satisfying results, for example.

The **Manual Adjust** function allows you to correct the local definition grid. After this, you can match it with the project tempo using **Musical Mode**.

RELATED LINKS


[Musical Mode](#) on page 475

Correcting the Audio Definition Grid


If the extraction of a definition grid with the **Auto Adjust** function did not bring satisfying results, you can correct the grid and tempo of your audio file with the **Manual Adjust** function.

PROCEDURE

1. Double-click the audio clip or event in the **Project** window to open it in the **Sample Editor**.
2. Open the **Definition** section, and activate **Manual Adjust**.
3. Move the mouse pointer to the beginning of the audio clip.
The tooltip **Set Grid Start** is shown, and the mouse pointer turns into a double arrow.



4. Click and drag to the right until the first downbeat and release the mouse button.
This matches the grid start and the snap point with the first main beat. The audio tempo definition ruler changes to reflect your edits.
5. In the upper part of the waveform, move the mouse pointer to the vertical line nearest to the second bar.
The tooltip **Stretch Grid** and a blue vertical line are shown.
6. Click and drag to the position of the first downbeat in the second bar and release the mouse button.
This sets the beginning of the next bar. All following bar positions in the grid are stretched or compressed so that all bars have the same length.



7. In the lower part of the waveform, move the mouse pointer over the grid lines.
The tooltip **Set Bar Position (Move Following Bars)** and a green vertical line are shown.
8. For incorrect bar positions, click and drag the green vertical line to the position of the first downbeat of the following bar and release the mouse button.
This also moves the bars to the right. The area to the left remains unaffected.



9. Move the mouse pointer over the grid lines for single beats.
The tooltip **Set Beat Position** and a blue vertical line are shown.
10. Click and drag the grid line to align single, incorrect beat positions and release the mouse button.



NOTE

You can remove misplaced beat edits by pressing any modifier key and clicking with the **Erase** tool.



RESULT

The definition grid is corrected, the audio tempo definition ruler reflects your edits.

AFTER COMPLETING THIS TASK

Activate **Musical Mode**.

Free Warp

The **Free Warp** tool allows you to correct the timing of individual positions in the audio material.

You can create and edit warp markers and drag them to musically relevant time positions in an audio event. This way, the audio before and after the warp marker is stretched. The amount of stretch is shown next to the warp marker handle.



A stretch factor higher than 1.0 indicates that the audio preceding the warp marker is stretched, a stretch factor lower than 1.0 indicates that the audio is compressed.

NOTE

The **Free Warp** tool snaps to hitpoint positions and warp markers.

Correcting the Timing with the Free Warp Tool

PROCEDURE

1. Double-click the audio clip or event in the **Project** window to open it in the **Sample Editor**.
 2. On the toolbar, activate **Snap to Zero Crossing**.
If this button is activated, warp markers snap to zero crossings.
 3. Optional: If you want to correct the timing of individual positions in the audio, define the local definition with the **Auto Adjust** or the **Manual Adjust** function, and activate **Musical Mode**.
 4. On the **Transport** panel, activate **Click**, and play back the audio to determine positions where the beat is not on time with the click.
 5. In the **AudioWarp** section, activate **Free Warp**, place the mouse pointer at the position of the beat that you want to adjust, click, and hold.
The mouse pointer changes to a clock with arrows, and a warp marker is inserted.
 6. Drag the warp marker to the new position, and release the mouse button.
-

RESULT

The beat is now aligned with the corresponding position in the project.

RELATED LINKS

[Auto Adjust](#) on page 477


[Manual Adjust](#) on page 477

[Musical Mode](#) on page 475

Correcting Warp Marker Positions

PROCEDURE

1. In the **AudioWarp** section, activate **Free Warp**.
2. In the **Sample Editor**, click the warp marker handle and drag it to a new position.



A tooltip is shown to indicate that you can drag to correct the warp marker position.

RESULT

The warp marker moves to the new position and the audio is stretched or compressed accordingly.

Deleting Warp Markers

PROCEDURE

1. In the **AudioWarp** section, activate **Free Warp**.
2. Hold down **Alt** and click the warp marker you want to delete.

NOTE

To delete several markers, draw a selection rectangle.

RESULT

The warp marker is removed from the waveform.

Resetting Warp Markers

PROCEDURE

- In the **AudioWarp** section, click **Reset Warp Changes**.
-

RESULT

The warp markers are removed from the waveform, and the warp edits of the waveform are reset.

NOTE


If **Musical Mode** is activated, only **Free Warp** edits are reset.

Flattening Realtime Processing

You can flatten warp modifications. This is useful if you want to reduce the CPU load, optimize the sound quality of the processing, or apply any offline processing.

PROCEDURE

1. Select the audio events that you want to process.
2. Perform one of the following actions:
 - Select **Audio > Realtime Processing > Flatten Realtime Processing**.
 - In the **Process** section of the **Sample Editor**, click **Flatten**.



In the dialog that opens, you can select an algorithm preset. If the time stretching factor is not outside the range of 0.5 and 2, you can choose between **Realtime** and **MPEX**.

3. Select an algorithm preset and click **OK**.
-

RESULT

Any loop that was previously stretched in realtime plays back exactly the same, but the warp markers discarded.

RELATED LINKS

[MPEX](#) on page 436

Unstretching Audio Files

PREREQUISITE

You have stretched an audio event in the **Sample Editor** with the **Free Warp** tool, or in the **Project** window with the **Object Selection** tool in **Sizing Applies Timestretch** mode.

PROCEDURE

1. Select the audio event that you want to unstretch.
 2. Select **Audio > Realtime Processing > Unstretch Audio**.
-

RESULT

All realtime time stretching is removed.

VariAudio (Cubase Pro only)

The VariAudio features in Cubase allow you to edit pitch, correct timing and intonation of individual notes in monophonic vocal recordings. Any modifications to the audio material can be undone.

NOTE

All VariAudio operations can be performed in the **Sample Editor** window and in the lower zone editor.

NOTE

The VariAudio features are optimized for monophonic recordings of vocals. Other monophonic recordings, such as saxophone, may work well. However, the quality of the result depends greatly on the recording.

Before you can edit the pitch and correct the timing of monophonic recordings, Cubase must analyze the audio and split it into segments. These segments are graphic representations of the notes sung.

As the quality of the segmentation is crucial for any further editing, we recommend you to verify the automatic segmentation and to edit it if necessary.

NOTE

- Due to the data gained during segmentation, the audio and thus the size of your project can increase.
- If you load projects with VariAudio files in Cubase Artist, VariAudio modifications are ignored. If you want to hear your modifications in Cubase Artist, you will have to bounce the audio files that have been edited with the Cubase VariAudio features.

RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484

[Manual Editing of Segments](#) on page 485

[Segments and Gaps](#) on page 485

VariAudio and Offline Processes

If you apply offline processes and edits that affect the length on audio files that contain VariAudio data, existing VariAudio data becomes invalid. We therefore recommend to apply offline processing or edits before using the VariAudio features.

The following processes and edits may lead to the reanalysis of the audio material:

- All offline processes in the **Process** submenu of the **Audio** menu, except **Envelope**, **Fade In Fade Out**, **Normalize**, and **Silence**.
- Effect processes in the submenu **Audio > Plug-ins**.

- Cutting, pasting, deleting or drawing in the **Sample Editor**.

Segmenting Monophonic Audio

To be able to edit the pitch and correct the timing of monophonic recordings, Cubase must analyze the audio and split it into segments.


PROCEDURE

1. In the **Project** window, double-click the monophonic vocal recording to open the **Sample Editor**.
2. In the **Sample Editor** Inspector, click **VariAudio** to open the **VariAudio** section. A waveform image of the audio is shown.
3. Activate the **Segments** tool.



RESULT

Cubase automatically analyzes the audio and splits it into segments that are shown in the waveform image. The segmentation allows you to associate the audio with the sung notes.



NOTE

The analysis of long audio files may take some time.

AFTER COMPLETING THIS TASK

Verify the automatic segmentation and edit it manually.


RELATED LINKS

[Segments and Gaps](#) on page 485

[Manual Editing of Segments](#) on page 485

Segments and Gaps

Cubase automatically analyzes the audio and splits it into segments that are shown in the waveform image.



To understand and edit the segmentation, the following concepts are crucial:

1 Pitch Position

The pitch position of the segments is indicated by the piano keyboard to the left of the waveform. Pitches represent the perceived fundamental frequency of the sound. The average pitch of a segment is calculated from its micro-pitch curve.

2 Time Position

The time position and the length of the segments are indicated by the timeline.

3 Audio Waveform

The audio waveform is always shown as mono, even if you have opened a stereo or multi-channel file.

4 Segment

The segments represent the tonal portions of the analyzed audio. The pitch and time position of the segments allow you to associate the segments to the original audio.

5 Gap

The gaps in between segments represent the non-tonal portions of the analyzed audio. These can be caused by breath sounds or rests, for example.

NOTE

Gaps, caused by weak audio signals or audio sections with unclear pitch information, such as consonants or effect sounds, must be included in the segments manually. Otherwise, later pitch modifications affect only the tonal portions.

6 Micro-Pitch Curves

The micro-pitch curves that are shown in the segments represent the progression of the pitch.

Manual Editing of Segments

As the quality of the segmentation is crucial for any further editing, we recommend you to verify the automatic segmentation and to edit it if necessary.

Verify the start and end positions of the segments and try to match them with the waveform envelope for each word. You have the following possibilities to edit segments:

- Changing the start and end points of segments by resizing segments.
- Changing the length of segments by cutting or glueing segments.

- Moving segments on the timeline by dragging them to the left or right.
- Deleting segments.

Navigating and Zooming

You can navigate through the segments and zoom in on them. This makes manual editing more comfortable.


- To navigate through the segments, use the **Left Arrow** key or the **Right Arrow** key on your computer keyboard.
- To zoom in on segments, hold down **Alt** and draw a selection rectangle.
- To zoom out, hold down **Alt** and click in an empty area of the waveform.
- To zoom out to show all segments, hold down **Alt** and double-click in an empty area of the waveform.

Auditioning Segments

You can audition the segments one by one, loop them, or play them back from the beginning to the end. This makes segmentation as well as pitch and warp editing more comfortable.

To audition segments use one of the following methods:


- To play back selected segments, select the segments and activate **Audition**.



- To play back selected segments in a loop, select the segments, activate **Audition Loop**, and activate **Audition**.



- To play back segments at a specific position, activate the **Play** tool, click at the position.




- To audition pitch modifications while editing, activate **Acoustic Pitch Feedback**.



- To compare your pitch changes to the original audio pitches, activate **Disable Pitch Changes** in the **VariAudio** section.



- To compare your warp changes to the original timing of the audio, activate **Disable Warp Changes** in the **AudioWarp** section.



Changing the Start and End Point of Segments

If the start and end points of the segments do not match with the waveform envelope, you can change them.

PREREQUISITE

You have opened the audio in the **Sample Editor** and activated the **Segments** tool in the **VariAudio** section.

PROCEDURE

1. Compare the start and end positions of the segments with the waveform envelope for each note.
2. Optional: Select one or several segments and on the **Sample Editor** toolbar, activate **Audition** to audition the segments.
3. Perform one of the following actions:
 - If a segment starts too early, move the mouse pointer over the start of the segment, click and drag to the right.



- If a segment ends too late, move the mouse pointer over the end of the segment, click and drag to the left.



NOTE

You can only drag the segment start or end until the boundaries of the next segment. Segments cannot overlap.

RESULT

The start and end positions of the segments are changed according to your edits. The average pitch of the segment is recalculated.

NOTE

Changing the length of a segment may lead to a different average pitch and therefore to a pitch change. If the non-tonal portions of the audio increase, the segment may be deleted.

RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484

Changing the Length of Segments

If a segment includes more than a note, or if a single note is spread over multiple segments, you can change them.

PREREQUISITE

You have opened the audio in the **Sample Editor** and activated the **Segments** tool in the **VariAudio** section.

PROCEDURE

1. Compare the segments with the waveform envelope for each note.

- Optional: Select one or several segments and on the Sample Editor toolbar, activate the **Audition** to audition the segments.
- Perform one of the following actions:
 - If a segment includes more than a note, move the mouse pointer over the lower border of the segment and click to cut the segment.



- If a single note is spread over several segments, hold down **Alt** and move the mouse pointer over the segment, and click to glue the segment to the next segment.



NOTE

If the segment is already very short, it cannot be cut.

RESULT

The segments are changed according to your edits. The average pitch of the segment is recalculated.

NOTE

Changing the length of a segment may lead to a different average pitch and therefore to a pitch change. If the non-tonal portions of the audio increase, the segment may be deleted.

AFTER COMPLETING THIS TASK

If a note is at the wrong position after cutting the segment, move it horizontally.

RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484

[Moving Segments on the Timeline](#) on page 488

Moving Segments on the Timeline

If a note is at the wrong position after cutting the segment, you can move it horizontally.

PREREQUISITE

You have opened the audio in the **Sample Editor** and activated the **Segments** tool in the **VariAudio** section.

PROCEDURE

- Compare the segments with the waveform envelope for each note.
- Optional: Select one or several segments and on the **Sample Editor** toolbar, activate the **Audition** to audition the segments.
- Move the mouse pointer over the upper border of the segment, click and drag to the left or to the right.



NOTE

You can only move the segment until the boundaries of the next segment. Segments cannot overlap.

RESULT

The segment is moved. The average pitch of the segment is recalculated.

NOTE

Changing the length of a segment may lead to different average pitch and therefore to a pitch change. If the non-tonal portions of the audio increase, the segment may be deleted.

RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484

Deleting Segments

Sometimes it might be useful to delete segments, for example for non-tonal portions of the audio.

PREREQUISITE

You have opened the audio in the **Sample Editor** and activated the **Segments** tool in the **VariAudio** section.

PROCEDURE

1. Compare the segments with the waveform envelope for each note.
 2. Optional: Select one or several segments and on the **Sample Editor** toolbar, activate the **Audition** to audition the segments.
 3. Select the segment that you want to delete, and press **Backspace**.
-

RESULT

The segment is deleted.

RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484

Muting Segments


You can mute individual segments.

PREREQUISITE

You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

1. Move the mouse pointer over the lower border of a segment. An x symbol is shown in the segment.



2. Click the x symbol.
-

RESULT


The segment is grayed out to indicate that it is muted.

AFTER COMPLETING THIS TASK

You can unmute the segment by clicking the x symbol again.

Segment Colors

You can select a color scheme for VariAudio segments. If you work with several audio events, this makes it easier to see which segments belong to which event.



The following options are available:

Auto

Segments that belong to the same audio event get the same color.

Event

Segments get the same color as the corresponding event in the **Project** window.

Pitch

Segments get colors depending on their pitches.

Chord Track

Segments that match the corresponding chord or scale events on the chord track get a specific color.

Pitch Changes

The VariAudio features allow you to change the pitch of audio segments for corrective purposes but also creatively. By changing note pitches you can change the melody of the original audio with or without preserving a natural sound.

Pitch changes include the following:

- Raising or lowering pitches.
- Quantizing pitches.

- Changing the micro-pitch curve.
- Straightening pitches.

Pitch Snapping

There are 3 different modes that affect the way in which a note will snap to a certain pitch.

- **Absolute Pitch Snapping**
To snap the segment to the next semitone, hold down **Ctrl/Cmd**.
- **Relative Pitch Snapping**
To snap the segment and keep its current deviation in cents, just drag.
- **No Pitch Snapping**
To edit the pitch freely, hold down **Shift**.

NOTE

You can change the modifier in the **Preferences** dialog (**Editing—Tool Modifier** page).

Raising or Lowering Pitches

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

1. Select one or several segments, and move the mouse pointer over it.
The mouse pointer becomes a hand symbol.
2. Perform one of the following actions to raise or lower the pitch:
 - Drag the segment up or down and release the mouse.
 - Use the **Up Arrow/Down Arrow** to change the pitch in semitone steps.
 - Hold down **Shift** and use **Up Arrow/Down Arrow** to change the pitch in cent steps.

NOTE

The more the pitch deviates from the original pitch, the less likely it is that your audio sounds natural. You cannot choose note pitches above C5 and below E0.

RESULT

The **Solo** algorithm is selected automatically and the segment pitch is raised or lowered according to your settings.

Changing Pitches by MIDI Input

You can change segment pitches by pressing a key on your MIDI keyboard or by using the **On-Screen Keyboard**.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section. You have connected and set up a MIDI keyboard.

PROCEDURE

1. Select one or several segments.
2. In the **VariAudio** section, activate **MIDI Input**.



3. Perform one of the following actions to change the pitch:
 - Press a key on your MIDI keyboard.
 - Use the **On-Screen Keyboard** to change the pitch.

NOTE

The more the pitch deviates from the original pitch, the less likely it is that your audio sounds natural. You cannot choose note pitches above C5 and below E0.

RESULT

The **Solo** algorithm is selected automatically, and the segment pitch is raised or lowered according to the note you play. If you select several segments, the pitch of the first selected segment is changed to the pitch of the MIDI note you play and the pitches of the other segments are changed by the same amount.

NOTE

The **MIDI Input** only affects the pitches of the segments. MIDI controller data are ignored.

AFTER COMPLETING THIS TASK

Deactivate **MIDI Input**.

RELATED LINKS

[On-Screen Keyboard](#) on page 234

MIDI Input Modes

The **MIDI Input** function allows you to assign MIDI notes in **Still** mode or in **Step** mode.

- To switch between **Still** mode and **Step** mode, **Alt-click MIDI Input**.

Still mode



Use this mode if you want to change the pitches of individual segments or selections.

Step mode



Use this mode if you want to step through the segments while changing their pitches. This allows you to work in a more creative way, for example, to develop completely new melody lines via MIDI.

After you have assigned a MIDI note to a segment, the next segment is automatically selected.

RELATED LINKS

[Step Input](#) on page 727

Quantizing Pitches

You can quantize the audio pitch to the nearest semitone position.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

1. Select one or several segments.
2. In the **VariAudio** section, move the **Quantize Pitch** slider to the right.



RESULT

The **Solo** algorithm is selected automatically, and the segment pitch is quantized iteratively.

NOTE

In the **Sample Editor** category of the **Key Commands** dialog, you can set up a key command for **Quantize Pitch**. If you use the key command, the segments are immediately quantized to the next semitone position.

RELATED LINKS

[Key Commands](#) on page 973

Micro-Pitch Changes

Sometimes changing the pitch of the whole note segment is not enough. In these cases, you can modify the micro-pitch curves inside the segments.

IMPORTANT

The micro-pitch curve displays the progression of the pitch for the tonal portion of the audio segment. For non-tonal portions of the audio, micro-pitch curves cannot be shown.

You have the following options to change the micro-pitch curve:

- Tilting an entire micro-pitch curve.
- Tilting a micro-pitch curve from a segment border to an anchor.
This is useful if you want to adjust only the start or the end of a segment.


Tilting an Entire Micro-Pitch Curve

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

1. Move the mouse pointer over the upper left or right border of the segment.
The mouse pointer becomes an up/down arrow.
2. To tilt the micro-pitch curve, drag the curve up or down, and release the mouse.



RESULT

The **Solo** algorithm is selected automatically, and the micro-pitch curve is tilted according to your settings.

Tilting a Micro-Pitch Curve from a Segment Border to an Anchor

You can set an anchor point to specify which part of the segment is affected when tilting a micro-pitch curve.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE


1. Move the mouse pointer over the upper border of the segment.
The mouse pointer becomes an I-beam symbol.
2. Click at the position where you want to set an anchor point.
A vertical line appears at the position where you clicked.



3. Move the mouse pointer over the upper left or right border of the segment.
The mouse pointer becomes an up/down arrow.
4. To tilt the micro-pitch curve, drag the curve up or down, and release the mouse.

RESULT

The **Solo** algorithm is selected automatically, and the micro-pitch curve is tilted from the segment border to the anchor.



RELATED LINKS


[Removing Anchors](#) on page 495

[Rotating a Micro-Pitch Curve around an Anchor](#) on page 495

Removing Anchors

PROCEDURE

1. Hold down **Alt** and move the mouse pointer over the position of the anchor at the upper border of the segment.
The mouse pointer becomes a glue tube.
2. Click at the position of the anchor point.



RESULT

The tilt anchor is removed.


Rotating a Micro-Pitch Curve around an Anchor

PREREQUISITE


The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

1. Move the mouse pointer over the upper border of the segment.
The mouse pointer becomes an I-beam symbol.
2. Click at the position where you want to set an anchor point.
A vertical line appears at the position where you clicked.




3. Move the mouse pointer over the upper left or right border of the segment.
The mouse pointer becomes an up/down arrow.
4. To rotate the micro-pitch curve, press **Alt** drag the curve up or down, and release the mouse.



RESULT

The **Solo** algorithm is selected automatically, and the micro-pitch curve is rotated around the anchor.



RELATED LINKS

[Removing Anchors](#) on page 495

[Tilting a Micro-Pitch Curve from a Segment Border to an Anchor](#) on page 494

Straightening Micro-Pitch Curves

You can straighten micro-pitch curves to compensate for the rise and fall of notes, that is, the deviation from a representative pitch.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.


PROCEDURE

1. Select one or several segments.
2. In the **VariAudio** section, move the **Straighten Pitch** slider to the right.



RESULT

The **Solo** algorithm is selected automatically, and the micro-pitch curves of the selected segments are straightened according to your settings.



Timing Modifications

Modifying the timing of segments, or warping, is useful if you want to align a musical accent to a certain time position or change the timing of segments in monophonic vocal recordings.

If you warp audio segments, warp markers are created. These are shown in the **VariAudio** and the **AudioWarp** sections of the **Sample Editor** Inspector.

Warping Segments

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section. **Snap** is activated.

PROCEDURE

1. Move the mouse pointer over the start or end of a segment.
The mouse pointer becomes a double arrow and warp markers are displayed below the ruler.
 2. Drag the start or end of the segment to the desired time position.
-

RESULT

The **Solo** algorithm is selected automatically. If **Snap** is activated, the segment border snaps to the grid. The timing of the segment and the adjacent segments is changed according to your settings. Warp markers are shown to indicate which portions of the audio are stretched.

NOTE

Timing modifications introduced this way do not adapt to the project tempo. If this is what you want, use **Musical Mode**.

Editing Warp Markers

You can change the insert position of a warp marker in the audio. This is useful if the beginning of the waveform does not correspond to the beginning of a segment because the audio starts with non-tonal portions like breath sounds, for example.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section. **Snap** is activated.

PROCEDURE

1. Move the mouse pointer over the start of the segment and drag to the beginning of the bar.
The mouse pointer becomes a double arrow and segment border snaps to the grid at the exact bar position.



2. Move the mouse pointer over the warp handle and drag it to the beginning of the waveform.



The mouse pointer becomes a double arrow and the background is highlighted to indicate which part of the waveform is affected by the change.

RESULT

Now the beginning of the waveform matches the beginning of the bar.



Deleting Warp Markers

You can delete warp markers.

PREREQUISITE

The audio file is segmented and the segments are correct. You have opened the audio in the **Sample Editor** and activated the **Pitch & Warp** tool in the **VariAudio** section.

PROCEDURE

- Hold down **Shift**, move the mouse pointer over the warp handle and click.
The mouse pointer becomes an eraser.
-


RESULT

The warp marker is deleted.

Reset Functions

The **Reset** pop-up menu provides functions that allow you to reset all **VariAudio** changes that you performed.

To open the **Reset** functions, open the **VariAudio** section of the **Sample Editor** Inspector and click **Reset**.



Pitch Changes

Resets pitch changes including micro-pitch modifications with the **Tilt Micro Pitches** tool either for the selected segments (if available) or for the whole file.

Warp Changes

Resets warp changes.

Pitch + Warp Changes

Resets pitch, micro-pitch, and warp changes either for the selected segments (if available) or for the whole file.

Reanalyze Audio

Resets the segmentation and reanalyzes the audio.

NOTE

You can set up key commands for the reset and the reanalyze function in the **Sample Editor** category of the **Key Commands** dialog.

RELATED LINKS

[Key Commands](#) on page 973

Extracting MIDI from Audio

You can extract a MIDI part from your audio. This is useful if you want to copy the tune and sound of your audio with a MIDI instrument or VST instrument.

PREREQUISITE

The audio file is segmented and the segments are correct. All pitch and timing changes are completed. You have opened the audio in the **Sample Editor** and activated the **Segments** tool in the **VariAudio** section.

PROCEDURE

1. In the **VariAudio** section, click **Extract MIDI**.
 2. In the **Extract MIDI** dialog that opens, make your settings and click **OK**.
-

RESULT

A MIDI part is created according to your settings.


RELATED LINKS

[Segmenting Monophonic Audio](#) on page 484
[Extract MIDI Dialog](#) on page 500

Extract MIDI Dialog

The **Extract MIDI** dialog allows you to specify which audio data is used when creating a MIDI part with the **Extract MIDI** function.

To open the **Extract MIDI** dialog, open the **VariAudio** section of the **Sample Editor Inspector**, activate the **Segments** tool, and click **Extract MIDI**.



The following pop-up menus are available:

Pitch Mode

Allows you to specify which data is included if you extract MIDI. The following options are available:

Just Notes and No Pitchbend Data

Extracts notes only.

Notes and Static Pitchbend Data

Extracts pitchbend events for each segment. In the **Pitchbend Range** field you can specify a pitchbend value from 1 to 24.

NOTE

If you work with an external MIDI device, set it to the same **Pitchbend Range** value.

Notes and Continuous Pitchbend Data

Extracts pitchbend events that correspond to the micro-pitch curve. In the **Pitchbend Range** field you can specify a pitchbend value from 1 to 24.

NOTE

If you work with an external MIDI device, set it to the same **Pitchbend Range** value.

Notes and NoteExp Pitchbend Curve

Extracts pitchbend events that correspond to the micro-pitch curve. These are saved as Note Expression data for the resulting MIDI notes.

Notes and NoteExp VST 3 Tuning Curve

Extracts VST 3 events for the **Tuning** parameter. These are created as Note Expression data for the resulting MIDI notes.

NOTE

This works only with a connected VST instrument that is compatible with Note Expression.

Volume Mode

Allows you to specify how volume information from the audio is extracted. The following options are available:

Fixed Velocity

Assigns the same velocity to all created MIDI notes. In the **Velocity** field you can specify a velocity value.

Dynamic Velocity

Assigns an individual velocity value to each created MIDI note according to the amplitude of the audio signal.

Volume Controller Curve

Creates a continuous volume controller curve within the MIDI part. In the **MIDI Controller** field you can specify the MIDI controller.

NoteExp Volume Controller Curve

Extracts MIDI volume controller events. These are created as Note Expression data for the resulting MIDI notes.

NoteExp VST 3 Volume Curve

Extracts a VST 3 volume curve. This is created as Note Expression data for the resulting MIDI notes.

NOTE

This option works only with a connected VST instrument that is compatible with Note Expression.

Destination

Allows you to specify where the MIDI part is placed. The following options are available:

First Selected Track

Places the MIDI part on the first selected MIDI or instrument track. Note that any MIDI parts from previous extractions that are on this track are deleted.

New MIDI Track

Creates a new MIDI track for the MIDI part.

Project Clipboard

Copies the MIDI part into the clipboard. This option allows you to insert it at the desired position on a MIDI or instrument track in the **Project** window.

NOTE

If you opened the **Sample Editor** from the **Pool** and the audio file is not part of your project, the MIDI part is inserted at the beginning of the project.

Flattening Realtime Processing

You can flatten VariAudio modifications. This is useful if you want to reduce the CPU load, optimize the sound quality of the processing, or apply any offline processing.

PROCEDURE

1. Select the audio events that you want to process.
 2. Perform one of the following actions:
 - Select **Audio > Realtime Processing > Flatten Realtime Processing**.
 - In the **Process** section of the **Sample Editor**, click **Flatten**.
 3. Click **OK**.
-

RESULT

Any loop that was previously pitch shifted plays back exactly the same, but **Musical Mode** is deactivated, and VariAudio data is lost.

Harmony Voices for Audio

Cubase allows you to quickly create harmonies for monophonic audio material.

You have the following options:

- You can have Cubase create default harmony voices for your audio.
- You can create a chord track with some chords first, and then create harmony voices for your audio based on that track.

In both cases, a VariAudio analysis is performed for the selected audio event, and up to 4 copies of the corresponding track are created. These new tracks that are named **Soprano**, **Alto**, **Tenor**, and **Bass** contain independent copies of the selected audio event.


If you use the function without a chord track, the voices are distributed by default. If you create a chord track with some chords and set the original track to follow the chord track in **Single Voice** mode, the harmony voices are distributed according to the chord voicing.

Generating Harmony Voices for Monophonic Audio

You can automatically generate harmony voices for monophonic audio.

PROCEDURE

1. Optional: Add a chord track to your project and set it up.
2. Select **File > Import > Audio File** and import a monophonic audio file.
3. In the **Project** window, select the audio event.
4. Select **Audio > Generate Harmony Voices**.
5. Specify the number of voices that you want to create, enter a value for the vibrato reduction, and click **OK**.



RESULT

The audio event is analyzed and VariAudio segments are created automatically. A copy of the event with altered pitches is created for every voice and placed on a newly created track.

NOTE

- If you added a chord track, the pitches of the resulting voices follow the soprano, alto, tenor, and bass voices from the chord track voicing.
 - If you work without the chord track, the generated VariAudio segments of voice number 1 (soprano) are transposed 3 semitones upwards in relation to the original audio. The segments of voice numbers 2, 3, and 4 (alto, tenor, and bass) are transposed 3, 6, and 9 semitones downwards.
-

RELATED LINKS

[Adding the Chord Track](#) on page 819

Audio Part Editor

The **Audio Part Editor** provides an overview of the selected audio parts. It allows you to view, audition and edit parts by cutting and pasting, crossfading, drawing level curves, or by processing parts. Editing is non-destructive so that you can undo modifications at any time.

You can open the **Audio Part Editor** in a separate window or in the lower zone of the **Project** window. Opening the **Audio Part Editor** in the lower zone of the **Project** window is useful if you want to access the **Audio Part Editor** functions from within a fixed zone of the **Project** window.


To open an audio part in the **Audio Part Editor**, do one of the following:

- Double-click an audio part in the **Project**.
- Select an audio part in the **Project** window and press **Return** or **Ctrl/Cmd-E**.
- Select an audio part in the **Project** window and select **Audio > Open Audio Part Editor**.
- In the **Key Commands** dialog in the **Editors** category, assign a key command for **Open Audio Part Editor**. Select an audio part in the **Project** window and use the key command.


NOTE

If you select **Audio > Set up Editor Preferences**, the **Preferences** dialog opens on the **Editors** page. Make your settings to specify if you want the **Audio Part Editor** to open in a separate window or in the lower zone of the **Project** window.

The **Audio Part Editor** window:



The **Audio Part Editor** in the lower zone of the **Project** window:



- 1 **Toolbar**
Contains tools for selecting, editing, and playing back audio parts.
- 2 **Info Line**
Displays information on the audio parts.

3 Ruler

Displays the timeline and the display format of the project.

RELATED LINKS

[Opening the Editor in the Lower Zone](#) on page 64

[Opening the Editor Inspector](#) on page 54

[Ruler](#) on page 46

[Info Line](#) on page 48

[Toolbar](#) on page 505

Toolbar

The toolbar contains tools for selecting, editing, and playing back audio parts.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

The following options are available:

Info/Solo

Solo Editor



Solos the selected audio during playback.

Left Divider

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

Auto-Scroll

Link Project and Lower Zone Editor Cursors



Links timelines, cursors and zoom factors of the lower zone editor and the **Project** window.

NOTE

You cannot activate **Link Project and Lower Zone Editor Cursors** if **Independent Track Loop** is active.

Auto-Scroll



Keeps the project cursor visible during playback. The **Switch Auto-Scroll Settings** pop-up menu allows you to activate **Page Scroll** or **Stationary Cursor** and to activate **Suspend Auto-Scroll When Editing**.

Preview

Audition



Plays back the edited audio. **Audition Loop** loops the playback until you deactivate the **Audition** icon. The **Audition Volume** slider allows you to adjust the volume.

Tool Buttons

Object Selection



Allows you to select audio parts.

Range Selection



Allows you to select ranges.

Zoom



Allows you to zoom in the waveform display. To zoom out, hold **Alt** while clicking.

Erase



Allows you to erase events from audio parts.

Split



Allows you to split audio parts.

Mute



Allows you to mute/unmute audio parts.

Comp



Allows you to assemble takes.

Draw



Allows you to edit audio.

Play



Allows you to play back the clip from the position where you click until you release the mouse button.

Scrub



Allows you to locate positions.

Time Warp (Cubase Pro only)



Allows you to drag a musical position to a certain position in time.

Multiple Part Controls

Show Part Borders




Shows/Hides part borders for the active audio part, within the left and right locators.

Edit Active Part Only



Restricts editing operations to the active part.

Currently Edited Part



Lists all parts that were selected when you opened the editor, and allows you to activate a part.

Nudge Palette

Trim Start Left



Increases the length of the selected element by moving its start to the left.

Trim Start Right



Decreases the length of the selected element by moving its start to the right.

Move Left



Moves the selected element to the left.

Move Right



Moves the selected element to the right.

Trim End Left



Decreases the length of the selected element by moving its end to the left.

Trim End Right



Increases the length of the selected element by moving its end to the right.

Snap/Quantize

Snap to Zero Crossings



Restricts editing to zero crossings, that is, positions where the amplitude is zero.

Snap On/Off



Activates/Deactivates the snap function.

Snap Type



Allows you to select one of the following snap types:

- **Grid**  snaps events to the grid that is selected in the **Quantize Presets** pop-up menu.
- **Grid Relative**  keeps the relative positions when snapping events to the grid.
- **Events**  snaps events to the start or end of other events.

- **Shuffle**  changes the order of events if you drag one event to the left or right of other events.
- **Magnetic Cursor**  snaps events to the cursor position.
- **Grid + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu or to the cursor position.
- **Events + Cursor**  snaps events to the start or end of other events or to the cursor position.
- **Grid + Events + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu, to the start or end of other events or to the cursor position.

Iterative Quantize On/Off



Activates/Deactivates iterative quantize.

Quantize Presets



Allows you to select a quantize or a groove preset.

Apply Quantize



Applies the quantize settings.

Open Quantize Panel



Opens the **Quantize Panel**.

Event Colors


Color Menu



Allows you to define audio part colors.

Independent Track Loop

Independent Track Loop



Activates/Deactivates the independent track loop for the edited part.

NOTE

If you activate **Independent Track Loop**, the **Link Project and Lower Zone Editor Cursors** function is automatically deactivated in the lower zone editor.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls

Open in Separate Window



This button is available in the lower zone editor. It opens the editor in a separate window.

Open in Lower Zone



This button is available in the editor window. It opens the editor in the lower zone of the **Project** window.

Show/Hide Info



Allows you to activate/deactivate the info line.

Set up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.

RELATED LINKS

[Link Project and Lower Zone Editor Cursors](#) on page 66

[Auto-Scroll](#) on page 221

[Suspend Auto-Scroll When Editing](#) on page 221

Info Line

The info line shows information about the audio part, such as the start, end, length, or the time stretch algorithm.

File	Start	End	Length	Offset	Snap
04 piano 01	1. 1. 1. 0	3. 1. 1. 0	2. 0. 0. 0	0. 0. 0. 0	1. 1. 1. 0
Fade-In	Fade-Out	Volume	Lock	Transpose	Fine-Tune
0. 0. 0. 0	0. 0. 0. 0	0.00 dB	-	0	0
Global Transpose	Root Key	Mute	Musical Mode	Algorithm	
Follow	E	-	Musical	élastique Pro - Time	

- To show or hide the info line, activate **Show/Hide Info**  on the toolbar. The on/off status of the info line in the **Audio Part Editor** window and in the lower zone editor are independent of each other.


The Ruler

The ruler shows the timeline and the display format of the project.

You can select a separate display format by clicking on the arrow button on the right. Select an option from the pop-up menu.

About Lanes

Lanes can make it easier to work with several audio events in a part. Moving some of the events to another lane can make selecting and editing much easier.



If **Snap** is deactivated and you want to move an event to another lane without accidentally moving it horizontally, press **Ctrl/Cmd** while dragging it up or down.

RELATED LINKS

[Track Handling](#) on page 151

Operations

All operations can be performed in the **Audio Part Editor** window and in the lower zone editor.

Zooming, selecting and editing in the **Audio Part Editor** is done just as in the **Project** window.

NOTE

If a part is a shared copy, any editing you perform will affect all shared copies of this part.

RELATED LINKS

[Project Window](#) on page 38

[Shared Copies](#) on page 199

Auditioning in the Audio Part Editor

To audition audio parts, you can use one of the following methods:

Auditioning Using the Audition Tool

You can use the audition tool to directly start a single audition of a selection or loop an audition using the **Audition Loop** function.

Clicking **Audition** on the toolbar plays back the edited audio, according to the following rules:

- If you have selected events in the part, only the section between the first and last selected event will be played back.
- If you have made a range selection, only this section will be played back.

- If there is no selection, the whole part will be played back. If the project cursor is within the part, playback starts from the current cursor position. If the cursor is outside the part, playback starts from the beginning of the part.
- If **Audition Loop** is activated, playback will continue until you deactivate **Audition**. Otherwise, the section will be played back once.

When auditioning with the **Speaker** tool or **Audition** icon, audio will be routed directly to the **Control Room** (Cubase Pro only) or to the main mix (the default output bus) if the **Control Room** is disabled. In Cubase Artist, the main mix bus is always used for auditioning.

Auditioning Using the Speaker Tool

PROCEDURE

1. Select **Speaker** on the toolbar.
 2. On an audio part, click and hold at the position you want to begin auditioning from.
-

RESULT

You are auditioning the audio part. The audition will stop at the end of the part you clicked on.

Auditioning Using Regular Playback

To audition from the cursor position, you can use the regular playback controls on the **Transport** panel. If you activate **Solo Editor** on the toolbar, only the events in the edited part will be played back.

Setting Up the Independent Track Loop

The independent track loop is a sort of mini-cycle, affecting only the edited part. When the loop is activated, the events in the parts that are within the loop will be repeated continuously and completely independent – other events (on other tracks) are played back as usual. The only interaction between the loop and the regular playback is that the loop starts every time the cycle starts over again.


PROCEDURE

1. Activate **Independent Track Loop** on the toolbar.

NOTE

If you activate **Independent Track Loop**, the **Link Project and Lower Zone Editor Cursors** function is automatically deactivated in the lower zone editor.

If it is not visible, right-click the toolbar and add the **Independent Track Loop Settings** section.



2. **Ctrl/Cmd**-click in the ruler to set the start and **Alt**-click to set the end of the loop.

NOTE

You can also edit the loop start and end positions numerically in the fields next to the **Loop** button.

RESULT

The loop is indicated in blue in the ruler.

NOTE

The events are looped as long as the **Loop** button is activated and the **Audio Part Editor** is open.

RELATED LINKS

[Using the Setup Options](#) on page 994

Scrubbing

In the **Audio Part Editor**, the **Scrub** tool has a separate icon on the toolbar. Apart from that, scrubbing works exactly as in the **Project** window.

RELATED LINKS


[Scrubbing](#) on page 190

Handling Several Parts

When you open the **Audio Part Editor** with several parts selected – all on the same track or on different tracks – they might not all fit in the editor window, which can make it hard to get an overview of the different parts when editing.

Therefore, the toolbar features a few functions to make working with multiple parts easier and more comprehensive:


- The **Currently Edited Part** pop-up menu lists all parts that were selected when you opened the editor, and lets you select which part is active for editing.
When you select a part from the list, it is automatically made active and centered in the display.




NOTE

You can also activate a part by clicking on it with the **Object Selection** tool.

- **Edit Active Part Only** lets you restrict editing operations to the active part only.
If you select **Edit > Select > All** with this option activated, all events in the active part are selected, but not the events in other parts.



- You can zoom in on an active part so that it is displayed in its entirety in the window by selecting **Edit > Zoom > Zoom to Event**.
- **Show Part Borders** can be used if you want to see clearly defined borders for the active part.
If this option is activated, all parts except the active one are grayed out, making the borders easily discernible. There are also two markers in the ruler with the name of the active part, marking its beginning and end. These can be moved freely to change the part borders.



- It is possible to cycle between parts, making them active using key commands. In the **Key Commands** dialog – Edit category, there are two functions: **Activate Next Part** and

Activate Previous Part. If you assign key commands to these, you can use them to cycle between parts.

RELATED LINKS

[Key Commands](#) on page 973

Controlling Sample Playback with Sampler Tracks

The sampler track features allow you to chromatically play back any audio from your audio sample library via MIDI. You can create and edit new sounds based on specific samples, and integrate them into an existing project.

The sampler track features include:

- A sampler track that allows you to control the playback of the audio sample that is loaded in **Sampler Control**.
- **Sampler Control** that allows you load and edit audio samples.

Loading Audio Samples into Sampler Control

You can load audio samples into **Sampler Control** by dragging.

Cubase allows you to load mono or stereo samples in .wav or .aiff file format into **Sampler Control**.

- To load an audio sample, drag it from the **MediaBay**, the **Project** window event display, or the File Explorer/macOS Finder and drop it in **Sampler Control**.

IMPORTANT

If **Sampler Control** already contains an audio sample, this sample and all its settings are overwritten.

NOTE

- Audio samples that you load into **Sampler Control** are not copied to the project audio folder. If you want to archive or share your project including all audio samples that you have loaded into **Sampler Control**, you must create a self-contained project.
- In the **Pool**, all audio samples that you have loaded into **Sampler Control** are listed in a dedicated sampler track subfolder in the main audio folder.

RELATED LINKS

[Creating Self-Contained Projects](#) on page 93

[Pool](#) on page 527

Loading MIDI Parts into Sampler Control

You can load MIDI parts from instrument tracks or MIDI tracks, into **Sampler Control** by dragging.

NOTE

For this to work, the instrument track or the MIDI track must be routed to a VST instrument.

- To load a MIDI part, drag it from the **MediaBay**, the **Project** window event display, or the File Explorer/macOS Finder and drop it in **Sampler Control**.

IMPORTANT

If **Sampler Control** already contains MIDI, it is overwritten.

Cubase creates an audio file from the MIDI part. This includes the instrument sound and the channel settings from the VST instrument or the return channel. The audio file is copied to the project audio folder.

RELATED LINKS

[VST Instruments](#) on page 628

[Instrument Track Inspector](#) on page 105

[MIDI Track Inspector](#) on page 112

Creating Sampler Tracks

To create a sampler track, do one of the following:

- In the **Project** window, select an audio event and select **Audio > Create Sampler Track**.
- In the **MediaBay**, right-click an audio file and select **Create Sampler Track**.
- In the **Inspector** of the **Sample Editor**, open the **Range** section and click **Create Sampler Track** .

This creates a sampler track from the selected range. If no range is selected, the entire event is used.

- On the context menu of the track list, select **Add Sampler Track**.

In this case, **Sampler Control** is empty and you must load an audio sample by dragging.

Sampler Control

If the sampler track is selected, **Sampler Control** is available in the lower zone of the **Project** window. **Sampler Control** allows you to view, edit, and play back samples or specific sections of the samples.



1 Toolbar

Contains tools that allow you to select and edit the audio sample, to organize track presets, and to transfer the sample with its settings to an instrument.

2 Waveform Display/Envelope Editor

Shows the waveform image of the sample and allows you to define the playback range for the sample and to set a loop.

If the envelope editors for the pitch, filter, or amp section are shown, you can adjust their envelope curve settings here.

3 Sound Parameter Section

Allows you to make settings for time stretching and formant shifting (**AudioWarp** section), tuning and pitch modulation (**Pitch** section), filtering (**Filter** section), or level and panorama (**Amp** section).

4 Keyboard Section

Allows you to set the key range of the sample, its root key, and the modulation range of the pitchbend wheel. These settings are used if you work with an external MIDI device.

RELATED LINKS

[Creating Sampler Tracks](#) on page 515

[Waveform Display](#) on page 518

[Envelope Editors](#) on page 522

[Sound Parameter Section](#) on page 519

[Keyboard Section](#) on page 524

Sampler Control Toolbar

The **Sampler Control** toolbar contains various settings and functions.

Read Automation



Allows you to read track automation.

Write Automation



Allows you to write track automation.

Switch between A/B Settings



Allows you to switch between different parameter settings.

Event Received Indicator



This LED indicates incoming MIDI messages via the selected MIDI input. The LED lights up on receiving note-on and controller messages. This way, you can check if Cubase and your MIDI keyboard are connected to the same MIDI device input.

Snap to Zero Crossing



Restricts sample editing to zero crossings, that is, to positions where the amplitude is zero.

Auto-Scroll



Keeps the project cursor visible during playback.

Preset section



Shows the name of the track preset that is loaded for the sampler track. You can also save and load presets.

Import Audio File



Opens the **Import Audio** dialog that allows you to load an audio file into **Sampler Control**.

NOTE

If **Sampler Control** already contains an audio file, the original file is replaced by the new file.

File Name



Shows the file name of the sample.

Tempo




Shows the tempo of the sample.

Root Key



Shows the root key that determines the pitch of the sample. You can change the root key by entering a new value in the value field or by dragging the root key handle on the **Sampler Control** keyboard.

Loop Mode



Allows you to select a loop mode for playback via MIDI.

- If this is set to **No Loop**, the sample is played once.
- If this is set to **Continuous**, the sample is played in a continuous loop.
- If this is set to **Alternate**, the sample is played back in a loop that alternates forward and backward.
- If this is set to **Once**, the sample is looped once.
- If this is set to **Until Release**, the sample is looped repeatedly until you release the key on the keyboard.
- If this is set to **Alternate Until Release**, the loop alternates forward and backward for as long as you hold the key.

One Shot



The sample is played back once from beginning to end, regardless of any loop settings.

MIDI Reset



Stops playback and resets all MIDI controllers to their default values.

This is useful, for example, if you want to stop playback of a long audio sample in **One Shot** mode.

Fixed Pitch



If a sample is triggered by a MIDI note other than the one defined by the **Root Key** setting, the sample is pitched accordingly. If **Fixed Pitch** is activated, the relation

between played note and root key is disregarded and all keys play the sample just as it was recorded.

Reverse Sample



Reverses the sample. This allows you to play back the sample backwards.

Monophonic Mode



Activates monophonic playback. For solo instruments, this usually results in a more naturally sounding performance. If monophonic playback is activated, a note that was stolen by another note is retriggered if you still hold the stolen note when you release the new one. This way, you can play trills by holding one note and quickly and repeatedly pressing and releasing another note, for example.

If this option is deactivated, you can play up to 128 notes simultaneously.

Transfer to New Instrument



Allows you to transfer the audio sample with all its **Sampler Control** settings to an instrument that is loaded to a new instrument track.

Open in Separate Window



Opens **Sampler Control** in a separate window.

To close the separate window and open **Sampler Control** in the lower zone, click **Open in Lower Zone** .

RELATED LINKS


[Setting the Root Key Manually](#) on page 525

[Setting up Loops for Audio Samples](#) on page 524

[Transferring Samples from Sampler Control to VST Instruments](#) on page 526

Waveform Display

The waveform display shows the waveform of your audio sample. It allows you to define the start and end of the audio sample, of the loop, and of the fade-in/-out.



Sample Start

Defines the sample start. On playback, all audio before the sample start is ignored.

Sample End

Defines the sample stop. On playback, all audio after the sample end is ignored.

Sustain Loop Start

Defines where the sustain loop starts.

Sustain Loop End

Defines where the sustain loop ends. When this marker is reached, playback jumps back to the sustain loop start.

Fade-In Length

Defines the fade-in length.

Fade-Out Length

Defines the fade-out length.

Sustain Loop Crossfade Length

Loop crossfades allow for smoother loops. This marker defines the length for the loop crossfade.

Ruler

The ruler shows the timeline in the specified display format.

- To select the format, click the arrow button to the right of the ruler and select an option from the pop-up menu.
You can display bars and beats, seconds, or samples.

Zooming

- To zoom in/out on the time and level axes, use the horizontal and vertical zoom sliders or the corresponding key commands.

RELATED LINKS

[Key Commands](#) on page 973

Sound Parameter Section

In the sound parameter section you can make settings for time stretching and formant shifting (**AudioWarp** section), tuning and pitch modulation (**Pitch** section), filtering (**Filter** section), or level and panorama (**Amp** section).

AudioWarp

In the **AudioWarp** section, you can apply time stretching and formant shifting to your samples.



- To activate the AudioWarp settings, click **Activate/Deactivate AudioWarp** .

AudioWarp Mode

- **Solo** mode offers parameters for time stretching and formant shifting. This mode is suitable for loops and samples of solo instruments or vocals.
- **Music** mode offers parameters for time stretching. This mode is suitable for complex material like drum loops and samples of mixed music. It uses considerably more CPU time than **Solo** mode.

NOTE

The more the sample is stretched, the higher the CPU load.

AudioWarp Sync Mode

Allows you to match the playback speed of the sample to the project tempo.

- If **Off** is selected, the playback speed is specified manually, in percent.
- If **Tempo** is selected, the playback speed is calculated using the ratio between the original tempo of the sample and the tempo of the host.

Legato

If this option is deactivated, each note that is played via MIDI starts playback from the **Sampler Control** position cursor.

If this option is activated, the first note starts playback from the position cursor, and any following notes start from the current playback position for as long as the first note is held.

Speed

If **AudioWarp Sync Mode** is set to **Off**, you can adjust the playback speed of the sample.

In **Music** mode, the minimum playback speed adjustment is 12.5 %. Values below this limit have no effect.

Original BPM

If **AudioWarp Sync Mode** is set to **Tempo**, you can enter the original tempo of the sample in beats per minute. The playback speed of the sample is adjusted to match the tempo of the host application.

NOTE

This parameter is only available in **Solo** and in **Music** mode. In **Music** mode, the lower limit of the playback speed adjustment is 12.5 %. Values below this limit have no further effect.


Formant

Allows you to adjust formant shifting. Formant shifting allows you to avoid so-called Mickey Mouse effects when pitch shifting a sample. This is especially useful with samples of human voices or acoustic instruments.

This parameter is only available in **Solo** mode.

Pitch

In the **Pitch** section, you can adjust the tuning and pitch of your audio sample. The pitch envelope allows you to modulate the pitch over time.



Coarse

Sets the pitch of the audio sample in semitone steps.

Fine

Fine-tunes the pitch of the audio sample in cents (hundredths of a semitone).

Glide

Specifies the time that is needed to bend the pitch of the audio sample from one note to the following note. If you move this control all the way to the left, **Glide** is deactivated.

Show/Hide Pitch Envelope


Shows the pitch envelope editor.

RELATED LINKS

[Envelope Editors](#) on page 522

Filter

In the **Filter** section, you can adjust the tone color of the sample sound. The filter envelope allows you to control the cutoff frequency to shape the harmonic content over time.



- To activate the filter settings, click **Activate/Deactivate Filter** .

Cutoff

Controls the cutoff frequency of the filter.

Resonance

Sets the filter resonance.

Drive

Determines the level of the input signal and thus the amount of saturation.

Show/Hide Filter Envelope

Shows the filter envelope editor.

RELATED LINKS

[Envelope Editors](#) on page 522

Amp

In the **Amp** section, you can set volume and pan of the sample. The amplifier envelope allows you to shape the volume over time.



Volume

Sets the level of the sample.

Pan

Sets the position of the sample in the stereo panorama.

Show/Hide Amp Envelope

Shows the amplifier envelope editor.

RELATED LINKS

[Envelope Editors](#) on page 522

Envelope Editors

You can adjust the **Pitch**, **Filter**, and **Amp** envelope curves. Each of these envelopes can contain up to 128 nodes.

- Click **Show/Hide Envelope**  at the top right of a section to show the corresponding envelope editor.



Pitch Envelope

Envelope Amount

Determines how much the selected envelope affects the audio. This parameter allows for positive and negative values. If the **Envelope Amount** is set to 0, the envelope has no effect.

NOTE

This parameter is only available for **Filter** and **Pitch**.

Envelope display

Shows the envelope curve. You can adjust it by adding, moving, and deleting nodes. The nodes for attack (**A**), sustain (**S**), and release (**R**) are always shown and cannot be deleted. Next to the release node, the release time of the envelope is shown.

Mode

Determines how the envelope is played back when it is triggered.

- Select **Sustain** to play the envelope from the first node to the sustain node. The sustain level is held for as long as you play the note. When you release the note, the envelope continues with the stages following the sustain. This mode is suited for looped samples.
- Select **Loop** to play back the envelope from the first node to the loop nodes. Then, the loop is repeated for as long as the key is held. When you release the note, the envelope continues playing the stages that follow the sustain. This mode is suited for adding motion to the sustain of the envelope.
- Select **One Shot** to play the envelope from the first to the last node, even if you release the key. The envelope has no sustain stage. This mode is suited for drum samples.
- Select **Sample Loop** to preserve the natural attack of the sample. The decay of the envelope does not start until the sample has reached the sample loop start.

If you set the second node to the maximum level and use the following nodes to shape the decay during the loop phase of the sample, the envelope only affects the loop phase. The attack of the envelope is still executed.

Velocity

Determines how the velocity affects the level of the envelope.

The level of the envelope depends on the velocity setting and on how hard you hit a key. Higher values increase the level of the envelope the harder you hit a key.

RELATED LINKS

[Selecting Nodes](#) on page 523

[Adding and Removing Nodes](#) on page 523

[Adjusting the Envelope Curve](#) on page 523

[Zoom Functions in the Envelope Editors](#) on page 523

Selecting Nodes

You can select single nodes or multiple nodes. Selected nodes are edited together.

- To select a node, click on it in the graphical editor.
The **Time** field at the top of the graphical envelope editor shows the parameters of the selected node.
- To add a node to a selection, **Shift**-click the node.
- To select multiple nodes, draw a rectangle around them with the mouse.
If multiple nodes are selected, the **Time** field shows the parameters of the node that is indicated by a white border.
- To select all envelope nodes, press **Ctrl/Cmd-A**.
- If the envelope editor has the keyboard focus, you can select the next or the previous node with the left and right arrow keys.

RELATED LINKS

[Keyboard Focus in the Project Window](#) on page 73

Adding and Removing Nodes

You can add up to 128 nodes to an envelope curve.

- To add a node, double-click at the position where you want to add the node.
- To remove a node, double-click it.
- To delete several selected nodes, press **Delete** or **Backspace**.

NOTE

- You cannot remove the attack (**A**), the sustain (**S**), or the release node (**R**).
- All nodes added after the sustain node always affect the release phase of the envelope.

Adjusting the Envelope Curve

The envelope editor allows you to adjust the envelope curve by dragging.

- To move a node horizontally or vertically, click and drag it.
- To move the envelope curve vertically between two nodes, click and drag it.

Zoom Functions in the Envelope Editors

The vertical axis of the envelope editor displays the level. The horizontal axis displays the time.

- To zoom in or out, click the **+** or **-** buttons to the right of the scrollbar below the envelope editor or use the corresponding key commands.
- To zoom in or out at the current position, click in the timeline and drag up or down.
- To zoom to a specific region, hold **Alt**, click and drag the mouse over the region.

RELATED LINKS

[Key Commands](#) on page 973

Keyboard Section

In the keyboard section of **Sampler Control** you can set the root key and the key range of the sample, and the modulation range of the pitchbend wheel on your MIDI keyboard.



Pitchbend

Determines the maximal modulation that is applied when you move the pitchbend wheel on your MIDI keyboard. You can set the pitchbend range in semitone steps up to 12 semitones.

Keyboard

Determines the root key and the key range of the sample.

RELATED LINKS

[Setting the Root Key Manually](#) on page 525

[Setting the Key Range](#) on page 525

Sample Editing and Playback Functions

All sample editing in **Sampler Control** is non destructive.

Setting Sample Start and End

By setting the sample start and end, you can define what range of the sample is played back when you press a key on your MIDI keyboard.

PROCEDURE

1. Drag the **Set Sample Start** handle to the right to adjust the sample start point.
 2. Drag the **Set Sample End** handle to the left to adjust the sample end point.
-

Setting up Loops for Audio Samples

You can set up a loop that is played back when the sample is triggered.

PROCEDURE

1. On the toolbar, click **Loop Mode** and select a loop mode from the pop-up menu. The **Sustain Loop Start/End** handles and the green loop range overlay are shown.
2. Drag the **Set Sustain Loop Start/End** handles to adjust the loop start and end points. To create a smooth loop transition, try to match the shape of the green loop range overlay with the shape of the gray sample waveform.

NOTE

You cannot drag the loop start and end points outside the defined sample range.

RELATED LINKS

[Setting Sample Start and End](#) on page 524

Setting the Root Key Manually

The **Root Key** shows the original pitch of the sample. Sometimes, if the sample does not contain any root key information or if you want the sample to play at a different pitch you must set the root key manually.

NOTE

If you load a sample that does not contain any root key information, the root key is automatically set to C3.

To set the root key manually, do one of the following:

- In the keyboard section of **Sampler Control**, click and drag the root key handle.
- On the toolbar of **Sampler Control**, double-click in the **Root Key** field and enter the new root key using your computer keyboard, your mouse wheel, or your MIDI keyboard.

RELATED LINKS

[Keyboard Section](#) on page 524

[Setting the Key Range](#) on page 525

Setting the Key Range

You can determine the key range for the sample. This is useful for samples that only sound good within a certain key range.

PROCEDURE

- In the keyboard section, adjust the key range by dragging the range handles above the keyboard display.
-

RESULT

Only keys within the determined key range play a sound when triggered.

RELATED LINKS

[Keyboard Section](#) on page 524

Playing Back Samples

After you have loaded an audio sample into **Sampler Control**, you can play back the sample using an external MIDI keyboard or the **On-Screen Keyboard**.

PREREQUISITE

You have loaded a sample into **Sampler Control** and made all sample editing and settings. You have installed and set up your MIDI keyboard.

PROCEDURE

1. In the track list, activate **Monitor** for the sampler track.
 2. Optional: On the **Sampler Control** toolbar, activate **Fixed Pitch**.
This allows you to play back the sample in its original pitch and speed.
 3. Hit some notes on your keyboard or use the **On-Screen Keyboard** to play back the sample.
-

RESULT

If **Fixed Pitch** is deactivated, the sample is played back and the pitch is defined by the notes you play. If you hit lower keys, the sample is played back with a low pitch. If you hit higher keys, the sample is played back with a high pitch.

If **Fixed Pitch** is activated, the sample is played back in its original pitch.

AFTER COMPLETING THIS TASK

To use the sound of the edited sample in your project, create or record a MIDI event on the sampler track.

RELATED LINKS

[On-Screen Keyboard](#) on page 234

[Monitoring via Cubase](#) on page 240

[MIDI Events](#) on page 188

[Basic Recording Methods](#) on page 236

[MIDI Editors](#) on page 702

Transferring Samples from Sampler Control to VST Instruments

You can transfer audio samples with all settings that you have made in **Sampler Control** to specific Steinberg VST instruments.

Transferring audio samples from **Sampler Control** to a VST instrument creates a new instrument track in the track list. This new track is added below the sampler track. The audio sample and all its settings are loaded in the VST instrument.

You can transfer audio samples from **Sampler Control** to the following Steinberg VST instruments:

- Groove Agent
- Groove Agent SE
- HALion
- Padshop Pro

Transferring a Sample

PREREQUISITE

You have installed Groove Agent, Groove Agent SE, or HALion. You have loaded an audio sample in **Sampler Control**.

PROCEDURE

1. In the **Sampler Control** toolbar, click **Transfer to New Instrument**.
 2. In the pop-up menu, select the instrument to which you want to transfer the sample.
-

RESULT

In the track list, a new instrument track is created below the sampler track. The instrument track has the same name as the sampler track. The audio sample and all its settings are loaded in the selected VST instrument.

RELATED LINKS

[Transferring a Sample](#) on page 526

Pool

Every time that you record on an audio track, a file is created on your hard disk. A reference to this file, a clip, is added to the **Pool**.

The following rules apply to the **Pool**:

- All audio and video clips that belong to a project are listed in the **Pool**.
- Every project has a separate **Pool**.

The way the **Pool** displays folders and their contents is similar to the way the File Explorer/macOS Finder displays folders and file lists. In the **Pool**, you can perform operations that affect files on disk and operations that only affect clips.

Operations That Affect Files

- Importing clips (audio files can automatically be copied and/or converted)
- Converting file formats
- Renaming clips (this also renames the referenced files on disk) and regions
- Deleting clips
- Preparing file archives for backup
- Minimizing files

Operations That Affect Clips


- Copying clips
- Auditioning clips
- Organizing clips
- Applying audio processing to clips
- Saving or importing complete **Pool** files

Pool Window

The **Pool** window allows you to manage the media files of the active project.

You can open the **Pool** in the following ways:

- On the **Project** window toolbar, click **Open Pool Window**. If this icon is not visible, you must activate the **Media & MixConsole Windows** option on the toolbar context menu.
- Select **Project > Pool**.
- Select **Media > Open Pool Window**.



The content of the **Pool** is divided into the following folders:

Audio Folder

Contains all audio clips and regions that are in the project.

If the projects contains one or more sampler tracks, a dedicated **Sampler Track** subfolder is created in the audio folder. This subfolder contains all clips of samples that you have loaded into **Sampler Control**.

Video Folder

Contains all video clips that are in the project.

Trash Folder


Contains unused clips that have been moved here for later permanent removal from the hard disk.

NOTE

You cannot rename or delete these folders, but you can add any number of subfolders.

Pool Window Columns

The **Pool** window columns display information about the clips and regions.



The following columns are available:

Media

Contains the **Audio**, **Video**, and **Trash** folders. If the folders are opened, the clip or region names are shown and can be edited.

Used

Displays how many times a clip is used in the project. If there is no entry in this column, the corresponding clip is not used.

Status

Displays various icons that relate to the current **Pool** and clip status. The following symbols can be displayed:

- **Record** folder  Record
Indicates the **Record** folder.
- Process 
Indicates that a clip has been processed.
- Missing 
Indicates that a clip is referenced in the project but missing from the **Pool**.
- External 
Indicates that the file the clip related to is external, for example, located outside the current **Audio** folder for the project.
- Recorded 
Indicates that the clip has been recorded in the open version of the project. This is useful for finding recently recorded clips quickly.

Musical Mode

You can use **Musical Mode** to tempo-match audio loops to the project tempo. The checkbox in this column allows you to activate or deactivate musical mode. If the **Tempo** column displays “???”, you must enter the correct tempo before you can activate **Musical Mode**.

Tempo

Displays the tempo of audio files if available. If no tempo has been specified, the column displays “???”.

Sign

Displays the time signature, for example, “4/4”.

Key

Displays the root key if one has been specified for the file.

Algorithm

Displays the algorithm preset that is used if the audio file is processed.

- To change the default preset, click the preset name and select another preset from the pop-up menu.

Info

For audio clips, this column displays the sample rate, bit depth, number of channels, and length.

For regions, it displays start and end times in frames.

For video clips, it displays the frame rate, resolution, number of frames, and length.

Type

Displays the file format of the clip.

Date

Displays the date when the audio file was last changed.

Origin Time

Displays the original start position where a clip was recorded in the project. As this value can be used as a basis for the **Insert into Project** option in the **Media** or context menu, you can change it if the **Origin Time** value is independent (for example, not for regions).

You can change the value by editing the value in the column, or by selecting the corresponding clip in the **Pool**, moving the project cursor to the new position and selecting **Audio > Update Origin**.

Image

Displays waveform images of audio clips or regions.

Path

Displays the path to the location of a clip on the hard disk.

Reel Name


If you have imported an OMF file, it may include this attribute, which is then shown in this column. It describes the reel or tape from which the media was originally captured.

NOTE

You can rearrange the order of the columns by clicking a header and dragging left or right.

Toolbar

The toolbar contains tools and settings for working in the **Pool**.



- 1 Show Info**
Activates/Deactivates the info line.
- 2 Audition**
If this option is activated and you select a clip in the **Pool**, it is played back.
- 3 Audition Loop**
If this option is activated, the playback of the selected clip is looped.
- 4 Volume**
Lets you specify the playback volume.
- 5 View/Attributes**
Lets you activate/deactivate which attributes are displayed in the **Pool** window.
- 6 Open/Close all folders**
Opens/Closes all folders.
- 7 Import**
Lets you import media files to the **Pool**.
- 8 Search**
Lets you search the **Pool** and connected disks for media files.
- 9 Project Folder**
Displays the path to the folder of the active project.

10 Pool Record Folder

Displays the path to the **Record** folder of the active project. By default, this is the **Audio** folder. However, you can create a new **Audio** subfolder and designate this as your **Pool** record folder.

Info Line

The info line shows information about the event or part that you selected in the **Pool**.

The info line displays additional information regarding the files in the **Pool**.

- To activate the info line, click **Show Info** at the left of the toolbar.

The info line shows the following information:

Audio Files

The number of audio files in the **Pool**.

Used

The number of audio files in use.

Total Size

The total size of all audio files in the **Pool**.

External Files

The number of files in the **Pool** that do not reside in the project folder (for example, video files).

Working with the Pool

NOTE

Most of the **Pool**-related main menu functions are also available on the **Pool** context menu.

Renaming Clips or Regions in the Pool

IMPORTANT

Renaming clips or regions in the **Pool** also renames the referenced files on disk. It is recommended to rename clips or regions in the **Pool**. Otherwise, the reference from the clip to the file may get lost.

PROCEDURE

1. In the **Pool** window, select a clip or region, and click the existing name.
 2. Type in a new name and press **Return**.
-

RELATED LINKS

[About Missing Files](#) on page 537

Duplicating Clips in the Pool

You can create duplicates of clips and apply different processing methods to them.

NOTE

Duplicating a clip does not create a new file on disk, but a new edit version of the clip that refers to the same audio file.

PROCEDURE

1. In the **Pool** window, select the clip that you want to duplicate.
 2. Select **Media > New Version**.
-

RESULT

A new version of the clip appears in the same **Pool** folder. The duplicated clip has the same name as the original but with a version number after it. Regions within a clip are also copied, but keep their name.

Inserting Clips into a Project

To insert a clip into a project, you can either use the insert commands on the **Media** menu or use drag and drop.

Inserting Clips into a Project Via Menu Commands

PROCEDURE

1. In the **Pool** window, select the clips that you want to insert into the project.
2. Select **Media > Insert into Project** and select one of the insert options.
If several clips are selected, choose whether to insert them on one track or each on a different track.

NOTE

The clips are positioned so that their snap points are aligned with the selected insert position. If you want to adjust the snap point before inserting a clip, double-click a clip to open the Sample Editor. Here, you can adjust the snap position and then perform the insert options.

RESULT

The clip is inserted on the selected track or on a new audio track. If several tracks are selected, the clip will be inserted on the first selected track.

RELATED LINKS

[Adjusting the Snap Point](#) on page 464

Inserting Clips into a Project Via Drag and Drop

You can drag a clip from the **Pool** into the **Project** window.

Snap is taken into account if **Snap** is activated.

If you drag the clip into the **Project** window, the cross-hair cursor and a tooltip are shown. The tooltip indicates the timeline position where the snap point of the clip is aligned.

If you position the clip in an empty area of the track list, that is, where no track exists, a new track is created for the inserted event.

NOTE

If you press and hold **Shift** while dragging the clip from the **Pool** on an event, the clip in this event is replaced.

RELATED LINKS

[Adjusting the Snap Point](#) on page 464

[Replacing Clips in Events](#) on page 187

[Cross-Hair Cursor](#) on page 81

Deleting Clips from the Pool

You can delete clips from the **Pool** with or without deleting the corresponding file from the hard disk.

Removing Clips from the Pool

PROCEDURE

1. In the **Pool** window, select the clips that you want to remove, and select **Edit > Delete**. You can also press **Backspace** or **Delete**.
 2. Depending on whether the clips are used by an event, you have the following options:
 - If the clips are used by an event, click **Remove** and then click **Remove from Pool**.
 - If the clips are not used by an event, click **Remove from Pool**.
-

RESULT

The clips are no longer available in the **Pool** for this project, but the files still exist on the hard disk and can be used in other projects, etc. This operation can be undone.

Deleting Files from the Hard Disk

To delete a file permanently from the hard disk, you must first move the corresponding clips to the **Trash** folder in the **Pool**.

IMPORTANT

Make sure that the audio files that you want to delete are not used in other projects.

PROCEDURE

1. In the **Pool** window, select the clips that you want to delete from the hard disk, and select **Edit > Delete**. You can also press **Backspace** or **Delete**, or drag the clips into the **Trash** folder.

NOTE

You can retrieve a clip or region from the **Trash** folder by dragging it back into an **Audio** or **Video** folder.

2. Depending on whether the clips are used by an event, you have the following options:
 - If the clips are used by an event, click **Remove** and then click **Trash**.
 - If the clips are not used by an event, click **Trash**.

3. Select **Media > Empty Trash**.
 4. Click **Erase**.
-

RESULT

The files are deleted from the hard disk.

Removing Unused Clips from the Pool

You can find all clips in the **Pool** that are not used in the project. This allows you to quickly remove all unused clips.

PROCEDURE

1. In the **Pool**, select **Media > Remove Unused Media**.
 2. Do one of the following:
 - To move the clips to the **Trash** folder, select **Trash**.
 - To remove the clips from the **Pool**, select **Remove from Pool**.
-

Removing Regions from the Pool

PROCEDURE

- In the **Pool**, select a region and select **Edit > Delete**.
You can also press **Backspace** or **Delete**.

IMPORTANT

You are not warned if the region is still in use.

Locating Events and Clips

You can quickly display to which clips the selected events belong and to which events the selected clips belong.

Locating Events via Clips in the Pool

You can find out which events in the project refer to a particular clip in the **Pool**.

PROCEDURE

1. In the **Pool** window, select one or more clips.
 2. Select **Media > Select in Project**.
-

RESULT

All events that refer to the selected clips are now selected in the **Project** window.

Locating Clips via Events in the Project Window

You can find out which clip belongs to a particular event in the **Project** window.

PROCEDURE

1. In the **Project** window, select one or more events.
 2. Select **Audio > Find Selected in Pool**.
-

RESULT


The corresponding clips are located and highlighted in the **Pool**.

Searching for Audio Files

The search functions help you locate audio files in the **Pool**, on your hard disk, or on other media. This works much like the regular file search, but with extra features.

PROCEDURE

1. In the **Pool** window, click **Search** on the toolbar.
A search pane appears at the bottom of the window, displaying the search functions.



2. Specify the files that you search for in the **Name** field.
You can use partial names or wildcards (*).

NOTE

Only audio files of the supported formats will be found.

3. Use the **Location** pop-up menu to specify where to search.
The pop-up menu lists all your local drives and removable media.
 - To limit the search to certain folders, select **Select Search Path**, and in the dialog that opens, select the folder in which you want to search.
The search will include the selected folder and all subfolders.

NOTE

Folders that you have recently selected using the **Select Search Path** function appear on the pop-up menu, so that you can quickly select them again.


4. Click **Search**.
The search is started and **Search** is labeled **Stop**.
 - To cancel the search, click **Stop**.When the search is finished, the files that are found are listed on the right.
 - To audition a file, select it in the list and use the playback controls to the left (Play, Stop, Pause, and Loop). If **Auto Play** is activated, selected files are automatically played back.
 - To import a file into the **Pool**, double-click the file in the list or select it and click **Import**.
 5. To close the search pane, click **Search** on the toolbar again.
-

Using the Extended Search Functionality

Apart from the search criterion **Name**, additional search filters are available. The extended search options allow for a detailed search, helping you to master even the largest sound database.

PROCEDURE

1. In the **Pool** window, click **Search** on the toolbar.
The search pane is displayed in the lower part of the **Pool** window.
2. Click the **Name** text to open the extended search pop-up menu where you can select and define a search criterion.



The menu also contains the **Add Filter** and **Presets** submenus.

The search criteria have the following parameters:

- **Name:** partial names or wildcards (*)
 - **Size:** less than, more than, equal, between (two values), in seconds, minutes, hours, and bytes
 - **Bit Depth:** 8 bit, 16 bit, 24 bit, 32 bit, 32 bit float, 64 bit float
 - **Channels:** mono, stereo, and from 3 to 16
 - **Sample Rate:** various values, choose **Other** for free setting
 - **Date:** various search ranges
3. Select one of the search criteria in the pop-up menu.
The search criterion changes to the selected criteria.
 4. Optional: To display more search options, open the extended search pop-up menu, select the **Add filter** submenu, and select an element.
 5. Optional: To save your search filter settings as a preset, open the extended search pop-up menu, select **Presets > Save Preset**, and enter a name for the preset.
Saved presets are added to the **Presets** submenu.
 6. Optional: To remove a search filter settings preset, open the extended search pop-up menu, select the preset, and then select **Remove Preset**.
-

Find Media Window

The **Find Media** window is a stand-alone window that offers the same functionality as the **Search Media** option in the **Pool**.

- To open the **Find Media** window, select **Media > Search Media**.
- To insert a clip or region into the project from the **Find Media** window, select it in the list, select **Media > Insert into Project**, and select one of the insert options.

RELATED LINKS

[Inserting Clips into a Project](#) on page 532

About Missing Files

When you open a project and one or more files are missing, the **Resolve Missing Files** dialog opens. If you click **Close**, the project opens without the missing files.

In the **Pool**, you can check which files are considered missing. This is indicated by a question mark in the **Status** column.

A file is considered missing under one of the following conditions:

- The file has been moved or renamed outside the program since you last worked with the project, and you ignored the **Resolve Missing Files** dialog when you opened the project for the current session.
- You have moved or renamed the file outside the program during the current session.
- You have moved or renamed the folder in which the missing files are located.

Locating Missing Files

PROCEDURE

1. Select **Media > Find Missing Files**.
 2. In the **Resolve Missing Files** dialog, decide if you want the program to find the file for you (**Search**) if you want to find it yourself (**Locate**), or if you want to specify in which directory the program will search for the file (**Folder**).
 - If you select **Search**, a dialog opens to let you specify which folder or disk will be scanned by the program. Click **Search Folder**, select a directory or a disk, and click **Start**. If found, select the file from the list and click **Accept**. Afterwards Cubase tries to map all other missing files automatically.
 - If you select **Locate**, a file dialog opens, allowing you to locate the file manually. Select the file and click **Open**.
 - If you select **Folder**, a dialog opens to let you specify the directory in which the missing file can be found. This might be the preferred method if you have renamed or moved the folder containing the missing file, but the file still has the same name. Once you select the correct folder, the program finds the file and you can close the dialog.
-

Reconstructing Missing Edit Files

If a missing file cannot be found, this is normally indicated with a question mark in the **Status** column in the **Pool**. However, if the missing file is an edit file (a file that is created when you process audio and stored in the Edits folder within the project folder), it may be possible for the program to reconstruct it by recreating the editing to the original audio file.

PROCEDURE

1. In the **Pool** window, locate the clips for which files are missing.
 2. Check the **Status** column. If the status of the files is "Reconstructible", the files can be reconstructed by Cubase.
 3. Select the reconstructible clips and select **Media > Reconstruct**.
-

RESULT

The editing is performed and the edit files are recreated.

Removing Missing Files from the Pool

If the **Pool** contains audio files that cannot be found or reconstructed, you may want to remove these.

PROCEDURE

- In the **Pool** window, select **Media > Remove Missing Files**.
-

RESULT

All missing files from the **Pool** and the corresponding events from the **Project** window are removed.

Auditioning Clips in the Pool

You can audition clips in the **Pool** using key commands, the **Audition** button, or by clicking in the waveform image for a clip.

- Use key commands.
If you activate the **Playback Toggle Triggers Local Preview** option in the **Preferences** dialog (**Transport** page), you can use **Space** to audition. This is the same as activating **Audition** on the toolbar.
- Select a clip and activate **Audition**.
The whole clip plays back. To stop playback, click **Audition** again.
- Click in the waveform image for a clip.
The clip plays back from the selected position in the waveform until the end. To stop playback, click **Audition** or anywhere else in the **Pool** window.

The audio is routed directly to the **Control Room** if activated (Cubase Pro only). When the Control Room is deactivated, the audio is routed to the Main Mix (the default output) bus, bypassing the settings of the audio channel, effects, and EQs. In Cubase Artist, the Main Mix bus is always used for auditioning.

NOTE

You can adjust the auditioning level with the miniature level fader on the toolbar. This does not affect the regular playback level.

If you have activated **Audition Loop** before you audition, the following happens:

- When you click **Audition** to audition a clip, the clip is repeated indefinitely until you stop playback by clicking **Audition** or **Audition Loop** again.
- When you click in the waveform image to audition, the section from the selected point to the end of the clip is repeated indefinitely until you stop playback.

Opening Clips in the Sample Editor

The Sample Editor allows you to perform detailed editing on the clip.

- To open a clip in the **Sample Editor**, double-click a clip waveform icon or a clip name in the **Media** column.
- To open a certain region of a clip in the **Sample Editor**, double-click a region in the **Pool**.
You can use this to set a snap point for a clip, for example. When you later insert the clip from the **Pool** into the project, the defined snap point allows it to be properly aligned.

RELATED LINKS

[Adjusting the Snap Point](#) on page 464

[Sample Editor](#) on page 445

Importing Media

The **Import Medium** dialog lets you import files directly into the **Pool**.

To open the dialog, select **Media > Import Medium**, or click **Import** on the **Pool** toolbar.

This opens a standard file dialog, where you can navigate to other folders, audition files, etc. The following audio file formats can be imported:

- Wave (Normal or Broadcast)
- AIFF and AIFC (Compressed AIFF)
- REX or REX 2
- FLAC (Free Lossless Audio Codec)
- SD2 (Sound Designer II) (macOS only)
- MPEG Layer 2 and Layer 3 (MP2 and MP3 files)
- Ogg Vorbis (OGG files)
- Windows Media Audio (Windows only)
- Wave 64 (W64 files)

The following characteristics are possible:

- Stereo or mono
- Any sample rate

NOTE

Files that have a different sample rate than the project sample rate are played back at the wrong speed and pitch.

- 8 bit, 16 bit, 24 bit, 32 bit, 32 bit float, or 64 bit float
- Various video formats

NOTE

You can also use the commands on the **Import** submenu of the **File** menu to import audio or video files into the **Pool**.

RELATED LINKS

[Wave Files](#) on page 926

[Importing ReCycle Files](#) on page 260

[Supported Compressed Audio File Formats](#) on page 256

[Video File Compatibility](#) on page 956

Importing Audio CDs into the Pool

You can import tracks or sections of tracks from an audio CD directly into the **Pool**. This opens a dialog in which you can specify which tracks are copied from the CD, converted to audio files, and added to the **Pool**.

- To import an audio CD to the **Pool**, select **Media > Import Audio CD**.


RELATED LINKS

[Importing Audio CD Tracks](#) on page 257

Import Options Dialog

The **Import Options** dialog allows you to specify how audio files are imported into the **Pool**.

- If you select a file in the **Import Medium** dialog and click **Open**, the **Import Options** dialog opens.



Copy Files to Working Directory

Copies the audio file to the **Audio** folder of the project, and has the clip refer to the copy.

Deactivate this option to have the clip refer to the original file in the original location. In this case, it is marked as “external” in the **Pool**.

Convert and Copy to Project if Needed

Converts the imported file if the sample rate or the bit depth differ from the settings in the **Project Setup** dialog.

Split Channels/Split Multi Channel Files

Splits stereo or multi channel audio files into a corresponding number of mono files, one for each channel, and copies the imported files to the **Audio** folder of the project.

Inserts the split files into the **Pool**.

The **Split File Name Format** pop-up menu allows you to select a naming format for the split files. This allows for compatibility with other products when exchanging audio files.

Please, don't ask again

Always imports files according to the settings, without opening the dialog again. You can reset this option in the **Preferences** dialog (**Editing—Audio** page).

RELATED LINKS

[Pool Window Columns](#) on page 528

[Converting Files](#) on page 543

[Conforming Files](#) on page 544

Exporting Regions as Audio Files

If you have created regions within an audio clip, these can be exported as separate audio files. If you have two clips that refer to the same audio file, you can create a separate audio file for each clip.

PROCEDURE

1. In the **Pool** window, select the region that you want to export.
2. Select **Audio > Bounce Selection**.
3. Select the folder in which you want the new file to be created and click **OK**.

4. If you are using the **Bounce Selection** option to create a separate audio file for a clip that refers to the same audio file as another clip, enter a name for the new audio file.
-

RESULT

A new audio file is created in the specified folder. The file has the name of the region and is automatically added to the **Pool**.

RELATED LINKS

[Creating Audio Events from Regions](#) on page 463

Changing the Pool Record Folder

All audio clips that you record in the project will end up in the **Pool Record** folder. The **Pool Record** folder is indicated by the text Record in the Status column and by a dot on the folder itself.

By default, this is the main Audio folder. However, you can create a new Audio subfolder and designate this as your **Pool Record** folder.

NOTE

The folders that you create in the **Pool** are only for organizing your files in the **Pool**. All files are recorded to the folder that you specified as the **Pool Record** Folder.

PROCEDURE

1. In the **Pool**, select the Audio folder or any audio clip.

NOTE

You cannot designate the Video folder or any of its subfolders as the **Pool Record** folder.

2. Select **Media > Create Folder**.
 3. Rename the new folder.
 4. Select the new folder and select **Media > Set Pool Record Folder**, or click in the **Status** column of the new folder.
-

RESULT

The new folder becomes the **Pool Record** folder. Any audio recorded in the project will be saved in this folder.

Organizing Clips and Folders

If you accumulate a large number of clips in the **Pool**, it can be difficult to quickly find specific items. Organizing clips in new subfolders with names that reflect the content can be a solution. For example, you could put all sound effects in one folder, all lead vocals in another, etc.

PROCEDURE

1. In the **Pool** window, select the type of folder, audio, or video for which you want to create a subfolder.

NOTE

You cannot put audio clips in a video folder and vice versa.

2. Select **Media > Create Folder**.
3. Rename the folder.

4. Drag the clips to the new folder.
-

Applying Processing to Clips in the Pool

You can apply audio processing to clips from within the **Pool** in the same way as to events in the **Project** window.

PROCEDURE

1. In the **Pool** window, select the clips that you want to process.
 2. Select **Audio > Direct Offline Processing** and select a processing method.
-

RESULT

A waveform symbol indicates that the clips have been processed.

RELATED LINKS

[Direct Offline Processing](#) on page 416

Undoing Processing

You can undo processing that has been applied to clips.

PROCEDURE

1. In the **Pool** window, select the clip from which you want to remove the processing.
 2. Select **Audio > Direct Offline Processing**.
 3. Select the action that you want to remove, and click **Delete**.
-

Minimizing Files

You can minimize the audio files according to the size of the audio clips referenced in the project. The files that are produced using this option only contain the audio file portions that are actually used in the project.

This can significantly reduce the size of the project if large portions of the audio files are unused. Therefore, the option is useful for archiving purposes after you have completed a project.

IMPORTANT

This operation will permanently change the selected audio files in the **Pool**. This cannot be undone. If you only want to create the minimized audio files as a copy, leaving the original project untouched, you can use the **Back up Project** option.

NOTE

Minimizing files clears the entire edit history.

PROCEDURE

1. In the **Pool** window, select the files that you want to minimize.
2. Select **Media > Minimize File**.
3. Click **Minimize**.
After the minimizing is finished, the file references in the stored project have become invalid.

4. Do one of the following:
 - To save the updated project, click **Save Now**.
 - To proceed with the unsaved project, click **Later**.
-

RESULT

Only the audio portions that are actually used in the project remain in the corresponding audio files in the **Pool** Record folder.

RELATED LINKS

[Backing Up Projects](#) on page 93

Importing and Exporting Pool Files (Cubase Pro only)

You can import or export a **Pool** as a separate file (file extension “.npl”).

- To import a **Pool** file, select **Media > Import Pool**.
When you import a **Pool** file, its file references are added to the current **Pool**.

NOTE

Since the audio and video files are only referenced but not saved in the **Pool** file, the **Pool** import is only useful if you have access to all referenced files. These files have preferably the same file paths as when the **Pool** was saved.

- To export a **Pool** file, select **Media > Export Pool**.

You can also save and open libraries, that is, stand-alone **Pool** files that are not associated with a project.

RELATED LINKS

[Working with Libraries \(Cubase Pro only\)](#) on page 543

Working with Libraries (Cubase Pro only)

You can use libraries to save sound effects, loops, video clips, etc., and transfer media from a library into a project by using drag and drop.

- To create a new library, select **File > New Library**.
You must specify a project folder for the new library in which media files will be stored. The library appears as a separate **Pool** window.
- To open a library, select **File > Open Library**.
- To save a library, select **File > Save Library**.

Converting Files

In the **Pool**, you can convert files to another format.


PROCEDURE

1. In the **Pool** window, select the files that you want to convert.
 2. Select **Media > Convert Files**.
 3. In the **Convert Options** dialog, make your settings and click **OK**.
-

Convert Options Dialog

In this dialog, you can convert audio files in the **Pool**.

To open the **Convert Options** dialog, select a clip in the **Pool** window, and select **Media > Convert Files**.



Sample Rate

Allows you to convert to another sample rate.

Bit Depth

Allows you to convert to 16 bit, 24 bit, 32 bit, 32 bit float, or 64 bit float.

Channels

Allows you to convert to mono or stereo interleaved.

File Format

Allows you to convert to Wave, AIFF, Wave 64, or Broadcast Wave format.

Options

You can use the **Options** pop-up menu to set one of the following options:

- **New Files**
Creates a copy of the file in the audio folder and converts this new file according to the chosen attributes. The new file is added to the **Pool**, but all clip references still point to the original, unconverted file.
- **Replace Files**
Converts the original file without changing clip references. However, the references are saved with the next save action.
- **New + Replace in Pool**
Creates a new copy with the chosen attributes, replaces the original file with the new one in the **Pool** and redirects the current clip references from the original file to the new file. Select the latter option if you want your audio clips to refer to the converted file, but want to keep the original file on disk, for example, if the file is used in other projects.

Conforming Files

You can align the file attributes with the project attributes. This is useful if the attributes of the selected files are different from the project attributes.

PROCEDURE

1. In the **Pool** window, select the clips that you want to conform.
2. Select **Media > Conform Files**.
3. Select whether to keep or replace the original unconverted files in the **Pool**.
 - If you select the **Replace** option, files in the **Pool** and in the Audio folder of the project are replaced.

- If any **Keep** option is selected, original files remain in the Audio folder of the project and new files are created.
-

RESULT

The files are conformed. Clip or event references in the **Pool** are redirected to the conformed files.

Extracting Audio from Video File

You can extract audio from video files. This automatically generates a new audio clip that appears in the **Pool** Record folder.

NOTE

This function is not available for MPEG-1 video files.

PROCEDURE

1. In the **Pool** window, select **Media > Extract Audio from Video File**.
 2. Select the video file from which you want to extract audio and click **Open**.
-

RESULT

The audio is extracted from the video file. The audio file gets the same file format and sample rate/width as in the current project, and the same name as the video file.

MediaBay

The **MediaBay** allows you to manage all your media files and presets from multiple sources.

Media Rack in Right Zone

The **Media** rack in the right zone of the **Project** window allows you to access the **MediaBay** functions from within a fixed zone of the **Project** window.

To open the **Media** rack in the right zone, do the following:

- Click **Show/Hide Right Zone**  on the **Project** window toolbar, and at the top of the right zone, click the **Media** tab.

The **Media** rack opens on the **Home** page that features different tiles that correspond to the available media types.

- Click a tile to show the corresponding media type or preset.

RELATED LINKS


[Showing/Hiding Zones](#) on page 39

[Home Page](#) on page 546

Home Page

The **Home** page  gives you access to the tiles that correspond to the available media types, to the **Favorite**, and to the **File Browser**.

Click one of the tiles to open the corresponding page in the **Media** rack:



Instruments

Shows the included VST instruments and instrument presets.

Loops & Samples

Shows audio loops, MIDI loops, or instrument sounds ordered by content set.

Presets

Shows track presets, strip presets, pattern banks, FX chain presets, and VST FX presets.

User Presets

Shows track presets, strip presets, pattern banks, FX chain presets, VST FX presets, and instrument presets that are listed in the **User Content** folder.

Favorites

Shows your favorite folders and to add new favorites. The folder content is automatically added to the **MediaBay** database.

File Browser

Shows your file system and the pre-defined folders **Favorites**, **This Computer**, **VST Sound**, **Factory Content**, and **User Content** where you can search for media files and access them immediately.

RELATED LINKS

[Loading Instrument Presets](#) on page 576

[Loading Loops and Samples](#) on page 575

[Loading Track Presets](#) on page 576

[Loading Effect Plug-In Presets](#) on page 576

[Loading FX Chain Presets](#) on page 577

[Loading Strip Presets](#) on page 577


[Loading Pattern Banks](#) on page 578

[Adding Favorites Using the Favorites Page](#) on page 552

[Adding Favorites Using the File Browser Page](#) on page 552

Favorites Page

The **Favorites** page allows you to add your own favorite folders to the **Media** rack.



1 Add Favorite

Opens a file dialog where you can navigate to the location of a folder and add it as a favorite folder.

2 Favorite Folders

The folders that you added as favorites, are shown as tiles on the **Favorites** page.

- To show the content of a folder, click it.
- To delete a folder from the **Favorites** page, click its close button.

RELATED LINKS

[Adding Favorites Using the Favorites Page](#) on page 552

Results Page

The **Results** page shows all media files that are found in the selected folder.




- 1 Media Rack Navigation Controls**
Allow you to navigate to specific folders and filter the **Results** list.
- 2 Attribute Filter**
Allows you to view and edit some of the standard file attributes found in your media files.
- 3 Results List**
Shows all media files that are found in the selected location and allows you to select a media file.
- 4 Previewer**
Allows you to preview the selected media file.

RELATED LINKS

- [Media Rack Navigation Controls](#) on page 550
- [Setting Up the Results List Columns](#) on page 557
- [Attribute Inspector](#) on page 570
- [Results Section](#) on page 557
- [Previewer Section](#) on page 562

Results Page for the File Browser

The **Results** page for the **File Browser** shows all media files that are found in the **File Browser**.



- 1 Media Rack Navigation Controls**
Allow you to navigate to specific folders and filter the **Results** list.
- 2 File Browser**
Allows you to browse and select folders.
- 3 Results List**
Shows all supported media files that are found in the selected folder and allows you to select a media file.
- 4 Previewer**

Allows you to preview the selected media file.

RELATED LINKS

[Media Rack Navigation Controls](#) on page 550

[File Browser Section](#) on page 554


[Results Section](#) on page 557

[Previewer Section](#) on page 562

Media Rack Navigation Controls

The navigation controls allow you to navigate to files and folders in the **Media** rack.

The following navigation controls are always available:



1 Search

Allows you to search media files by name or by attribute.

2 Back

Allows you to navigate back to the previous page.

3 Home

Allows you to navigate back to the **Home** page.

4 Show All Items

Shows the **Results** page for a selected tile. If no tile is selected, all media files are shown.

The following navigation controls are available on the **Results** page for all tiles, except **File Browser**.



1 Select Media Types

Allows you to select the media types that are displayed in the **Results** list.

2 Shuffle Results

Shuffles the **Results** list.

3 Reset Attribute Filter

Lights up if an attribute filter is set. Click this button to reset the attribute filter.

4 Set up Result Columns

Allows you to specify which attribute columns are displayed in the **Results** list.

5 Show/Hide Attribute Filters

Shows/Hides the **Attribute Filters** section.

The following navigation controls are only available, if you click **Show All Items**.



1 Back/Forward/Up

Up navigates to the parent folder. **Back** navigates to the previously used folder. **Forward** navigates to the most recent folder.

2 Select Defined Favorite

Allows you to select a different **Favorite** to quickly browse to the files you are looking for.

3 Include Folders and Subfolders

Activate this to show the content of folders and subfolders.

RELATED LINKS

[Home Page](#) on page 546

[Adding Favorites Using the Favorites Page](#) on page 552

[Media File Attributes](#) on page 568

Working with the Media Rack

The **Media** rack in the right zone of the **Project** window allows you to search for supported media files and included VST instruments, and add them to your project.

The controls on the different pages of the **Media** rack allow you to browse, to filter, select, and to preview you media files.

The **Favorites** page and the **File Browser** page allow you to add folders where your media files are located as **Favorites**. This helps you to quickly browse to these media files.

The tiles and controls on the different pages of the **Media** rack allow you to browse, to filter, select, and preview the content.

Once you have located the media file, the instrument, or the preset that you want to use, and selected it in the **Results** list, you can insert it into your project by using drag & drop, by using the context menu options, or by double-clicking.

RELATED LINKS

[Media Rack in Right Zone](#) on page 546

[Results Page](#) on page 548

Adding Instruments to Projects

You can use the **Media** rack to add VST instruments to your project. This works only for VST instruments contained in Cubase.

PROCEDURE

1. In the **Media** rack, click the **Instruments** tile.
2. Drag the instrument that you want to load and drop it on the track list.

NOTE

You can also drag a specific instrument preset and drop it on the track list or in the event display.

RESULT

A new instrument track with the selected instrument is added to the track list.

Adding Favorites Using the Favorites Page

You can add favorite folders to the **Favorites** page. This allows you to directly access media files in specific folders.

PROCEDURE

1. In the **Media** rack, click the **Favorites** tile.
2. At the top left of the page, click **Add Favorite** .
3. Select the folder that you want to add as a **Favorite**.
4. Click **OK**.

RESULT

On the **Favorites** page, a new tile with the specified name is added.

In the **File Browser**, a new folder with the specified name is added to the **Favorites** folder.

Adding Favorites Using the File Browser Page

You can add favorite folders using the **File Browser** page. This allows you to directly access media files in specific folders.

PROCEDURE

1. In the **Media** rack, click the **File Browser** tile.
2. In the **File Browser**, navigate to the folder that you want to add as a favorite and select it.
3. Do one of the following:
 - At the top left of the page, click **Add Favorite** .
 - Right-click the folder, and from the context menu, select **Add Favorite**.
4. In the **Set Name** dialog that opens, enter a name for the folder.
5. Click **OK**.

RESULT

In the **File Browser**, a new folder with the specified name is added to the **Favorites** folder.

On the **Favorites** page, a new tile with the specified name is added.

MediaBay Window

To open the **MediaBay** in a separate window, do one of the following:

- Select **Media > MediaBay**.
- Press **F5**.



MediaBay

The **MediaBay** is divided into the following sections:

- 1 File Browser**
Allows you to scan specific folders in your file system, and to add favorites.
- 2 Favorites**
Allows you to switch between the previously defined favorite locations.
- 3 Filters**
Allows you to filter the results list using a logical or an attribute filter.
- 4 Results**
Displays all supported media files. You can filter the list and perform text searches.
- 5 Previewer**
Allows you to preview the files shown in the results list.
- 6 Attribute Inspector (Cubase Pro only)**
Allows you to view, edit, and add media file attributes or tags.

RELATED LINKS

- [File Browser Section](#) on page 554
- [Favorites Section](#) on page 556
- [Filters Section](#) on page 566
- [Results Section](#) on page 557
- [Previewer Section](#) on page 562
- [Attribute Inspector](#) on page 570
- [Setting Up the MediaBay](#) on page 554

Setting Up the MediaBay

You can show and hide the different sections of the **MediaBay**. This saves screen space and enables you to display only the information that you need.

PROCEDURE

1. Click **Set up Window Layout** in the lower left corner of the **MediaBay**.




2. Activate/Deactivate the checkboxes for the sections that you want to show/hide.
3. Click outside the pane to exit the setup mode.

MediaBay Navigation Controls

The **MediaBay** window features controls that allow you to navigate to files and folders. These controls are always visible, even if you deactivate specific sections of the **MediaBay**.

The following navigation controls are always available in the **MediaBay** window:



- 1 **Back/Forward/Up**
Up navigates to the parent folder. **Back** navigates to the previously used folder. **Forward** navigates to the most recent folder.
- 2 **Include Folders and Subfolders**
Activate this to show the content of folders and subfolders.
- 3 **Select Defined Favorite**
Allows you to select a different **Favorite** to quickly browse to the files you are looking for.

By default, the **Back/Forward/Up** controls are shown in the **File Browser** section of the **MediaBay** window. If you also hide that section, they are shown in the **Favorites** section. If you hide that section, they are shown in the **Results** section.

Accordingly, the **Include Folders and Subfolders** button is shown in the **Favorites** section, and if you hide that section, it is shown in the **Results** section.

This allows you to navigate to files and folders at any time.

File Browser Section

The **File Browser** section allows you, to scan specific folders in your file system and to add favorites.

To show the supported media files in the **Results** section of the **MediaBay**, you must scan all folders that you want to include in the search.

You can also add favorite folders. All media files contained in a **Favorite** are automatically scanned.

RELATED LINKS

[Scanning Folders](#) on page 555


[Adding Favorites](#) on page 555

Scanning Folders

To include specific folders in the **MediaBay** search, you must scan them.

PROCEDURE

1. In the **File Browser** section of the **MediaBay**, navigate to the folder that you want to include in the scan.
2. Click the checkbox for the folder to activate the scan.



RESULT

All files that are found in the scanned folder are shown in the **Results** list. The color of the checkmark helps you to identify which folders and subfolders are scanned:

- Red indicates that a folder is currently being scanned.
- White indicates that all subfolders have been scanned.
- Orange indicates that at least one subfolder is excluded from the scan.


The scan result is saved in a database file.

Adding Favorites

You can add favorite folders using the **File Browser** section. This allows you to access media files in specific folders.

PROCEDURE

1. In the **File Browser** section, navigate to the folder that you want to add as a favorite, and select it.
2. Do one of the following:
 - At the top right of the page, click **Add Favorite** +*.



- Right-click the folder, and from the context menu, select **Add Favorite**.

3. In the **Set Name** dialog that opens, enter a name for the folder.
 4. Click **OK**.
-

RESULT

In the **File Browser** section, a new folder with the specified name is added to the **Favorites** folder.

In the **Favorites** section, the added favorite is available in the **Select Defined Favorite** pop-up menu.

In the **Media** rack in the right zone of the **Project** window, a new tile with the specified name is added on the **Favorites** page.

NOTE

All media files that a **Favorite** contains are automatically scanned. If you change the files when Cubase is closed, you must update the favorite later by right-clicking the favorite and selecting **Update Favorite** from the context menu.

AFTER COMPLETING THIS TASK

To remove a **Favorite**, select it in the **Favorites** tree of the **File Browser** section, open the context menu and select **Remove Favorite**.

Refresh Views


If you added or removed files when Cubase was closed, you must refresh the views. This also applies if you modified attributes of your user content using another program.

If you have made changes to your content and want the changes to be displayed in the **MediaBay**, you must rescan the corresponding media folders.

- To refresh a folder, in the **File Browser** section of the **MediaBay**, right-click a folder, and select **Refresh Views**.
- To display a new network drive, in the **File Browser** section of the **MediaBay**, right-click the parent node, and select **Refresh Views**. You can then scan the drive for media files.

Favorites Section

In the **Favorites** section, you can select the **Favorites** that you specified in the **File Browser** section. The contents of a **Favorite** are shown in the **Results** list.



- 1 **Select Defined Favorite**
Allows you to select a different **Favorite** to quickly browse to the files you are looking for.
- 2 **Include Folders and Subfolders**
Activate this to show the content of folders and subfolders.

RELATED LINKS

[Adding Favorites](#) on page 555

[Favorites Page](#) on page 548

[File Browser Section](#) on page 554

Results Section

The **Results** list shows all media files that are found in the selected folder in the **File Browser**.

NOTE

To show media files in the **Results** section, you must select a scanned folder in the **File Browser** section of the **MediaBay**.



NOTE


You can set the maximum number of files that are displayed in the **Results** list in the **MediaBay Settings**.

Setting Up the Results List Columns

For each media type, or for combinations of media types, you can specify the attribute columns that are displayed in the **Results** list.

PROCEDURE

1. In the **Results** section, select the media types for which you want to make settings.
2. Click **Set up Result Columns** and activate or deactivate the options on the submenus.



To exclude a particular category, select **Select None** on the corresponding submenu.

If **Allow Editing in Results List** is activated in the **MediaBay Settings**, you can also edit attributes in the **Results** list. Otherwise, this is only possible in the **Attribute Inspector**.

RELATED LINKS

[Setting Up the MediaBay](#) on page 554

[Attribute Inspector](#) on page 570

Managing Media Files in the Results List

- To move or copy a file from the **Results** list to another location, drag it to another folder in the **File Browser** section.
- To change the order of the columns in the **Results** list, click a column header and drag that header to another position.
- To delete a file, right-click it in the list and select **Delete**. The file is permanently deleted from your computer.

IMPORTANT

If you delete a file using the File Explorer/macOS Finder, it is still displayed in the **Results** list, although it is no longer available to the program. To remedy this, rescan the corresponding folder.

Shuffling the Results List

You can display the **Results** list entries in a random order.

- To shuffle the **Results** list, click **Shuffle Results**  in the **MediaBay**.

Finding the Location of a File

You can show the location of a file on your system in the File Explorer/macOS Finder.

NOTE

This function is not available for files which are part of a VST Sound archive.

PROCEDURE

- In the **Results** list, right-click a file, and select **Show in Explorer/Reveal in Finder**.
-

RESULT


The File Explorer/macOS Finder opens and the corresponding file is highlighted.

Filtering According to Media Type

You can set up the **Results** list to display only a particular media type or a combination of media types.

PROCEDURE

1. In the **Results** section, click **Select Media Types**.




2. Activate the media types that you want to be displayed in the **Results** list.
-

RESULT

The files are filtered by the selected media type.

Show Media Types Selector

You can activate the media types that you want to be displayed in the **Results** list.



The following media types are available:

Audio Files

If this option is activated, the list shows all audio files. The supported formats are .wav, .w64, .aiff, .aifc, .rex, .rx2, .mp3, .mp2, .ogg, .sd2 (macOS only), .wma (Windows only).

MIDI Files

If this option is activated, the list shows all MIDI files (file name extension .mid).

MIDI Loops

If this option is activated, the list shows all MIDI loops (file name extension .midiloop).

Pattern Banks

If this option is activated, the list shows all pattern banks (file name extension .patternbank). Pattern banks are generated via the MIDI plug-in **Beat Designer**. For more information, see the separate document **Plug-in Reference**.

Track Presets

If this option is activated, the list shows all track presets for audio, MIDI, and instrument tracks (file name extension .trackpreset). Track presets are a combination of track settings, effects, and **MixConsole** settings that can be applied to new tracks of various types.

Plug-in Presets

If this option is activated, the list shows all VST presets for instrument and effect plug-ins. Furthermore, EQ presets that you save in the **MixConsole** are listed. These presets contain all parameter settings for a particular plug-in. They can be used to apply sounds to instrument tracks and effects to audio tracks.

Strip Presets

If this option is activated, the list shows all strip presets (file name extension .strippreset). These presets contain channel strip effect chains.

FX Chain Presets

If this option is activated, the list shows all effect chain presets (file name extension .fxchainpreset). These presets contain insert effect chains.

Video Files

If this option is activated, the list shows all video files.

Projects

If this option is activated, the list shows all project files (from Cubase, Nuendo): .cpr, .npr.

RELATED LINKS

[Previewing Pattern Banks](#) on page 565

[Track Presets](#) on page 179

[Saving/Loading Strip Presets](#) on page 358

[Saving/Loading EQ Presets](#) on page 351

[Saving/Loading FX Chain Presets](#) on page 348

[Video File Compatibility](#) on page 956

Filtering According to Rating

With the **Rating Filter**, you can filter files according to their rating.

NOTE

The **Rating Filter** is not available in the **Media** rack in the right zone.

PROCEDURE

- In the **Results** section of the **MediaBay**, drag the **Rating Filter** to the left or right, or click the asterisk to display all media files regardless of their rating.




Performing a Text Search

You can perform a text search in the **Results** list. If you enter text in the text search field, only media files whose attributes match the entered text are displayed.

NOTE

The **Search** field has the same function as the **matches** operator of the logical filter. However, the search is applied to all file attributes.

- Click the field and enter the text that you want to find.
For example, if you are looking for all audio loops relating to drum sounds, enter “drum” in the search field. The search results will contain loops called “Drums 01”, “Drumloop”, “Snare Drum”, etc. In addition, all media files with the **Drum&Percussion** category attribute or any other attribute that contains “drum” are found. You can also add apostrophes to find exact matches for the entered words and use boolean operators.



- To reset the text search, delete the text.

RELATED LINKS

[Logical Filter](#) on page 566

Boolean Text Search

You can perform advanced searches, using boolean operators or wildcards.

The following elements can be used:

And [+]

[a and b]

When entering strings separated by “and” (or a plus sign), all files are found that contain both a and b.

[And] is the default setting when no boolean operator is used, for example, you can also enter [a b].

Or [,]

[a or b]

When entering strings separated by “or” (or a comma), files are found that contain either a or b, or both.

Not [-]

[not b]

When entering text preceded by “not” (or a minus sign), all files not containing b are found.

Parentheses [()]

[(a or b) + c]

Using parentheses, you can group text strings. In this example, files are found that contain c and either a or b.

Quotation marks [“”]

[“example text”]

With quotation marks, you can define sequences of several words. Files are found if they contain this sequence of words.

IMPORTANT

When you are searching for files whose names contain a hyphen, put the search text in quotation marks. Otherwise the program treats the hyphen as the boolean operator “not”.

NOTE

These operators can also be used for logical filtering.

RELATED LINKS

[Applying a Logical Filter](#) on page 567

Resetting the Results List

You can reset all filter settings and filter results.

- To reset the **Results** list, click **Reset Result Filters**  in the **MediaBay**.

Previewer Section

You can preview individual files in the **Previewer** section to find out which one to use in your project.

The elements visible in this section and their functions depend on the media type.


IMPORTANT

The **Previewer** section is not available for video files, project files, and audio track presets.

RELATED LINKS

[MediaBay Settings](#) on page 582

Previewing Audio Files



1 Transport Controls

Allow you to start, stop, pause, and cycle the preview.

2 Preview Level Fader

Allow you to specify the preview level.

3 Auto Play New Results Selection

If this option is activated, the selected file is automatically played back.

4 Align Beats to Project

If this option is activated, the selected file is played back in sync with the project, starting at the project cursor position. Note that this can apply realtime time stretching to your audio file.

NOTE

If you import an audio file into your project for which **Align Beats to Project** is activated in the **Previewer**, **Musical Mode** is automatically activated for the corresponding event.

5 Wait for Project Play

If this option is activated, the play and stop functions from the **Transport** panel are synchronized with the play and stop buttons in the **Previewer** section.

To use this option to its full extent, set the left locator at the beginning of a bar, then start playing back the project using the **Transport** panel. The loops that you now select in the **Results** list start together with the project in perfect sync.


RELATED LINKS

[Musical Mode](#) on page 475

Previewing MIDI Files

IMPORTANT

To preview a MIDI file, you must load a VST instrument and select it as output device from the **Output** pop-up menu.



- 1 Transport Controls**
Allow you to start and stop the preview.
- 2 Preview Level Fader**
Allows you to specify the preview level.
- 3 Output**
Allows you to select the output device.
- 4 Auto Play New Results Selection**
If this option is activated, the selected file is automatically played back.
- 5 Align Beats to Project**
If this option is activated, the selected file is played back in sync with the project, starting at the project cursor position. Note that this can apply realtime time stretching to your MIDI file.

RELATED LINKS

[VST Instruments](#) on page 628

Previewing MIDI Loops

NOTE

MIDI loops are always played back in sync with the project.



- 1 Transport Controls**
Allows you to start and stop the preview.
- 2 Preview Level Fader**
Allows you to specify the preview level.
- 3 Auto Play New Results Selection**
If this option is activated, the selected file is automatically played back.
- 4 Link Playback to Chord Track**
If this option is activated, the events of the MIDI loop are transposed to play back in context with the chord track. Note that you need a chord track with chord events for this.
If this option is activated, and you insert a MIDI loop into the project, **Follow Chord Track** is automatically activated for the track.

RELATED LINKS

[Using Follow Chord Track](#) on page 831

Previewing VST Presets and Track Presets for MIDI and Instrument Tracks

To preview track presets for MIDI or instrument tracks and VST presets, you need some MIDI notes. These notes can be sent to the track preset via MIDI Input, using a MIDI file, the **Memo Recorder** mode, or via the computer keyboard.



On-Screen keyboard in keyboard display mode

- 1 Transport Controls**
Allows you to start and stop the preview.
- 2 Previewer Sequence Mode Menu**
Allows you to load a MIDI file to apply the selected preset to the MIDI file. You can also select the **Memo Recorder** mode that continually repeats a given sequence of notes as a loop.
- 3 Preview Level Fader**
Allows you to specify the preview level.
- 4 On-Screen Keyboard**
You can display the **On-Screen Keyboard** in the keyboard display mode or in the piano display mode.
- 5 Computer Keyboard Input**
If this option is activated, you can use your computer keyboard to preview the presets.

RELATED LINKS

[Previewing Presets Using the Memo Recorder Mode](#) on page 565

[On-Screen Keyboard](#) on page 234

Previewing Presets Via MIDI Input

MIDI input is always active, for example, when a MIDI keyboard is connected to your computer and set up properly, you can directly start playing the notes to preview the selected preset.

Previewing Presets Using a MIDI File

PROCEDURE

1. On the **Previewer Sequence Mode** pop-up menu, select **Load MIDI File**.
 2. In the file dialog that opens, select a MIDI file and click **Open**.
The name of the MIDI file is displayed on the pop-up menu.
 3. Click **Play** to the left of the pop-up menu.
-

RESULT

The notes received from the MIDI file are played back with the settings of the track preset applied.

NOTE

The recently used MIDI files are kept on the menu for quick access. To remove an entry from this list, select it on the menu and then select **Remove MIDI File**.

Previewing Presets Using the Memo Recorder Mode

The **Memo Recorder** mode continually repeats a given sequence of notes as a loop.

NOTE

You cannot use the **Memo Recorder** mode when previewing presets using a MIDI file.

PROCEDURE

1. On the **Previewer Sequence Mode** pop-up menu, select **Memo Recorder**.
 2. Activate **Play**.
 3. Play some notes on the MIDI keyboard or on the computer keyboard.
-

RESULT

The notes are played back with the instrument preset that is selected in the **Results** section.

When you stop playing notes and wait for 2 seconds, the note sequence that you played until this moment is played back in a continuous loop.

To use another sequence, start entering notes again.

Previewing Presets Via the Computer Keyboard

NOTE


If you activate **Computer-Keyboard Input**, the computer keyboard is used exclusively for the **Previewer** section. However, you can still use the following key commands: **Ctrl/Cmd-S** (Save), **Num *** (Start/Stop Record), **Space** (Start/Stop Playback), **Num 1** (Jump to left locator), **Delete** or **Backspace**, **Num /** (Cycle on/off), and **F2** (Show/Hide Transport panel).

PROCEDURE

1. Activate **Computer-Keyboard Input**.
 2. Play some notes on the computer keyboard.
-

Previewing Pattern Banks

Pattern banks containing drum patterns can be created with the MIDI plug-in **Beat Designer**.



1 Transport Controls

Allow you to start and stop the preview.

2 Preview Level Fader

Allows you to specify the preview level.

3 Keyboard

The keyboard allows you to preview the selected pattern bank. In the **Previewer** section, choose a subbank (the number at the top) and pattern (a key), and click **Play**.

One pattern bank contains 4 subbanks which in turn contain 12 patterns each.

Subbanks can contain empty patterns. Selecting an empty pattern in the **Previewer** section has no effect. Patterns containing data are indicated by a circle in the upper part of the key in the display.

4 Auto Play New Results Selection

If this option is activated, the selected file is automatically played back.

NOTE

You can find detailed information on the **Beat Designer** and its functions in the separate document **Plug-in Reference** in the **MIDI Effects** chapter.

Filters Section

The **MediaBay** allows you to refine your file searches. You have two possibilities: **Logical** or **Attribute** filtering.

Logical Filter

The logical filter allows you to set up complex search conditions that must be met to find files.

NOTE

The **Logical Filter** is not available in the **Media** rack in the right zone.



contains

The search result must contain the text or number specified in the text field to the right.

matches words

The search result must match the words specified in the text field to the right.

omits

The search result must not contain the text or number specified in the text field to the right.

equals

The search result must correspond exactly to the text or number specified in the text field to the right, including any file extension. Text searches are not case-sensitive.

>=

The search result must be higher than or equal to the number specified in the field to the right.

<=

The search result must be lower than or equal to the number specified in the field to the right.

is empty

Use this option to find files for which certain attributes have not been specified yet.

matches

The search result must include the text or number entered in the text field to the right. You can also use boolean operators. Add apostrophes to find exact matches

for the entered words, for example, 'drum' AND 'funky'. This option allows for a very advanced text search.

range

If this option is selected, you can specify a lower and an upper limit for the search result in the fields to the right.

Applying a Logical Filter


To quickly find certain audio files, you can search for a specific file attribute value, for example.

PREREQUISITE

In the **Favorites** section, select the defined **Favorite** in which you want to search for files.

PROCEDURE

1. In the **Filters** section, activate **Logical**.
2. Click **Search in these Attributes** to open the **Select Filter Attributes** dialog.
3. Select the attributes that you want to use.
If you select more than one attribute, the files found match either one or the other attribute.
4. Click **OK**.
5. On the condition pop-up menu, select one of the search operators.



6. Enter the text or number that you want to find in the field to the right.

NOTE

If you enter 2 or more strings or filter lines, the files that are found match all strings or filter lines.

- To add more than one string in the text field, enter a **Space** between them.
 - To add another filter line, click **+** to the right of the text field. You can add up to seven filter lines in which you can define further search conditions.
 - To remove a filter line, click **-**.
 - To reset all search fields to their default settings, click **Reset Filter** in the top right corner of the **Filters** section.
-

RESULT

The **Results** list is automatically updated, showing only the files that correspond to your search conditions.

Advanced Text Search

You can perform advanced text searches using boolean operators.

PREREQUISITE

In the **Favorites** section, select the defined **Favorite** in which you want to search for files.

PROCEDURE

1. In the **Filters** section, activate **Logical**.
2. Select an attribute on the **Select Filter Attributes** pop-up menu or keep the **Any Attribute** setting on.
3. Set the condition to **matches**.
4. Specify the text that you want to search for in the field to the right using boolean operators.

RELATED LINKS

[Performing a Text Search](#) on page 560

Media File Attributes

Media file attributes are sets of meta data providing additional information on the file.

The different types of media files have different attributes. For example, .wav audio files have attributes, such as name, length, size, sample rate, content set, etc., while .mp3 files have additional attributes, such as artist or genre.

RELATED LINKS

[Attribute Inspector](#) on page 570

Attribute Filter

Assigning attribute values to your files facilitates organizing your media files. The **Attribute** filter allows you to view and edit some of the standard file attributes that are found in your media files.

If you click **Attribute**, the **Filters** section displays all values that have been specified for the displayed attribute categories. Selecting one of these values displays only the files to which this attribute value is assigned.

Category	Tempo	Style	Sub Style	Sample Rate	File Type
Accordion	75.000	Alternative/Indie	80's Pop	32000.00	AIFF File
Bass	75.001	Ambient/ChillOut	Acoustic Blues	40000.00	Broadcast Wave F
Brass	75.002	Blues	Africa	44099.00	Midi Loop File
Chromatic Perc	76.000	Classical	Alternative Rock	44100.00	Strip Preset
Drum&Perc	77.000	Country	Asia	48000.00	Track Preset File

1 Attribute column titles

Allow you to select different attribute categories. If the columns are wide enough, the number of files that match this criteria is displayed to the right of the value.

2 Attribute values

Displays the attribute values and how often a certain attribute value is available among your media files.

NOTE

- Some attributes are directly linked to each other. For example, for each category value, there are certain sub-category values available. Changing the value in one of these attribute columns displays different values in the other column.
- Each attribute column displays only the attribute values that are found in the selected location.

RELATED LINKS

[Attribute Inspector](#) on page 570

Applying an Attribute Filter

With the **Attribute** filter, you can quickly find tagged media files with certain attributes.

- To apply an **Attribute** filter, select an attribute value. The **Results** list is filtered accordingly. Apply more attribute filters to narrow down the result even more.
- To find files that match either one or the other attribute, **Ctrl/Cmd**-click different attribute values in the same column.
- To change the displayed attribute values of a column, click the attribute column title and select another attribute.


NOTE

Character attributes always form an AND condition.

Performing a Context Menu Search

You can search for other files that have the same attribute as the selected file. This allows you to find all the files that have a value in common, for example, if you want to view all the files that were created on the same day.

- In the **Results** list or the **Attribute Inspector**, right-click a file and select the attribute value for which you want to search from the **Search for** submenu.



The **Filters** section automatically switches to **Logical** filtering and the corresponding filter condition line is displayed.

- To reset the filter, click **Reset Result Filters**.

Resetting the Filter

PROCEDURE

- To reset the filter, click **Reset Filter** at the top of the **Filters** section.



This also resets the **Results** list.

Attribute Inspector


When you have selected one or more files in the **Results** list, the **Attribute Inspector** shows a list of attributes and their values.

NOTE

The **Attribute Inspector** is not available in the **Media** rack in the right zone.

In the **Attribute Inspector**, you can also edit and add new attribute values.

The available attributes are divided into several groups (Media, Musical, Preset, etc.), to keep the list manageable and to facilitate finding items.



Dynamic

Displays all available values for the selected files.

Defined


Displays a configured set of attributes for the selected media type regardless of whether corresponding values are available for the selected files.

Configure Defined Attributes

Activates the configuration mode, in which you can set up the attributes that are displayed in the **Attribute Inspector**.

Configuration Mode

When you click **Configure Defined Attributes**, the configuration mode is enabled.



Select Media Types

Allows you to select one or several media types. You can then manage which attributes are displayed in the **Attribute Inspector** for the selected media types.

+/-

Opens the **Add User Attribute** dialog, where you can add or remove custom user attributes. You can select the **Attribute Type** and the **Display Name**.

Reset to Default

Resets the attribute list to the default settings.

Attribute

Shows the attribute name.

Select

Shows whether an attribute is activated or deactivated.

Type

Shows whether the value for an attribute is a number, text, or a Yes/No switch.

Precision

Shows the number of decimals displayed for number attributes.

RELATED LINKS

[Media File Attributes](#) on page 568

[Managing Attribute Lists](#) on page 574

Color Legend in the Attribute Inspector

The color of an attribute value indicates if and in which form you can edit an attribute.

White

One or more files are selected in the **Results** list, and they have the same values.

Yellow

Multiple files are selected in the **Results** list, and their values differ.

Orange

Multiple files are selected in the **Results** list, with differing values, and they cannot be edited.

Red

One or more files are selected in the **Results** list, and their values cannot be edited.



Information on the meaning of the colors that are used in the **Attribute Inspector** is also displayed in a tooltip when you move the mouse pointer over one of the color icons below the **Attribute Inspector**.

Editing Attributes

The search functions, especially the attribute filter, are a powerful media management tool when making extensive use of tagging, that is, when adding and editing attributes.

Media files are usually organized in complex folder structures to provide a logical way of guiding the user to certain files, with the folder and/or file names indicating the instrument, style, tempo, etc.

Tags help you to find a particular sound or loop in such a folder structure.

Editing Attributes in the Attribute Inspector

In the **Attribute Inspector**, you can edit attribute values of the various media files. Attribute values can be chosen from pop-up lists, entered as text or numbers, or set to Yes or No.

NOTE

- Changing an attribute value in the **Attribute Inspector** permanently changes the corresponding file unless the file is write-protected or part of a VST Sound archive.
- Some attributes cannot be edited. In this case, the file format probably does not permit changing this value, or changing a particular value makes no sense. For example, you cannot change the file size in the **MediaBay**.

PROCEDURE

1. In the **Results** list, select the file for which you want to make settings.
The corresponding attribute values are displayed in the **Attribute Inspector**.
You can also select several files and make settings for them simultaneously. The only exception is the name attribute, which must be unique for every file.
2. In the **Attribute Inspector**, click in the **Value** column for an attribute.
Depending on the selected attribute, the following happens:
 - For most of the attributes, a pop-up menu opens from which you can choose a value. Some of the pop-up menus also have a "more..." entry to open a window with more attribute values.
 - For the **Rating** attribute, you can click in the **Value** column and drag left or right to modify the setting.
 - For the **Character** attribute (Musical group), the **Edit Character** dialog opens. To define values, click a radio button on the left or the right side and then click **OK**.
3. Set the attribute value.
To remove the attribute value from the selected files, right-click in the corresponding **Value** column and select **Remove Attribute** from the context menu.

Editing Attributes in the Results List

You can edit attributes directly in the **Results** list. This allows you to assign attributes to a number of loop files, for example.

PREREQUISITE

Allow Editing in Results List must be activated in the **MediaBay Settings**.

PROCEDURE

1. In the **Results** list, select the files for which you want to make settings.
You can make settings for several files simultaneously, except for the attribute name, which must be unique for every file.
 2. Click in the column for the value that you want to change and make the settings.
-

RELATED LINKS

[MediaBay Settings](#) on page 582

Editing Attributes of Multiple Files Simultaneously

You can edit attributes for multiple files at the same time.

NOTE


If you edit a large number of files simultaneously, the processing of your edits may take some time.

Editing attributes is executed in the background so that you can continue with your work as usual. The **Attribute Counter** above the **Results** list displays how many files are still being updated.

Editing Attributes of Write-Protected Files

Media files can be write-protected due to a number of reasons: the content could have been provided by someone who write-protected the files, the file format could restrict write operations by the **MediaBay**, etc.

In the **MediaBay**, the write protection status of files is shown as an attribute in the **Attribute Inspector** and in the **Write Protection** column in the **Results** list.



IMPORTANT

You can define attribute values of write-protected files in the **MediaBay**. These changes are only saved in the **MediaBay** database file, they are not saved to disk. This means that if you delete your program preferences, these changes are lost.

NOTE

If the **Write Protection** and/or the **Pending Tags** columns are not visible, activate the corresponding attributes for the file type in the **Attribute Inspector**.

- To set or remove the write protection attribute for a file, right-click the file in the **Results** list and select **Set/Remove Write Protection**.
This is only possible if the file type allows write operations and if you have the necessary operating system permission.
- When you specify attribute values for a file that is write-protected, this is reflected in the **Pending Tags** column next to the **Write Protection** column in the **Results** list.
If you rescan the **MediaBay** content and a media file on your hard disk has changed since the last scan, the pending tags for this file will be lost.

- If a file has pending tags, and you want to write the corresponding attributes to the file, you must remove the write protection, then right-click the file, and select **Write Tags to File**.

NOTE

If you use other programs than Cubase to change the write-protection status of files, you must rescan the files in the **MediaBay** to reflect these changes.

RELATED LINKS

[Disabling the Preferences](#) on page 1006


[Editing Attributes](#) on page 572

Managing Attribute Lists

In the **Attribute Inspector**, you can define which attributes are displayed in the **Results** list and in the **Attribute Inspector** itself. For different media types, you can configure individual attribute sets.

PROCEDURE

1. In the **Attribute Inspector**, click **Defined**.
2. Click **Configure Defined Attributes** to enter configuration mode.



3. Open the **Show** pop-up menu, activate the media types that you want to display, and click anywhere in the **MediaBay**.



The **Attribute Inspector** now shows a list of all attributes available for these media types.

- If you have activated more than one media type, your settings affect all selected types. An orange checkmark indicates that the current display settings for an attribute differ for the selected media types.
 - The display settings made for the **Mixed Media Types** option are applied if you select files of different media types in the **Results** list or in the **Attribute Inspector**.
4. Activate the attributes that you want to be displayed.
You can edit several attributes simultaneously.
 5. Click **Configure Defined Attributes** again to exit the configuration mode.
-

Defining User Attributes

You can define your own attributes and save these in the **MediaBay** database and the corresponding media files. Cubase recognizes all user attributes that are included in media files.

PROCEDURE

1. In the **Attribute Inspector**, activate **Defined**.
2. Click **Configure Defined Attributes** to enter configuration mode.



3. Click **+**.
 4. In the **Add User Attribute** dialog, specify the **Attribute Type** and the **Display Name**. The display name must be unique in the attribute list. The **Database Name** field indicates if a certain name is valid or not.
 5. Click **OK**.
-

RESULT

The new attribute is added to the list of available attributes and is displayed in the **Attribute Inspector** and the **Results** list.

Working with the MediaBay

When you work with many music files, the **MediaBay** helps you to find and organize your content. After scanning your folders, all found media files of the supported formats are listed in the **Results** section.

You can set up **Favorites**, that is, folders or directories on your system that contain media files. Usually, files are organized in a specific way on your computer. You might have folders reserved for audio content, folders for special effects, folders for combinations of sounds making up the ambience noise that you need for a certain film take, etc. These can all be set as different **Favorites** in the **MediaBay**, allowing you to limit the files available in the **Results** list according to context.

By using the search and filter options, you can narrow down the results.

You can insert the files into your project by using drag & drop, by double-clicking, or by using the context menu options.

Using Media Files

The **MediaBay** window and the **Media** rack in the right zone of the **Project** window offer you multiple possibilities to search for specific files, loops, samples, presets, and patterns that you can use in your project.

Once you have found the media files that you were looking for, you can load them into your project.

Loading Loops and Samples

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **MIDI Files**, **Audio Files**, or **MIDI Loops**, and select a media file.
 - In the **Media** rack in the right zone, click the **Loops & Samples** tile, and click the following tiles until you can select the media files in the **Results** list.
 2. Do one of the following:
 - Double-click a media file to create a new instrument or an audio track with the loaded file.
 - Drag the media file and insert it on a track in the event display.
-

RESULT

The media file is inserted on the new track or at the insert position.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Loading Track Presets

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **Track Presets**, and select a preset.
 - In the **Media** rack in the right zone, click **Presets > Track Presets**, and click the following tiles until you can select the preset in the **Results** list.
 2. Do one of the following:
 - Double-click the track preset to create a new track with the loaded preset.
 - Drag the track preset and insert it on a track to apply the preset to the track.
-

RESULT

The preset is applied to the track, and all settings of the preset are loaded.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Loading Instrument Presets

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **Plug-in Presets**, and select a preset for an instrument plug-in.
 - In the **Media** rack in the right zone, click the **Instruments** tile, and click the following tiles until you can select the preset in the **Results** list.
 2. Do one of the following:
 - Double-click the instrument preset to create a new instrument track with the loaded instrument preset.
 - Drag the instrument preset and drop it on the track list to create a new instrument track with the loaded instrument preset.
 - Drag the instrument preset and drop it in the event display to create a new instrument track with the loaded instrument preset.
 - Drag the instrument preset and drop it on an instrument track to apply the preset to the track.
-

RESULT

The instrument is loaded as a track instrument, and the preset is applied to the instrument track.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Loading Effect Plug-In Presets

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **Plug-in Presets**, and select a preset.

- In the **Media** rack in the right zone, click **Presets > VST FX Presets**, and click the following tiles until you can select the preset in the **Results** list.
2. In the **Project** window, select an audio track.
 3. Drag the plug-in preset from the **MediaBay** and insert it on the open **Inserts** section of the **Inspector**.
-

RESULT

The effect plug-in preset is applied to the audio track and the settings are loaded.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Loading FX Chain Presets

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **FX Chain Presets**, and select a preset.
 - In the **Media** rack in the right zone, click **Presets > FX Chain Presets**, and click the following tiles until you can select the preset in the **Results** list.
 2. In the **Project** window, select an audio track.
 3. Drag the preset from the **MediaBay** and drop it on the open **Inserts** section of the **Inspector**.
-

RESULT

The **FX Chain Preset** is applied to the track, and all settings of the preset are loaded. Any inserts that have previously been loaded are overwritten.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Loading Strip Presets

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **Strip Presets**, and select a preset.
 - In the **Media** rack in the right zone, click **Presets > Strip Presets**, and click the following tiles until you can select the preset in the **Results** list.
 2. In the **Project** window, select an audio track.
 3. Drag the preset from the **MediaBay** and drop it on the open **Strip** section of the **Inspector**.
-

RESULT

The strip preset is applied to the track, and all settings of the preset are loaded.

RELATED LINKS

[Show Media Types Selector](#) on page 559

[Saving/Loading Strip Presets](#) on page 358

Loading Pattern Banks

PROCEDURE

1. Do one of the following:
 - In the **MediaBay**, open the media types selector, click **Pattern Banks**, and select a preset.
 - In the **Media** rack in the right zone, click **Presets > Pattern Banks**, and click the following tiles until you can select the preset in the **Results** list.
 2. Do one of the following:
 - Double-click the pattern bank to create a new instrument track with the loaded preset.
 - Drag the pattern bank and drop it on an instrument track to apply the pattern bank to the track.
 - Drag the pattern bank and drop it on the track list to create a new instrument track with the loaded pattern bank.
-

RESULT

Groove Agent is loaded as a track instrument. A drum map is loaded for the instrument track, and an instance of the **Beat Designer** is loaded as an insert effect.

RELATED LINKS

[Show Media Types Selector](#) on page 559

Working with MediaBay-Related Windows


The **MediaBay** concept can be found throughout the program, for example, when you add new tracks or when you choose presets for VST instruments or effects. The workflow in all **MediaBay**-related windows is the same as in the **MediaBay**.

Adding Tracks

If you add a track by selecting **Project > Add Track**, the following dialog opens:



Click **Browse** to expand the dialog to show the **Results** list. Only file types that can be used in this context are shown.




Applying Track Presets

You can choose from a variety of track presets.

PROCEDURE

1. In the **Inspector**, click the **Preset Management** icon on the right of the **Inserts** section.



2. Select **From Track Preset**.
3. In the **Results** browser, double-click a track preset to apply it.

RELATED LINKS

[Track Presets](#) on page 179

Applying Instrument Presets

When working with VST instruments, you can choose from a variety of presets via the **Results** browser.

PROCEDURE

1. In the track list, right-click the instrument track and select **Load Track Preset**.
2. In the **Results** browser, double-click a preset to apply it.

Instrument Presets Results Browser

The **Results** browser for instrument track presets allows you to preview VST presets and apply them to your instrument track.

To open the **Results** browser, right-click an instrument track, and select **Load Track Preset**.



VST presets for instruments can be divided into the following groups:

Presets

Presets contain the settings of the entire plug-in. For multi-timbral instruments, this includes the settings for all sound slots as well as the global settings.

Programs

Programs contain only the settings for one program. For multi-timbral instruments, this includes only the settings for one sound slot.

Working with Volume Databases

Cubase saves all media file information that is used in the **MediaBay**, such as paths and attributes, in a local database file on your computer. However, in some cases, it might be necessary to browse and manage this kind of metadata on an external volume.

For example, a sound editor might have to work both at home and in a studio, on two different computers. Therefore, the sound effects are stored on an external storage medium. To be able to connect the external device and directly browse its contents in the **MediaBay** without having to scan the device, you have to create a volume database for the external device.

Volume databases can be created for your computer drives or for external storage media. They contain the same kind of information about the media files on these drives as the regular **MediaBay** database.

NOTE

When you launch Cubase, all available volume databases are automatically mounted. Databases that are made available while the program is running have to be mounted manually.

Rescanning Volume Databases

If you have modified the data on your external volume on a different system, you must rescan the **MediaBay**.


RELATED LINKS

[Refresh Views](#) on page 556

Creating a Volume Database

PROCEDURE

- In the **File Browser** section, right-click the external storage medium, drive, or partition of your computer system for which you want to create a database, and select **Create Volume Database**.




IMPORTANT

You must select the topmost directory level for this. You cannot create a database file for a lower-level folder.

RESULT

The file information for this drive is written into a new database file. When the new database file is available, this is reflected by the symbol to the left of the drive name.



NOTE

If the drive contains a large amount of data, this process may take some time.

Volume databases are automatically mounted when Cubase is launched. They are shown in the **File Browser** section and their data can be viewed and edited in the **Results** list.

Removing a Volume Database

If you have worked on another computer using an external hard disk and return to your own computer and connect the external device again as part of your system setup, you no longer need a separate volume database for it. Any data on this drive can be included in the local database file again, by removing the extra database file.

PROCEDURE

- In the **File Browser** section, right-click the volume database and select **Remove Volume Database**.
-

RESULT

The metadata is integrated in the local **MediaBay** database file, and the volume database file is deleted.

NOTE

If the drive contains a large amount of data, this process may take some time.

Mounting and Unmounting Volume Databases

Volume databases that are made available while Cubase is running must be mounted manually.

- To mount a volume database manually, right-click the external storage medium, drive, or partition of your computer system that you want to mount and select **Mount Volume Database**.
- To unmount a volume database, right-click it and select **Unmount Volume Database**.

MediaBay Settings

- To open a pane with settings for the **MediaBay**, click **MediaBay Settings** in the lower left corner of the **MediaBay**.



Hide Folders That Are Not Scanned

If this option is activated, all folders that are not scanned for files are hidden. This keeps the tree view in the **File Browser** less cluttered.

Show Only Selected Folder

If this option is activated, only the selected folder and its subfolders are shown.

Scan Folders Only When MediaBay Is Open

If this option is activated, Cubase only scans for media files when the **MediaBay** window is open.

If this option is deactivated, the folders are scanned in the background even when the **MediaBay** window is closed. However, Cubase never scans folders while playing back or recording.

Maximum Items in Results List

Specifies the maximum number of files that are displayed in the **Results** list. This avoids unmanageably long lists of files.

NOTE

The **MediaBay** does not warn you if the maximum number of files has been reached. There might be situations where a certain file cannot be found because the maximum number of files was reached.

Allow Editing in Results List

If this option is activated, you can edit attributes in the **Results** list. If this option is deactivated, attributes can only be edited in the **Attribute Inspector**.

Show File Extensions in Results List

If this option is activated, file name extensions are displayed in the **Results** list.

Scan Unknown File Types

When scanning for media files, the **MediaBay** ignores files with an unknown file extension. If this option is activated, the **MediaBay** tries to open and scan any file in the search location and ignores those files that cannot be recognized.

MediaBay Key Commands

You can display the available **MediaBay** key commands from within the **MediaBay** window. This is useful if you want to get a quick overview over the assigned and the available **MediaBay** key commands.

- To open the key commands pane, click **Key Commands** in the lower left corner of the **MediaBay**.



- To close the key commands pane, click anywhere outside of the pane.
- To assign or modify a key command, click the corresponding key command.

RELATED LINKS

[Key Commands](#) on page 973

Surround Sound (Cubase Pro only)

Cubase provides integrated surround sound features with support for several formats. All audio-related channels and busses can handle multi-channel speaker configurations. A channel in the **MixConsole** can contain either complete surround mixes or an individual speaker channel which is part of a surround setup.

Cubase offers the following surround-related features:

- You can route audio-related tracks, that is audio, instrument, and sampler tracks, to surround channels.
- The **VST MultiPanner** plug-in is automatically applied to audio-related tracks with a mono or stereo configuration that are routed to output channels with any kind of multi-channel configuration other than stereo. The **VST MultiPanner** plug-in is available in the **Inspector** and **MixConsole** and can be used to position channels in the surround field.
- The **MixConvert V6** plug-in is used to convert a surround channel into a different format if the corresponding input/output configuration is not handled by **VST MultiPanner**. Cubase places **MixConvert V6** automatically where needed.
- Plug-ins with multi-channel support specifically designed for surround sound mixing tasks are supported, for example, the **Mix6to2** plug-in. Furthermore, any VST 3 plug-in features multi-channel support and can therefore be used in a surround configuration, even if it was not specifically designed for surround. For detailed information about all included plug-ins, see the separate document **Plug-in Reference**.
- You can export surround mixes in different formats using the **Export Audio Mixdown** function.

RELATED LINKS

[Preparations for Creating Surround Mixes](#) on page 586

[VST MultiPanner](#) on page 589

[MixConvert V6](#) on page 601

[Insert Effects in Multi-Channel Configurations \(Cubase Pro only\)](#) on page 398

[Surround Mix Export](#) on page 605

Deliverables

A surround mix in Cubase can be sent as multi-channel audio from the surround output bus to a recorder, or can be exported to audio files on your hard disk.

Exported surround mixes can either be split to one mono file per speaker channel, or interleaved to a single file containing all the surround channels.

RELATED LINKS

[Export Audio Mixdown](#) on page 920

Available Surround Channel Configurations

Cubase supports several surround channel configurations.

The following surround channel configurations are supported:

LRC

This format uses the channels left, right, and center.

Quadro

This is the original quadraphonic format for music, with one speaker in each corner. This format was intended for vinyl record players.

5.1

This format, also referred to as Dolby Digital, AC-3, DTS and MPEG 2 Multichannel, uses the front channels left, center, and right, the surround channels left and right, and an additional LFE (Low Frequency Effects) channel.

The center channel is mainly used for speech, the front and surround channels left and right for music and sound effects, and the LFE channel for boosting low-frequency content.

5.0

This format uses the front channels left, center, and right, and the surround channels left and right.

6.0 Cine

This format uses the front channels left, center, and right, and the surround channels left, center, and right.

6.0 Music

This format uses the front channels left and right, the surround channels left and right, and the side channels left and right.

LRCS

This format uses the channels left, right, center, and surround. The surround channel is center-rear positioned. This is the original surround format that first appeared as Dolby Stereo in cinema and later as the home cinema format Dolby ProLogic.

LRCS+LFE

This is the same format as LRCS but with an additional LFE channel.

Quadro+LFE

This is the same format as Quadro but with an additional LFE channel.

LRS

This format uses the channels left, right, and surround. The surround channel is positioned at center-rear.

LRC+LFE

This is the same format as LRC but with an additional LFE channel.

LRS+LFE

This is the same format as LRS but with an additional LFE channel.

IMPORTANT


In Cubase, the order of surround busses and side busses follows the specification of Microsoft Inc. To meet the Dolby specification for side surround busses and surround rear busses, swap the device ports of surround busses and side busses.

Preparations for Creating Surround Mixes

You must prepare Cubase for surround sound by defining input and output busses in a surround format and specifying which audio inputs and outputs are used for the different channels in the busses.

Output Bus Configuration

Before you can start working with surround sound, you must configure a surround output bus through which all the speaker channels of the selected surround format are routed.



Output bus in 5.1 channel configuration


RELATED LINKS

[Adding Input and Output Busses](#) on page 28

Child Busses

Child busses allow you to route tracks to particular channels within a surround bus. Creating stereo busses within your surround bus allows you to route stereo tracks directly to a pair of stereo speakers. You can also add child busses in other surround formats with fewer channels than the parent bus.

- Once you have created a surround bus, you can add one or several child busses to it by right-clicking the bus and selecting **Add Child Bus**.



Output bus in 5.1 channel configuration with stereo child bus

RELATED LINKS

[Adding Child Busses \(Cubase Pro only\)](#) on page 28

Surround Routing

The processing format of **VST MultiPanner** depends on the channel routing. You can use the **Routing** and the **Direct Routing** racks in the **MixConsole** to route audio-related tracks to output busses or group channels with a surround configuration.



For example, if a mono source channel is routed to a 5.1 bus, the panner works in 5.1 mode.

RELATED LINKS

[VST MultiPanner](#) on page 589

[Routing](#) on page 344

[Setting Up Direct Routing](#) on page 360

Routing Channels to Individual Surround Channels

If you want to place an audio source in one separate speaker channel, you can route it directly to that speaker channel. This is useful for premixed material or multi-channel recordings that do not require panning.

- To route a channel to an individual surround channel, select the corresponding output bus of that speaker channel in the **Routing** rack.



NOTE

If a stereo audio channel is routed directly to a speaker channel, the left and the right channels are mixed to mono. The pan control for the audio channel determines the balance between the left and the right channel in the resulting mono mix. Center pan produces a mix of equal proportion.

Routing Channels to Child Busses

If you add a child bus within a surround bus, it appears as a subentry of the surround bus on the routing selector. Select this option to route a stereo audio channel directly to that stereo speaker pair of the surround bus, for example, to route a music track directly to the left and right front speakers in a surround channel.



RELATED LINKS

[Child Busses](#) on page 586

Input Bus Configuration

In most cases you do not need to configure a surround format input bus in order to work with surround sound in Cubase. You can record audio files via standard inputs, and easily route the resulting audio channels to surround outputs at any stage. You can also directly import multi-channel files of a specific surround format to audio tracks of the same format.

However, you must add a surround input bus in the following cases:

- You have existing audio material in a specific surround format, and you want to transfer this material to Cubase as a single, multi-channel file.
- You want to make a live recording with a surround setup.

- You have prepared surround premixes, for example, stems, that you want to record on a new audio track with a surround configuration.

RELATED LINKS

[Importing Audio Files](#) on page 254

[Adding Input and Output Busses](#) on page 28

VST MultiPanner

The **VST MultiPanner** plug-in allows you to position a sound source in the surround field or to modify existing premixes. The plug-in distributes the incoming audio in various proportions to the output surround channels.

In the pan area, the sound sources are shown as blue panning balls. In a stereo configuration, the left and right front channels are shown as a yellow and a red ball. You can position the sound sources within the room by dragging the panning balls.

To perform rotating movements that you cannot achieve by dragging, you can use the rotation and orbit controls below the pan area. To adjust the size of the sound source, use the controls for distributing the signal to the different speaker channels and for advanced scaling.

NOTE

Whether you can use **VST MultiPanner** for a specific input/output configuration depends on whether this configuration can be mapped by the panner.

RELATED LINKS

[VST MultiPanner Plug-in Panel](#) on page 590

[Position of the Sound Source](#) on page 594

[MixConvert V6](#) on page 601

Constant Power Panning

VST MultiPanner uses constant power panning laws. This means that the power of a source channel is identical to the power of the corresponding output signal.

Constant power laws ensure that the overall volume as perceived by the listener is always the same, regardless of the signal panning. This allows you to move the sound source in the pan area, disable specific speaker channels, or use the divergence controls without experiencing any volume changes.

VST MultiPanner Plug-in Panel

The **VST MultiPanner** plug-in panel allows you to position a mono or stereo sound source.



- To open the **VST MultiPanner** plug-in panel in a separate window, double-click a miniature view of **VST MultiPanner** in the **Inspector** or the **MixConsole**.

The following settings and options are available:

Movement restriction buttons



Allow you to restrict the movement to one axis when moving the sound source with the mouse.

NOTE

- The movement restriction buttons do not affect the controls in the positioning section below the pan area.

Reset Parameters

Alt-click this button to reset all panner parameters to their default values.

Input level meter

Shows the input level for all speaker channels. The numeric values above the meters indicate the peak levels registered for the channels.

Position Left/Right Channels Independently

Activate this option to adjust the front left and right input channels independently by dragging.

Pan area

Shows the room from the top and allows you to position the sound source by dragging the panning balls.

To zoom out of the pan area, activate **Overview Mode**.

Speaker channel buttons

The speaker buttons around the pan area represent the output configuration. The buttons allow you to solo, mute, and disable the corresponding channels.

NOTE

You cannot automate the soloing of output channels.

Output level meter

Shows the output level for all speaker channels. The numeric values above the meters indicate the peak levels registered for the channels.

Left-Right Pan

Sets the position of the signal on the x-axis.

Rear-Front Pan

Sets the position of the signal on the y-axis.

Rotate Signal around Z-Axis

Rotates the sound source around its positioning handle. This option is only available for stereo signals.

Orbit Center

Rotates the sound source including all input channels and the positioning handle signal around the center of the room.

Click **Counter Shot** to rotate the sound source by exactly 180 degrees.

Radius

Sets the distance of the sound source from the center of the room when using **Orbit Center**.

Center Distribution

Distributes part or all of the center signal to the left and right front speakers.

NOTE

If **Front Divergence** is set to 100 %, **Center Distribution** has no effect.

Front Divergence

Determines the attenuation curve that is used when positioning the sound source on the front x-axis.

Front/Rear Divergence

Determines the attenuation curve that is used when positioning the sound source on the y-axis.

Rear Divergence

Determines the attenuation curve that is used when positioning the sound source on the rear x-axis.

Signal Width

Sets the expansion of the sound source on the x-axis. This parameter is only available for channels with stereo or multi-channel output configurations.

Signal Depth

Sets the expansion of the sound source on the y-axis. This parameter is only available for channels with multi-channel output configurations.

LFE Level

Sets the signal amount that is sent to the LFE (Low Frequency Effects) channel.

NOTE

The LFE channel is used as a full range channel, no low-pass filtering is applied.

RELATED LINKS

[Movement Restriction Modes](#) on page 595

[Overview Mode](#) on page 597

[Soloed, Muted, and Disabled Speaker Channels](#) on page 600

[Pan Controls](#) on page 597

[Rotate Control](#) on page 597

[Orbit Controls](#) on page 598

[Center Distribution](#) on page 598

[Divergence Controls](#) on page 599

[Scale Controls](#) on page 599

Miniature Views

In the **MixConsole**, in the **Channel Settings** window, and in the **Inspector**, miniature views of **VST MultiPanner** allow basic panning operations.

While you must open the plug-in panel to access all of the panner features, you can perform basic panning operations also in the following areas:

- In the **MixConsole** and in the **Channel Settings** window, a miniature view of the panner is displayed at the top of the fader section.



- In the **Inspector**, a miniature view of the panner is displayed in the **Surround Pan** section.



In the miniature views, the following applies:

- To move the signal source in the surround field, click and drag.
- In the **Inspector** miniature view, you can also solo, mute, and disable channels.

NOTE

In all miniature panner views, you can hold **Shift** while moving the sound source to allow for more accurate positioning.

RELATED LINKS

[Soloed, Muted, and Disabled Speaker Channels](#) on page 600

[Movement Restriction Modes](#) on page 595

General Plug-in Controls

Bypass Effect

The **Bypass Effect** button at the top left of the plug-in panel allows you to bypass **VST MultiPanner**.

The following applies:

- If the input and output configurations are identical, the input signals are directly routed to the output channels.
- If the input and output configurations differ, the panner attempts to route the input signals to the appropriate output channels. For example, if you pan a stereo signal to a 5.1 configuration, the left and right front speakers are used.

Mute/Solo

The **Mute** and **Solo** buttons at the top of the plug-in panel are identical to the **Mute** and **Solo** controls of the channel.

Read/Write

The **Read** and **Write** buttons at the top of the **VST MultiPanner** window allow you to apply and record automation data.

RELATED LINKS

[Bypassing Insert Effects](#) on page 396

[Using Solo and Mute](#) on page 338

[Automation Parameters in VST MultiPanner](#) on page 594

Automation Parameters in VST MultiPanner

Most of the parameters in the **VST MultiPanner** plug-in can be automated just like any other channel or insert parameter.

Recording automation for the orbit controls and the independent positioning mode, however, is handled differently. Automation data for these parameters is written as a combination of the front-rear panning, left-right panning, and the **Rotate Signal** parameters. For the independent positioning mode, scaling is added. Therefore, modifying existing automation data is quite troublesome, since it involves changing many different parameters. If an automation pass does not meet your expectations, we recommend to start from scratch.

RELATED LINKS

[Orbit Controls](#) on page 598


[Movement Restriction Modes](#) on page 595

[Writing Automation Data](#) on page 607

Position of the Sound Source

The pan area of the **VST MultiPanner** plug-in shows you the position of the sound source and allows you to move it.

In the pan area, the virtual position of the sound source is shown as a circle. The left and right stereo channels are shown in yellow and red. Mono channels are shown in blue.



The pan area showing a stereo sound source

- 1 Left and right front channels
- 2 The virtual position of the sound source

You can position the sound source anywhere inside the room and even move it out of the pan area. This can be useful for extreme panning positions, such as panning all channels hard right. To show the position outside the pan area, activate **Overview Mode**.

NOTE

If you work with mono channels, the sound source corresponds to the mono channel.

RELATED LINKS

[Positioning a Sound Source in the Pan Area](#) on page 595

[Overview Mode](#) on page 597

Positioning a Sound Source in the Pan Area

The pan area of the **VST MultiPanner** plug-in allows you to use the mouse for positioning the sound source.

PROCEDURE

- To position the sound source, do one of the following:
 - Click at the exact position where you want the sound source to be placed.
 - Click and drag the positioning handle to the exact position where you want the sound source to be placed.
-

RELATED LINKS

[Position of the Sound Source](#) on page 594

[Movement Restriction Modes](#) on page 595

Movement Restriction Modes

VST MultiPanner allows you to restrict the movement within the pan area. This way, you can move the sound source along a specific axis, for example, from bottom left to top right.

The following positioning modes and modifier keys are available:

Standard Positioning Mode



Mouse movements are not restricted.

Fine-Scaled Positioning Mode



Mouse movements are scaled to allow very fine movements. This is useful when panning in one of the miniature displays, for example.

Modifier key: **Shift**

Horizontal Movements Only



Mouse movements are restricted to horizontal.

Modifier key: **Ctrl/Cmd**

Vertical Movements Only



Mouse movements are restricted to vertical.

Modifier key: **Ctrl/Cmd-Shift**

Diagonal Movements Only - Bottom Left to Top Right



Mouse movements are restricted to diagonal from bottom left to top right.

Modifier key: **Alt**

Diagonal Movements Only - Bottom Right to Top Left



Mouse movements are restricted to diagonal from bottom right to top left.

Modifier key: **Alt-Shift**

Jump to Positioning Handle



In this mode, the mouse pointer jumps immediately to the positioning handle, even if it is located outside the pan area.

Modifier key: **Ctrl/Cmd-Alt-Shift**

NOTE

If **Position Left/Right Channels Independently** is activated, clicking anywhere in the pan area always moves the mouse pointer to the closest panning ball.

Position Left/Right Channels Independently



Mouse movements are restricted to left channels or right channels only.

IMPORTANT

- If **Position Left/Right Channels Independently** is activated, automation data is written for several parameters. Due to this, specific automation rules apply.
 - Automation data for the independent positioning mode is always written for the complete sound source, not for individual channels. This means it is not possible to record automation for one stereo channel and then add automation for the other stereo channel in a second go, for example.
-

NOTE

The movement restriction buttons do not affect the controls in the positioning section below.

RELATED LINKS

[Restricting Movements When Dragging the Sound Source](#) on page 596

Restricting Movements When Dragging the Sound Source

When dragging the sound source within the pan area, different movement restriction modes allow you to limit the movement to a specific axis, allowing for very accurate positioning.

PROCEDURE

- To restrict the movement within the pan area, do one of the following:
 - Press the corresponding modifier key. The corresponding movement restriction button is highlighted, indicating that this mode is active. As soon as you release the modifier key, you return to **Standard Positioning Mode**.
 - Click the corresponding button to activate a positioning mode permanently. To deactivate the selected positioning mode, click **Standard Positioning Mode**.
-

RELATED LINKS


[Movement Restriction Modes](#) on page 595

Overview Mode

Overview Mode visualizes panning movements outside the pan area. However, the actual panning is done in the standard view.

If you have moved the sound source to outside of the pan area, **Overview Mode** allows you to see where the positioning handle and the panning balls are located. A thin line connects these theoretical positions with their acoustically effective positions.

- To activate/deactivate overview mode, click **Overview Mode**  below the pan area.



- 1 Acoustically effective positions of the left and right channel within the pan area
- 2 Theoretical positions of the left and right panning ball outside the pan area
- 3 Positioning handle outside the pan area

Pan Controls

Left-Right Pan and **Rear-Front Pan** allow you to pan the sound source on the x-axis and on the y-axis.



NOTE

The panning controls are not affected by the movement restriction buttons.

RELATED LINKS

[Movement Restriction Modes](#) on page 595

Rotate Control

The **Rotate Signal around Z-Axis** control allows you to rotate the sound source.



Orbit Controls

The orbit controls allow you to rotate the sound source, including all input channels, around the center of the surround field.



- 1 Orbit Center
- 2 Radius

Orbit Center

This is the main control that allows you to perform the rotation.

Radius

If you use **Orbit Center**, **Radius** allows you to control the distance of the sound source from the center of the surround field without changing the angle.

IMPORTANT

In terms of automation, **Orbit Center** and **Radius** are not independent parameters as such. Instead, a combination of different automation parameters is used.

RELATED LINKS

[Automation Parameters in VST MultiPanner](#) on page 594

Center Distribution

The **Center Distribution** dial distributes part or all of the center signal to the left and right front speakers.



If you pan the center signal directly to the center speaker and set **Center Distribution** to 0 %, you may get a signal that is too discrete. In this case you can add part of the signal to the left and right front speakers to widen it. By raising the **Center Distribution** value you can distribute the signal to the 3 speakers. At 100 %, the center source is provided entirely by the phantom image created by the left and right speakers.

A line at the top of the surround field indicates the distance up to which a phantom signal is added:



If you position the source signal inside this range, the signal is sent to all 3 channels.


Divergence Controls

Front Divergence, **Front/Rear Divergence**, and **Rear Divergence** determine the attenuation curves used when positioning sound sources for x-axis front, y-axis front/rear, and x-axis rear.



If all divergence controls are set to 0 %, positioning a sound source on a speaker sets all other speakers to level zero. With higher values, the other speakers receive a percentage of the sound source.

Horizontal and vertical lines show the effect of changing the divergence settings:



- At 0 %, a moving sound source is concentrated in one spot.
- At 100 %, a moving sound source is very diffuse and hard to locate.

NOTE

- **Center Distribution** and **Front Divergence** are combined. If the front divergence is set to 100 %, the center distribution has no effect.

Scale Controls

The scale controls allow you to control the horizontal (**Signal Width**) and vertical (**Signal Depth**) expansion of the sound source.



The scale controls influence the perception of spatiality and ambience, as well as the traceability of signals.

- 100 % corresponds to the complete width or depth of the surround field.
- If you reduce both values to 0 %, the distance is reduced to zero and all source channels are centered in one spot.

NOTE

Signal Depth is only available for configurations with front and rear channels.

Soloed, Muted, and Disabled Speaker Channels

The speaker buttons around the pan area represent the output configuration and allow you to disable, solo, or mute channels. The speaker buttons around the **Top View** and the **Rear View** represent the output configuration and allow you to disable, solo, or mute channels.

Enabled speaker



This channel is enabled.

Disabled speaker



This channel is disabled. Its signal is distributed to the other channels instead.

Soloed speaker



This channel is soloed.

Muted speaker



This channel is muted.

Disabled and muted speaker



This channel is disabled and muted.

- To disable a channel, **Alt**-click on the corresponding speaker button. That way, no audio is routed to this channel. The signal that would otherwise be sent to this channel is distributed to the other channels instead.

NOTE

If the signal of a disabled channel is distributed to other channels, the power level stays constant.

- To solo a channel, click the corresponding speaker button. That way, you only hear the signal sent to this channel while all other channels are muted. This can be useful for testing purposes, for example, to make sure that a signal is sent to a specific channel as intended.

NOTE

You can solo several channels at the same time by clicking on the corresponding speaker buttons one after the other. If you **Ctrl/Cmd**-click a speaker button, this channel is soloed exclusively and all other channels are muted.

IMPORTANT

Solo and Mute cannot be automated.

RELATED LINKS

[Constant Power Panning](#) on page 589

Remote Controlling VST MultiPanner

You can control the **VST MultiPanner** plug-in remotely with several control devices. To control all panner functions, you may need updated software for your device.

Yamaha Nuage

Avid

The parameters of **VST MultiPanner** are mapped on the following devices:

- System 5-MC
- S6
- Artist Series

Panning with a Joystick

You can use a joystick to remote-control **Rear-Front Pan** and **Left-Right Pan** in **VST MultiPanner**.

PREREQUISITE

You have connected a joystick to your computer and restarted Cubase.

PROCEDURE

- To position the sound source in the room, pull the joystick trigger and move the joystick.
-

RELATED LINKS

[Joysticks](#) on page 665

MixConvert V6

MixConvert V6 is a plug-in that converts one multi-channel audio source into another multi-channel destination. It is most frequently used to downmix a multi-channel surround mix into a format with fewer channels, for example, a 5.1 surround mix into a stereo mix.

MixConvert V6 can be used as an insert effect in the **MixConsole** like other plug-ins, but it also has special functions.

Cubase automatically inserts **MixConvert V6** instead of **VST MultiPanner** if the channel, for example, an audio track or a group channel, is routed to a destination with fewer audio channels. **MixConvert V6** is also inserted in place of any cue send panner if the destination has a different channel configuration than the source.

NOTE

There is one exception to this behavior. If a stereo channel is routed to a mono destination through the channel routing or a cue send routing, a normal stereo panner is inserted. However, this stereo panner controls the balance of the left and right channels as they are blended into the mono destination. The center position blends both channels together by equal amounts. With the pan set all the way to the left, only the left channel can be heard, and vice versa.

The following table gives you an overview of which plug-in is used in a specific configuration:

Mono Tracks

Routing Destination	Surround Pan Option
Mono	<ul style="list-style-type: none"> • n.a.
Stereo	<ul style="list-style-type: none"> • Mono - Standard Panner
Surround	<ul style="list-style-type: none"> • VST MultiPanner • MixConvert V6

Stereo Tracks

Routing Destination	Surround Pan Option
Mono	<ul style="list-style-type: none"> • Stereo - Standard Panner
Stereo	<ul style="list-style-type: none"> • Stereo - Balance Panner • Stereo - Combined Panner
Surround	<ul style="list-style-type: none"> • VST MultiPanner • MixConvert V6

Surround Tracks

Routing Destination	Surround Pan Option
Mono	<ul style="list-style-type: none"> • MixConvert V6
Stereo	<ul style="list-style-type: none"> • MixConvert V6
Surround	<ul style="list-style-type: none"> • VST MultiPanner • MixConvert V6
Surround with larger channel width	<ul style="list-style-type: none"> • VST MultiPanner • MixConvert V6
Surround with smaller channel width	<ul style="list-style-type: none"> • MixConvert V6

You can select the surround pan option in the context menu of the panner miniature views in the **MixConsole**, in the **Channel Settings** window, and in the **Inspector**.

RELATED LINKS

[MixConvert V6 Plug-in Panel](#) on page 603

[VST MultiPanner](#) on page 589

[Input and Output Channel Configurations](#) on page 604

[Miniature Views](#) on page 592


MixConvert V6 Plug-in Panel

The **MixConvert V6** plug-in panel allows you to set the levels of the surround channels, and to solo or mute channels for input and output channels.



The plug-in panel is divided into three sections: the **Input** section, the **Output** section, and the center section. The **Input** and **Output** sections are hidden by default.

- To show/hide the **Input** or **Output** sections, click the corresponding arrow button.



Input section

Shows all input channels and allows you to solo or mute channels.

Output section

Shows all output channels and allows you to solo or mute channels.

The center section contains the main plug-in parameters as well as buttons for soloing several speaker channels in one go.

Input Channel Configuration

Shows the input channel configuration.

Output Channel Configuration/Select Output Channel Configuration

Shows the output channel configuration.

If **MixConvert V6** is used as an insert effect, the pop-up menu allows you to set the output channel configuration.

Solo Channel buttons

Solos all front channels, the LFE channel, or all surround channels in the input or output display. All other channels are muted.

Listen to Solo Channels on Center Channel

Routes all soloed channels to the center channel. If no center channel is present, the signal from the soloed channels is distributed equally to the left and right speakers.

Listen to Surround Channels on Front Channels

Solos all surround channels, including the side channels, and routes or downmixes them to the front speakers.

Center Level

Sets the level of the front center channel.

LFE fader

Sets the level of the LFE channel.

Surround Level

Sets the level of the surround channels. The level of the surround channels cannot be adjusted individually.

Global Gain

Sets the level of all output channels.

Activate/Deactivate Low-Pass Filter

Activates/Deactivates the low-pass filter that is applied to the LFE channel.

RELATED LINKS

[Input and Output Channel Configurations](#) on page 604

Input and Output Channel Configurations

The input channel configuration is determined by the channel width of the track, group, or output bus on which **MixConvert V6** is inserted. The output channel configuration depends on whether **MixConvert V6** is used.

- If **MixConvert V6** replaces the panner, the output configuration is determined by the destination of the channel or cue send.
- If **MixConvert V6** is used as an insert effect, the output configuration can be modified using the **Select Output Channel Configuration** pop-up menu. You can select any configuration from the VST 3 specification that contains speakers that are also present in the input configuration.



NOTE

You can also modify the output configuration by loading a preset.

Soloing Channels

You can click the speaker icons in the input and output channel displays or the solo channel buttons in the center section to solo or mute channels.

Soloing an input channel allows you to hear the influence of the soloed channel on the downmix. Soloing an output channel allows you to hear only the soloed channel in the downmix.

To solo channels, do one of the following:

- To solo a channel, click the corresponding speaker icon.
You can solo several channels at the same time. All other channels are muted.
To deactivate the solo state of a channel, click the corresponding speaker icon again.
- To solo a channel exclusively, **Ctrl/Cmd**-click the corresponding speaker icon.
- To solo all front channels or all surround channels, click the corresponding button in the center section.
- To solo the LFE channel, click the corresponding cross-hair icon in the center of the channel display.

NOTE

Alternatively, click the **Solo Input/Output LFE Channel** button in the center section.

- To mute a channel, **Shift**-click the corresponding speaker icon.

RELATED LINKS

[MixConvert V6 Plug-in Panel](#) on page 603

Surround Mix Export

Cubase allows you to export a surround mix using the **Export Audio Mixdown** function.

You have the following export options when working with a surround configuration:

- Split channels, resulting in one mono audio file for each surround channel.
- Export to interleaved format, resulting in a single multi-channel audio file, for example, a 5.1 file containing all 6 surround channels.

RELATED LINKS

[Export Audio Mixdown](#) on page 920

[Wave Files](#) on page 926

Automation

In essence, automation means recording the values for a particular **MixConsole** or effect parameter. When you create your final mix, Cubase can adjust this particular parameter control.

Automation Curves

Within a Cubase project, the changes in a parameter value over time are reflected as curves on automation tracks.

There are different kinds of automation curves:



1 Ramp curves

Ramp curves are created for any parameter that generates continuous multiple values, such as fader or encoder movements.

2 Jump curves

Jump curves are created for on/off parameters, such as mute.

Static Value Line

When you open an automation track for the first time, it does not contain any automation events. This is reflected in the event display as a dotted horizontal line, the static value line. This line represents the current parameter setting.

If you manually added any automation events or used write automation for the corresponding parameter and then disable the reading of automation data, the automation curve is grayed out in the event display and the static value line is used instead.

As soon as **Read** is enabled, the automation curve is used.

Write/Read Automation

You can automation-enable tracks and **MixConsole** channels by activating their automation write **W** and read **R** buttons.

- If you activate **W** for a channel, virtually all **MixConsole** parameters that you adjust during playback for that specific channel are recorded as automation events.
- If **R** is activated for a channel, all your recorded **MixConsole** actions for that channel are performed during playback.

The **R** and **W** buttons for a track in the track list are the same as the **R** and **W** buttons in the **MixConsole**.

NOTE

R is automatically enabled when you enable **W**. This allows Cubase to read existing automation data at any time. You can separately deactivate **W** if you only want to read existing data.

There are also global read and write indicator buttons **Activate/Deactivate Read/Write for All Tracks** on the **MixConsole** toolbar and at the top of the track list. These buttons light up as soon as there is an enabled **R** or **W** button on any channel/track within your project. Furthermore, they can be clicked to activate or deactivate **R/W** of all tracks simultaneously.

NOTE

R/W are also available on the **Automation Panel** (Cubase Pro only).

RELATED LINKS

[Read/Write Buttons](#) on page 616

Writing Automation Data

You can create automation curves manually or automatically.

- Manual writing makes it easy to quickly change parameter values at specific points without having to activate playback.
- Automatic writing lets you work almost as if you were using a real mixer.

With both methods, any applied automation data is reflected in both the **MixConsole** (a fader will move for example) and in the corresponding automation track curve.

RELATED LINKS


[Manual Writing of Automation Data](#) on page 608

Automatic Writing of Automation Data

Every action that you perform is automatically recorded on automation tracks which you can later open for viewing and editing.

PROCEDURE

1. In the track list, click **Show/Hide Automation** for a track to open its automation track.



2. Click **W** to enable the writing of automation data on this track.
3. Start playback.
4. Adjust the parameters in the **MixConsole**, in the **Channel Settings** window, or in the effect control panel.

The value settings are recorded and displayed as a curve on the automation tracks. When automation data is being written, the color of the automation track changes and the delta indicator in the automation track shows the relative amount by which the new parameter setting deviates from any previously automated value.

5. Stop playback and return to the position where you started playback.
 6. Click **W** to disable the writing of automation data.
 7. Start playback.
-

RESULT


All actions that you recorded are reproduced exactly. When you drag a plug-in to a different insert slot on the same channel, any existing automation data moves with the plug-in. When you drag it to an insert slot on a different channel, any existing automation data is not transferred to the new channel.

Manual Writing of Automation Data

You can add automation events manually by drawing automation curves on an automation track.

PROCEDURE

1. In the track list, click **Show/Hide Automation** for a track to open its automation track.



2. Click the automation parameter name and select the parameter from the pop-up menu.
3. Select the **Draw** tool.
4. Click on the static value line.
An automation event is added, read automation mode is automatically activated, and the static value line changes to a colored automation curve.
5. Click and hold to draw a curve by adding many automation events.
When you release the mouse button, the number of automation events is reduced.

NOTE

To adjust the thinning out of events, open the **Automation Panel**, click **Automation Settings** and enter a value for **Reduction Level**.

6. Start playback.
-

RESULT

The automated parameter changes with the automation curve, and the corresponding fader in the **MixConsole** moves accordingly.

AFTER COMPLETING THIS TASK

Repeat the procedure if you are not happy with the result. If you draw over existing events, a new curve is created.

Tools for Drawing Automation Data

Apart from the **Draw** tool, you can use the **Object Selection** tool and the **Line** tool to draw automation events. If you click with any of these tools on the automation track, **R** is activated automatically.


- **Object Selection**

If you click on an automation track with the **Object Selection** tool, an automation event is added. If you hold down **Alt**, you can draw several automation events.

NOTE

Events that are introduced between existing events and do not deviate from the existing curve are removed as soon as you release the mouse button.

To activate the **Line** tool in any other available mode, click the **Line** tool and click again to open a pop-up menu where you can select the **Line** tool mode.



The following **Line** tool modes are available:

Line mode

If you click on the automation track and drag with the **Line** tool in **Line** mode, you can create automation events in a line. This is a quick way to create linear fades, etc.

Parabola mode

If you click and drag on the automation track with the **Line** tool in **Parabola** mode, you can create more natural curves and fades.

NOTE

The result depends on the direction from which you draw the parabolic curve.

Sine, Triangle, or Square mode

If you click and drag on the automation track with the **Line** tool in **Sine**, **Triangle**, or **Square** mode and the **Snap Type** is set to **Grid**, the period of the curve (the length of one curve cycle) is determined by the grid setting. If you press **Shift** and drag, you can set the period length manually, in multiples of the grid value.

NOTE

The **Line** tool can only be used for ramp type automation curves.

Editing Automation Events

Automation events can be edited much like other events.

NOTE

If you move an event or part on a track and you want the automation events to follow automatically, select **Edit > Automation Follows Events**. Any automation events at the new position are overwritten.

- You can use the tools on the **Project** window toolbar to edit automation events.
- You can use the automation event editor to edit selected automation events on ramp automation curves.

RELATED LINKS

[Toolbar](#) on page 40

[Automation Event Editor](#) on page 611

Creating Smooth Transitions Between Automation Events (Bézier Automation Curves)

Cubase supports bézier automation curves that allow you to create smooth transitions between automation events. This way, you can edit linear ramp curves with much more precision, flexibility, and intuition.

PREREQUISITE

The **Object Selection** tool is active.

PROCEDURE

1. Move the mouse pointer on the linear ramp curve segment that you want to edit.
A handle is shown on the curve segment.



NOTE

If the automation events are next to each other on an almost horizontal or vertical line, or if they are too close to each other, the handle is not available.

2. Click and drag with the mouse button pressed to modify the shape of the curve segment.



3. When you are satisfied with the result, release the mouse button.
-

RESULT

A smooth transition curve according to your edits is created.

If you are not satisfied with the result and want to start over again from the original linear curve segment, double-click the handle.

Cubase Pro only: You can use bézier automation curves with tracks that are connected to VCA faders.

AFTER COMPLETING THIS TASK

For even more precise editing, add new automation events to your bézier curve segment.



This creates new segments that you can smoothen as described above.



RELATED LINKS

[VCA Fader Settings](#) on page 365

[VCA Fader Automation](#) on page 369

Selecting Automation Events

- To select an automation event, click it with the **Object Selection** tool.

- To select multiple events, drag a selection rectangle with the **Object Selection** tool or **Shift**-click the events.
- To select multiple events, select a range with the **Range Selection** tool or **Shift**-click the events.
- To select all automation events on an automation track, right-click the automation track and select **Select All Events** from the context menu.

Selected events are indicated by a dark color.

NOTE

If you select several events of a ramp automation curve, the automation event editor becomes available.

RELATED LINKS

[Automation Event Editor](#) on page 611

Automation Event Editor

The automation event editor allows you to edit selected events on the automation track. The automation event editor is only available for automation ramp curves.

NOTE

All editing in the automation event editor only affects the automation events that are part of the selection.


To open the automation event editor, do one of the following:

- Activate the **Object Selection** tool and drag a selection rectangle on a ramp type automation track.
- Activate the **Range Selection** tool and select a range on a ramp type automation track.

NOTE

If you work with the **Range Selection** tool, the smart control for **Stretch** is not available.

The automation event editor features the following smart controls for specific editing modes:



1 Tilt Left

If you click in the upper left corner of the editor, you can tilt the left part of the curve. This allows you to tilt the event values at the start of the curve upwards or downwards.

2 Compress Left

If you **Alt**-click in the upper left corner of the editor, you can compress or expand the left part of the curve. This allows you to compress or expand the event values at the start of the curve.

3 Scale Vertically

If you click in the middle of the upper border of the editor, you can scale the curve vertically. This allows you to raise or lower the event values of the curve in percent.

4 Move Vertically

If you click on the upper border of the editor, you can move the entire curve vertically. This allows you to raise or lower the values of the event values of the curve.

5 Compress Right

If you **Alt**-click in the upper right corner of the editor, you can compress or expand the right part of the curve. This allows you to compress or expand the event values at the end of the curve.

6 Tilt Right

If you click in the upper right corner of the editor, you can tilt the right part of the curve. This allows you to tilt the event values at the end of the curve upwards or downwards.

7 Scale Around Relative Center

If you **Alt**-click in the middle right border of the editor, you can scale the curve relative to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

8 Scale Around Absolute Center

If you click in the middle right corner of the editor, you can scale the curve absolute to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

9 Stretch

If you click on the lower border of the editor, you can stretch the curve horizontally. This allows you to move the event values of the curve to the left or to the right.

NOTE

To edit the automation curves on several tracks simultaneously, select the automation events using the **Object Selection** tool or the **Range Selection** tool on the corresponding automation tracks, and hold down **Ctrl/Cmd** while using the smart controls.

NOTE

If you select automation events using the **Range Selection** tool, additional automation events are automatically created at the start and the end of the selection. This ensures that the entire selection is edited.

RELATED LINKS

[Automation Curves](#) on page 606

Quick Vertical Scaling of Automation Events

You can scale the curve segment between two automation events vertically without any need to select the events first.

PROCEDURE

1. Move the mouse pointer to the upper border of the automation track above the linear ramp curve segment that you want to scale.

A handle is shown.



2. Click and drag up or down with the mouse button pressed.

3. When you are satisfied with the result, release the mouse button.
-

RESULT

The curve segment between the two automation events is scaled.

Moving Automation Events

Moving Single Automation Events

- To move a selected automation event, click it and drag to the left or to the right.
- To restrict the direction of the movement, press **Ctrl/Cmd** and drag.

NOTE

Snap is taken into account when you move automation curves horizontally. To turn it off temporarily, hold down **Ctrl/Cmd** and any other modifier, and drag.

Moving Multiple Automation Events

- To move a selection of automation events, click inside the selection rectangle and drag to the left or to the right.
If you made a continuous selection of automation events, events at the destination range are overwritten. However, if you move the same selection range past already existing events, they appear again. If a selection range contains automation events that are deselected, dragging is restricted. You cannot move this selection past existing events.
- To copy a continuous selection of automation events, click inside the selection rectangle, hold down **Alt**, and drag to the left or to the right.

NOTE

If you press **Esc** while dragging the selection rectangle, the selection jumps back to its original position.

RELATED LINKS

[Selecting Automation Events](#) on page 610

Removing Automation Events

- To remove an automation event, click on it with the **Erase** tool.
- To remove multiple automation events, select them and press **Backspace** or **Delete** or select **Edit > Delete**.
- When **Use Virgin Territory** is enabled, this creates a gap. When disabled, the events within the range are removed.
- To remove all automation events from the automation track and close the automation track, click the automation parameter name in the track list and select **Remove Parameter** from the pop-up menu.

NOTE

When removing automation events, the curve is redrawn to connect the remaining events.

RELATED LINKS

[Virgin Territory vs. Initial Value \(Cubase Pro only\)](#) on page 615

Automation Tracks

Most of the tracks in your project have automation tracks, one for each automated parameter.

To show automation tracks, you must open them.

Showing/Hiding Automation Tracks

- Position the mouse pointer over the lower left corner of the track and click the arrow icon (**Show/Hide Automation**) that appears.
- Right-click the track in the track list and select **Show/Hide Automation** from the context menu.
- To open another automation track, position the mouse pointer over the lower left corner of an automation track and click + (**Append Automation Track**).
- To show all used automation tracks in the track list, right-click any track and select **Show All Used Automation** from the context menu.
- Cubase Pro only: To open the corresponding automation track on writing automation parameters, select **Project > Automation Panel > Automation Settings > Reveal Parameter on Write**.
- Cubase Artist only: To open the corresponding automation track on writing automation parameters, activate **Show Automation Track in Project on Writing Parameter** in the **Preferences** dialog (**Editing** page).

Removing Automation Tracks

- To remove an automation track together with all automation events, click the parameter name, and from the pop-up menu, select **Remove Parameter**.
- To remove all automation tracks from a track that do not contain automation events, select **Remove Unused Parameters** from any of its automation parameter name pop-up menus.
- To remove automation tracks, you can also select **Project > Automation Panel > Functions** and select one of the options to delete automation (Cubase Pro only).

Assigning a Parameter to an Automation Track

Parameters are already assigned to automation tracks when you open them, according to their order in the parameter list.

PROCEDURE

1. Open an automation track and click on the automation parameter name.
A parameter list is shown. The content depends on the track type.
2. From the pop-up menu, select the parameter or select **More** to open the **Add Parameter** dialog that lists all parameters that can be automated, and select the parameter there.

RESULT

The parameter replaces the current parameter in the automation track.

NOTE

The replacement of the automation parameter is non-destructive. If the automation track contains any automation data for the parameter that you just replaced, this data is there, although it is not visible. By clicking on the automation parameter name in the track list, you can switch back to the replaced parameter. On the pop-up menu, an asterisk (*) is shown after the parameter name for hidden automation tracks.

Muting Automation Tracks

By muting an automation track, you turn off automation for a single parameter.

- To mute individual automation tracks, click **Mute Automation** in the track list.

Virgin Territory vs. Initial Value (Cubase Pro only)

For parameter automation, Cubase works either with an initial value or with virgin territory.

When you enable **Use Virgin Territory**, no automation curve is displayed on the automation track, and you find automation data only where you actually perform an automation pass. After an automation pass, you will find virgin territory only to the right of the last automation event.

Creating Gaps

Gaps are empty sections between automation curves. You can create gaps inside a section with automated values.

PROCEDURE

1. Select **Project > Automation Panel**.
2. Click **Automation Settings** and activate **Use Virgin Territory**.
3. With the **Range Selection** tool, select a range on an automation track with existing automation data and press **Delete** or **Backspace**.

RESULT

A gap is created and new events at the beginning and the end of the selection range are created. These mark the end point of the automation curve to the left and the start of the next automation curve to the right of the gap.

Defining a Terminator Point

You can define any automation event on the automation curve as the terminator point of this part of the curve. This will automatically delete the line between this event and the next one, creating a gap.

PROCEDURE

1. In the automation curve, click the event that you want to define as the last point to select it.
2. In the **Project** window info line, set **Terminator** to **Yes**.
The line between this event and the next one is deleted and a gap is created.

NOTE

If you define the last automation event of an automation curve as terminator point, any automation data to the right of this event (as defined by an initial value) is deleted.

Automation Panel (Cubase Pro only)

The **Automation** panel is a floating window, similar to the **MixConsole** and **Transport** panel, and can be left open while you work.



To show the **Automation** panel, do one of the following:

- Select **Project > Automation Panel**.
- On the **Project** window toolbar, click **Open Automation Panel**.
- Press **F6**.

Read/Write Buttons

In the upper part of the **Automation Panel**, you will find the **Read** and **Write** buttons. These are used to globally enable or disable **Read** and **Write** on all tracks.



- To enable all **Read** buttons on all tracks/channels of your project, click **Activate Read for all tracks**.
- To disable all **Read** buttons, click **Deactivate Read for all tracks**.
- To enable all **Write** buttons and, at the same time, all **Read** buttons on all tracks/channels of your project, click **Activate Write for all tracks**.
- To disable all **Write** buttons, click **Deactivate Write for all tracks**. The **Read** buttons will remain enabled.

Automation Modes

Cubase provides different punch out modes for automation: **Touch**, **Auto-Latch**, and **Cross-Over**. In all modes, automation data will be written as soon as a parameter control is touched in play mode. They differ in their punch out behavior.

The automation modes are available on the upper part of the **Automation Panel** and on the **Project** window toolbar on the **Global Automation Mode** pop-up menu.



You can change the automation mode at any time, for example, in play or stop mode or during an automation pass. You can also assign key commands to the automation modes.

The current automation pass will always punch out as soon as one of the following conditions is met, independent of which automation mode is selected:

- If you disable **Write**.
- If you stop playback.


- If you activate **Fast Forward/Rewind**.
- If the project cursor reaches the right locator in **Cycle** mode.
- If you click in the ruler to move the project cursor. This is user-definable and can be controlled via the **Automation Panel**.

RELATED LINKS

[Automation Settings](#) on page 624

Touch

Touch mode is useful in situations where you want to make a change lasting only a few seconds to an already set up parameter.



- **Touch** writes automation data only for as long as you actually touch a parameter control. Punch out occurs as soon as you release the control.
- After punch out, the control returns to the previously set value.

NOTE


You can set the time it takes for the parameter to reach the previously set value with the **Return Time** setting in the **Automation Settings**.

RELATED LINKS

[Automation Settings](#) on page 624

Auto-Latch

Auto-Latch is useful in situations where you want to keep a value over a longer period of time – for example when making EQ settings for a particular scene. In **Auto-Latch** mode, there is no specific punch out condition other than those that are valid in all modes.




- Once your pass has started, the writing of automation data continues for as long as playback lasts or **Write** is enabled.
- When you release the control, the last value is kept until you punch out.

NOTE

The automation mode for On/Off switches is always **Auto-Latch** even if another mode is selected globally or for the track.

Cross-Over

Cross-Over mode allows you to perform a manual return to ensure smooth transitions between new and existing automation settings. For **Cross-Over**, the punch out condition is crossing over an already existing automation curve after touching the parameter for a second time. The **Cross-Over** mode can be used in situations where you are not satisfied with an automation curve or with the automatically applied return settings.



- Once your pass has started, the writing of automation data continues for as long as playback lasts or **Write** is enabled.
- When you release the control, the automation pass continues, with the value setting remaining the same.


- When you re-touch the fader and move it towards the original value, punch out occurs automatically as soon as you cross the original curve.

RELATED LINKS

[Automation Settings](#) on page 624

Trim

Trim allows you to modify the automation curve from a previous pass. If you activate **Trim**, a trim curve is positioned in the middle of the automation track.



NOTE

Trim works for channel volume and cue send level adjustments.

If you activate **Trim**, all editing and recording affects the trim curve. If you deactivate **Trim**, it affects the original automation curve instead.

You can edit trim data like any other automation data. It is stored with the project.

- Drag the trim curve up or down and add automation events to it. These increase or decrease the values of the original automation curve, but allow you to preserve the original data.

You can use **Trim** either in stop or in play mode:

- In stop mode, you can select one of the **Fill** options and edit the trim curve manually by clicking on it and moving it up or down. The original automation curve is displayed in a lighter color and its values are merged with the trim curve. The resulting automation curve is displayed in a darker color.
- In play mode, the events of the original automation curve are trimmed as the project cursor passes over them.

NOTE

Trim also works with bézier automation curves.

RELATED LINKS

[Creating Smooth Transitions Between Automation Events \(Bézier Automation Curves\)](#) on page 610

Freeze Trim

You can freeze your trim curve automatically or manually. This renders all trim data into a single automation curve.

- To freeze your trim curve automatically whenever a write operation is finished, open the **Automation Settings** and select **On Pass End** in the **Freeze Trim** pop-up menu.
- To freeze your trim curve automatically when Trim mode is switched off, open the **Automation Settings** and select **On Leaving Trim Mode** in the **Freeze Trim** pop-up menu.
- To freeze your trim curve manually, open the **Automation Settings** and select **Manually** in the **Freeze Trim** pop-up menu. To freeze a specific parameter for the track, click the parameter name, and from the pop-up menu, select **Freeze Trim**.
- To freeze the trim automation for all tracks in the project, open the **Automation Panel**, and in the **Functions** pop-up menu, select **Freeze All Trim Automation in Project**.
To freeze the trim automation of all selected tracks, open the **Automation Panel**, and in the **Functions** pop-up menu, select **Freeze Trim Automation of Selected Tracks**.

Functions

At the top right of the **Automation Panel**, you will find the **Functions** pop-up menu, which contains a number of global automation commands.

Delete All Automation in Project

Removes all automation data from your project.

Delete Automation of Selected Tracks

Removes all automation data for the selected tracks.

Delete Automation in Range

Deletes all automation data between the left and right locators on all tracks.

Fill Gaps on Selected Tracks

This option is used with virgin territories. Select this to fill any gaps in the automation curves of the selected tracks with a continuous value. The value of the last event (the end point) of a section is used to fill the gap. This value is written across the gap up to one millisecond before the first event of the next automated section. A new event is inserted here; the value will be ramped to the next automated section.

Fill Gaps with Current Value (Selected Tracks)

This option is used with virgin territories. Select this option to fill any gaps in the automation curves of the selected tracks. The gaps are filled with the current value of the corresponding control.

Freeze All Trim Automation in Project

Freezes all trim automation for all tracks in the project.

Freeze Trim Automation of Selected Tracks

Freezes all trim automation for the selected tracks.

Fill Options

The **Fill** options define what happens in a specific section of your project when you punch out of a running automation pass.

The **Fill** options write one particular value across a defined section of your automation track. Any previously created data within this section is overwritten.

You can also combine the various **Fill** options.

Activating To Punch

PROCEDURE

1. On the **Automation Panel**, activate **Touch**, and activate **To Punch** as **Fill** option.
2. Start playback.
3. Move the fader until you have found the volume setting that you need and release the fader to punch out.

The volume curve is set from the point of punch out back to where you punched in. The values written while moving the fader to find the right value are deleted, and the volume jumps at exactly the right moment from the value set in the first scene to the value found for the second scene.

Activating To Start

PROCEDURE

1. On the **Automation Panel**, activate **Touch**, and activate **To Start** as **Fill** option.
2. Start playback.
3. Move the fader until you have found the volume setting that you need and release the fader to punch out.

The automation track is filled from where you punched out to the start of the project.

Activating To End

PROCEDURE

1. On the **Automation Panel**, activate **Touch**, and activate **To End** as **Fill** option.
 2. Start playback and touch the parameter control to punch in the automation pass.
 3. Move the fader until you have found the setting that you want and release it.
This will punch out the writing of automation data. As you let go of the fader, the automation curve takes the found value setting, from where you punched out to the end of the project.
-

Activating Loop

PREREQUISITE

You have set up a loop range with the left and right locators.

PROCEDURE

1. On the **Automation Panel**, activate **Touch**, and activate **Loop** to activate it as **Fill** option.
2. Start playback.
3. Move the fader until you have found the volume setting that you need and release the fader to punch out.

The found value is set within the range that is defined by the left and right locators.

Activating Gaps

PREREQUISITE

You have set up virgin territories.

NOTE

When **Trim** is active, **Gap** has no effect. This is because **Trim** only modifies already existing data.

PROCEDURE

1. On the **Automation Panel**, activate **Touch**, and activate **Gaps** to activate it as **Fill** option.
 2. Start playback.
 3. Move the fader until you have found the volume setting that you need and release the fader to punch out.
Any gaps between previously written automation events is filled with the last value that was found during the last automation pass.
-

RELATED LINKS

[Virgin Territory vs. Initial Value \(Cubase Pro only\)](#) on page 615

One Shot vs Continuous Fill

You can use the **Fill** options in different ways:

- **One shot**
When you click one of the **Fill** buttons, it is highlighted, and will be enabled during the next automation pass. Afterwards, the option is disabled again.
- **Continuous fill**
If you click a **Fill** button a second time, a lock symbol is displayed on the highlighted button, indicating that you are in continuous fill mode and that the operation can be repeated as many times as you want. Click the button a third time to disable the corresponding **Fill** option.

Drawing Fill Manually

You can use the **Fill** options on the **Automation Panel** in combination with the **Draw** tool. This provides you with a powerful method for writing automation data manually.

PROCEDURE

1. Open an automation track and select the **Draw** tool.
2. On the **Automation Panel**, select **To End** as a **Fill** option.
3. Click and draw to create an automation curve.
4. Release the mouse button.
At the moment of release, a final automation event is created. The automation curve is written from this last event through to the end of the project.

NOTE

This procedure can be used with all the **Fill** options.

Suspend Options

This section on the **Automation Panel** allows you to exclude specific parameters from the reading or writing of automation data. This way, you have full manual control of these parameters.

Suspend Read

Suspending the reading for a specific parameter during automation gives you full manual control of it.

- To suspend the reading of automation data for a specific parameter, click the corresponding parameter.
- To suspend the reading of automation data for all parameters/parameter groups, click **All**.

NOTE

When any of the options in the **Suspend Read** category are enabled, clicking **All** will disable these buttons.

EXAMPLE

Imagine that you have already automated several tracks. While working on the current track, you want one of the other tracks to be louder, to better identify a particular position in your audio material.

By suspending **Read** for the volume parameter, you regain full manual control and can set the volume to the required level.

Suspend Write

Suspending the writing for a specific parameter during automation punches this parameter out of the automation pass.

- To suspend the writing of automation data for a specific parameter, click the corresponding parameter.
- To suspend the writing of automation data for all parameters/parameter groups, click **All**.

NOTE

When any of the options in the **Suspend Write** category are enabled, clicking **All** will disable these buttons.

EXAMPLE

Imagine the following situation: To help you concentrate while working on a particular track, you mute several other tracks. However, because write automations are active on these tracks, this mute state is also automated during the next automation pass – a classic situation in mixing.

To avoid inadvertently excluding whole tracks from your mix in this way, you can exclude **Mute** from all automation writing. Simply click **Mute** in the **Suspend Write** category on the **Automation Panel**.

Show Options

The **Show** options allow you to open all automation tracks for a specific parameter. This gives you an overview of the automated parameter.

- To open the volume, pan, EQ, sends, or inserts automation tracks for all tracks, click the corresponding parameter.

The automation tracks are opened even if no automation data was recorded on these tracks.

- To step through the individual parameter sets of parameter groups, for example Pan, EQ, Sends, and Inserts, click the respective button repeatedly.
- To show only the automation tracks for which automation data has already been written, activate **Used Only** and click one of the options.
- To show all automation tracks that contain automation data, activate **Show Used**.
- To hide all open automation tracks, activate **Hide All**.

NOTE

The **Show** options on the **Automation Panel** affect all tracks.

Automation Settings

To set up specific automation settings, click the button in the bottom left of the automation panel.

Show Data on Tracks

Activate this to show audio waveforms or MIDI events on automation tracks.

The events are displayed only if **Show Waveforms** is enabled in the **Preferences** dialog (**Event Display—Audio** page), and if **Part Data Mode** is set to an option other than **No Data**(**Event Display—MIDI** page).

Use Virgin Territory

Activate this if you want to use virgin territories.

Continue Writing

If you activate this option, the recording of automation will not be blocked when locating to a new position. This can be used to perform multiple automation passes in cycle mode or if you are using the arranger functions.

If this option is deactivated and you write automation data and locate to another position in the project, the writing will be stopped until the mouse button is released or until a stop command is received.

Reveal Parameter on Write

If you activate this option, the corresponding automation track is revealed on writing automation parameters. This is useful if you want to have a visual control of all parameters changed on writing.

Return Time

This determines how fast the automated parameter returns to any previously automated value when you release the mouse button. Set this to a value higher than 0 to prevent sudden jumps in your parameter settings which may lead to crackles.

Reduction Level

Punching out or using the **Reduce Automation Events** function removes all superfluous automation events. This results in an automation curve that contains only the events necessary to reproduce your actions. A reduction level value of 0 % removes repeated automation points only. A reduction level value between 1 to 100 % smoothens the automation curve. The default value of 50 % should reduce the automation data amount significantly without touching the sound result of the existing automation.

Spike Detection Range

Defines a period of time in which sudden changes in the automated parameter are considered to be unwanted spikes. The spikes can be removed using the **Delete Automation Spikes** function. You can set values from 0 to 200 ms.

Freeze Trim

In this pop-up menu, you can specify how to freeze your trim curve.

- To freeze your trim curve manually, select **Manually**.
- To perform a freeze whenever a write operation is finished, select **On Pass End**.
- If you want the trim data to freeze automatically when the trim mode is switched off (globally or individually for a track), select **On Leaving Trim Mode**.

RELATED LINKS

[Virgin Territory vs. Initial Value \(Cubase Pro only\)](#) on page 615

MIDI Controller Automation

When working with Cubase, it is possible to record automation data for MIDI controllers as MIDI part data and as data on an automation track.

If you have such conflicting automation data, you can specify separately for every parameter how these will be combined during playback. This is done by selecting an automation **Merge Mode** in the track list for the automation track.

Automation Merge Modes

This pop-up menu is only available for controllers that can be recorded both for a part and a track. The settings that you make for a controller are applied to all MIDI tracks that use this controller.

Use Global Settings

When this is selected, the automation track uses the global automation **Merge Mode** that is specified in the **MIDI Controller Automation Setup** dialog.

Replace 1 - Part Range

When this option is selected, the part data has playback priority over the automation track data. At the left and right part borders, for example, the automation mode switches abruptly from part to track automation, and vice versa.

Replace 2 - Last Value Continues

Similar to the above, but part automation only begins when the first controller event within the part is reached. At the end of the part, the last controller value is kept until an automation event is reached on the automation track.

Average

When this option is selected, the average values between part and track automation is used.


Modulation

In this mode, the automation track curve modulates the existing part automation, with higher curve points emphasizing the automation values and lower curve points reducing the automation values even further.

MIDI Controller Automation Setup

In the **MIDI Controller Automation Setup** dialog, you can specify how existing MIDI automation is handled on playback and new automation data is recorded in a MIDI part or as track automation. All settings that you make in this dialog are saved with the project.

- To open the **MIDI Controller Automation Setup** select **MIDI > CC Automation Setup**.



Record Destination on Conflict (global)

Allows you to determine which destination is used if MIDI controller data is received by Cubase and both the **Record** and the **Write Automation** buttons are enabled. Select **MIDI Part** to record MIDI part automation. Select **Automation Track** to record the controller data on an automation track in the **Project** window.

Automation Merge Mode (global)

Allows you to specify the global merge mode for automation.

Controller list

Lists all MIDI controllers for which you can specify the record destination and the merge mode for automation separately. This gives you full control over the MIDI automation (destination as well as merge mode) in your project.

Record Destination

Click in the **Record Destination** column for a MIDI controller to open the pop-up menu where you can choose where you want recorded data of this particular MIDI controller to be saved.

Automation Merge Mode

Click in the **Automation Merge Mode** column for a MIDI controller to specify what happens with data for this specific controller on playback.

Save As Default

Allows you to save the current settings as default settings. When you create a new project, the default settings are used.

Load Default

Allows you to load the default settings.

VST Instruments

VST instruments are software synthesizers or other sound sources that are contained within Cubase. They are played internally via MIDI. You can add effects or EQ to VST instruments.

Cubase allows you to make use of VST instruments in the following ways:

- By adding a VST Instrument and assigning one or several MIDI tracks to it.
- By creating an instrument track.
This is a combination of a VST instrument, an instrument channel, and a MIDI track. You play and record MIDI note data directly for this track.

NOTE

Some VST instruments are included with Cubase. These are described in the separate document **Plug-in Reference**.

RELATED LINKS

[Instrument Tracks](#) on page 105

Adding VST Instruments

PROCEDURE

1. On the **Studio** menu, select **VST Instruments**.
2. Right-click on an empty area of the **VST Instruments** window.
3. From the context menu, select one of the following:
 - **Add Track Instrument**
 - **Add Rack Instrument**
4. From the instrument selector, select an instrument.
 - Click **Add Track** if you chose to add a track instrument.
 - Click **Create** if you chose to add a rack instrument.

RESULT

If you chose **Add Track Instrument**, the instrument control panel opens, and an instrument track with the name of the instrument is added to your project.

If you chose **Add Rack Instrument**, the instrument control panel opens, and the following tracks are added to the track list:

- A MIDI track with the name of the instrument. The output of the MIDI track is routed to the instrument.

NOTE

In the **Preferences** dialog (**VST—Plug-ins** page), you can specify what happens when you load a VST instrument.

- A folder with the name of the instrument that is added within a **VST Instruments** folder. The instrument folder contains two automation tracks: one for the plug-in parameters and one for the synth channel in the **MixConsole**.

Creating Instrument Tracks

You can create instrument tracks that hold dedicated VST instruments.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. Open the **Instrument** pop-up menu and select a VST instrument for the instrument track.
3. Click **Add Track**.

RESULT

The selected VST instrument is loaded for the instrument track. In the **MixConsole** an instrument channel is added.

VST Instruments in the Right Zone

The **VST Instruments** in the right zone of the **Project** window allow you to add VST instruments for MIDI and instrument tracks.

All instruments that are used in your project are shown. You can access up to 8 quick controls for each added instrument.

To open the **VST Instruments** in the right zone, click **Show/Hide Right Zone**  on the **Project** window toolbar, and at the top of the right zone, click the **VST Instruments** tab.



NOTE

The **VST Instruments** in the right zone are just another representation of the **VST Instruments** window. All features are the same.

RELATED LINKS


[Showing/Hiding Zones](#) on page 39

VST Instruments Window

The **VST Instruments** window allows you to add VST instruments for MIDI and instrument tracks.

All instruments that are used in your project are shown. You can access up to 8 quick controls for each added instrument.

To open the **VST Instruments** window, select **Studio > VST Instruments**.



RELATED LINKS

[Instrument Tracks](#) on page 105

VST Instruments Toolbar

The VST instruments toolbar contains controls that allow you to add and set up VST instruments and VST quick controls.

The following controls are available:



1 Add Track Instrument

Opens the **Add Instrument Track** dialog that allows you to select an instrument and add an instrument track that is associated to this instrument.

2 Find Instruments

Opens a selector that allows you to find a loaded instrument.

3 Set Remote-Control Focus for VST Quick Controls to Previous/Next Instrument

Allows you to set the remote-control focus to the next/previous instrument.

4 Show/Hide all VST Quick Controls

Shows/Hides the default quick controls for all loaded instruments.

5 Settings


Opens the **Settings** menu where you can activate/deactivate the following modes:

- **Show VST Quick Controls for One Slot Only** shows the VST Quick Controls exclusively for the selected instrument.
- **MIDI Channel follows track selection** ensures that the **Channel** selector follows the MIDI track selection in the **Project** window. Use this mode if you work with multitimbral instruments.
- **Remote-Control Focus for VST Quick Controls follows track selection** ensures that the VST Quick Control remote-control focus follows the track selection.

VST Instrument Controls

The VST instrument controls allow you to make settings for a loaded VST instrument.

The following controls are available on each instrument:



1 Activate Instrument

Activates/Deactivates the instrument.

2 Edit Instrument

Opens the instrument panel.

3 Freeze Instrument

Freezes the instrument. This allows you to save CPU power.

4 Instrument Selector

Allows you to select another instrument. Double-click to rename the instrument. The name is shown in the **VST Instruments** window in the **Output Routing** pop-up menu for MIDI tracks. This is useful when you work with several instances of the same instrument.

5 Preset Browser

Allows you to load or save an instrument preset.

6 Input Options

This lights up when MIDI data is received by the instrument. Click this button to open a pop-up menu that allows you to select, mute/unmute, and solo/unsolo for tracks that send MIDI to the instrument (inputs).

NOTE

If you resize the VST Instruments window, you can access this option by using an **Input/Output Options** pop-up menu.

7 Activate Outputs

This control is only available if the instrument provides more than one output. It allows you to activate one or more outputs for the instrument.

NOTE

If you resize the VST Instruments window, you can access this option by using an **Input/Output Options** pop-up menu.

8 Read/Write Automation

Allows you to read/write automation for the instrument parameter settings.

9 Select Quick Control Layer

Allows you to select a program.

NOTE

The **Activate Side-Chain** option allows you to activate/deactivates side-chain input for VST 3 instruments that support side-chaining.

RELATED LINKS

[Freezing Instruments](#) on page 634

[Side-Chain Input for VST Instruments](#) on page 639

VST Instrument Context Menu

The following functions are available in the instruments context menu:

Copy/Paste Instrument Setting

Allows you to copy the instrument settings and paste them to another instrument.

Load/Save Preset

Allows you to load/save an instrument preset.

Default Preset

Allows you to define and save a default preset.

Switch to A/B Setting

Activates the setting A or B.

Copy A to B

Copies the effect parameters of effect setting A to effect setting B.

Activate Outputs

Allows you to activate one or more outputs for the instrument.

Activate Side-Chain

Activates/Deactivates side-chain input for the instrument.

NOTE

This option is only available for VST 3 instruments that support side-chaining.

Remote Control Editor

Opens the **Remote Control Editor**.

RELATED LINKS

[Side-Chain Input for VST Instruments](#) on page 639

Presets for Instruments

You can load and save presets for instruments. These contain all the settings that are required for the sound that you want.

The following presets for instruments are available:

- **VST presets** include the parameter settings of a VST instrument. These are available from the **VST instruments** window, from the instrument control panels, and from the **Programs** field in the Inspector.
- **Track presets** include the instrument track settings and the settings for the corresponding VST instrument. These are available from the Inspector or the track list context menu.

Loading VST Presets

You can load **VST Presets** from the **VST Instruments** window, from the instrument panel or from the Inspector.

PROCEDURE

1. Do one of the following:
 - Select the track that contains the VST instrument and in the **Inspector**, click the **Programs** field.
 - In the **VST Instruments** window, click **Preset Browser** for the instrument, and select **Load Preset**.
 - In the control panel for the VST instrument, click **Preset Browser**, and select **Load Preset**.
2. In the preset browser, select a preset from the list and double-click it to load it.

RESULT

The preset is applied. To return to the previously loaded preset, open the preset browser again and click **Revert to Last Setting**.

Saving VST Presets

You can save your settings on VST instruments as VST presets for further use.

PROCEDURE

1. Do one of the following:
 - In the **VST Instruments** window, click **Preset Browser** for the instrument, and select **Save Preset**.
 - In the control panel for the VST instrument, click **Preset Browser**, and select **Save Preset**.
2. In the **Save <VST instrument name> Preset** dialog, enter a name for the preset.
3. Optional: Click **Show Attribute Inspector** and define attributes for the preset.
4. Click **OK** to save the preset and close the dialog.

Loading Track Presets

You can load track presets for instrument tracks from the Inspector.

PROCEDURE

1. Do one of the following:
 - Select the instrument track and in the Inspector, click the **Load Track Preset** field.
 - Right-click the instrument track and from the context menu, select **Load Track Preset**.
2. In the preset browser, select a preset from the list and double-click it to load it.

RESULT

The track preset is applied. To return to the previously loaded preset, open the preset browser again and click **Revert to Last Setting**.

Saving Track Presets

You can save your settings on instrument tracks as track presets for further use.

PROCEDURE

1. Do one of the following:
 - Select the instrument track and in the Inspector, click **Save Track Preset**.
 - Right-click the instrument track and from the context menu, select **Save Track Preset**.
 2. In the **Save Track Preset** dialog, enter a name for the preset.
 3. Optional: Click **Show Attribute Inspector** and define attributes for the preset.
 4. Click **OK** to save the preset and close the dialog.
-

Playing Back VST Instruments

After you have added a VST instrument and selected a sound, you can play back the VST instrument using the instrument or MIDI track in your project.

PROCEDURE

1. In the track list, activate **Monitor** for the track that has the VST instrument loaded.
 2. Press one or more keys on your MIDI keyboard or use the **On-Screen Keyboard**. The corresponding sounds are triggered on your VST instrument.
 3. Select **Studio > MixConsole** to open the **MixConsole** and adjust the sound, add EQ or effects, assign another output routing, etc.
-

VST Instruments and Processor Load

VST instruments can consume a lot of CPU power. The more instruments you add, the more likely you will run out of processor power during playback.

If the CPU overload indicator in the **Audio Performance** window lights up or you get crackling sounds, you have the following options:

- Activate **Freeze** for instruments.
This renders the instrument into an audio file and unloads it.
- Activate **Suspend VST 3 plug-in processing when no audio signals are received** for VST 3 instruments.
This ensures that your instruments do not consume CPU power on silent passages.

RELATED LINKS

[Freezing Instruments](#) on page 634

[Suspend VST 3 plug-in processing when no audio signals are received](#) on page 1039

Freezing Instruments

If you are using a moderately powerful computer or a large number of VST instruments, your computer may not be able to play back all instruments in realtime. At this point, you can freeze instruments.

PROCEDURE

1. Do one of the following:

- Select **Studio > VST Instruments**.
 - Select the instrument track and open the top **Inspector** section.
2. Click **Freeze**.
 3. In the **Freeze Instrument Options** dialog, make your settings.
 4. Click **OK**.
-

RESULT

- The instrument is rendered to an audio file and on playback you hear the same sound as before freezing.
- Less CPU load is used.
- The **Freeze** button lights up.
- The MIDI/instrument track controls are grayed out.
- The MIDI parts are locked.

NOTE

To edit the tracks, parameters, or synth channels again, and to delete the rendered file, unfreeze the instrument by clicking **Freeze** again.

Freeze Instrument Options

The **Freeze Instrument Options** dialog opens when you click **Freeze**. It allows you to specify exactly what should happen if you freeze an instrument.

The following controls can be found in the **Freeze Instrument Options** dialog:

Freeze Instrument Only

Activate this option if you still want to be able to edit insert effects on the synth channel after freezing the instrument.

Freeze Instrument and Channels

Activate this option if you do not need to edit the insert effects on your synth channels.

NOTE

You can still adjust level, pan, sends, and EQ.

Tail Size

Allows you to set a Tail Size time to let sounds complete their normal release cycle.

Unload Instrument when Frozen

Activate to unload the instrument after freezing. This makes the RAM available again.

Latency

The term latency stands for the time it takes for the instrument to produce a sound when you press a key on your MIDI controller. It can be an issue when using VST instruments in realtime. Latency depends on your audio hardware and its ASIO driver.

In the **Studio Setup** dialog (**VST Audio System** page), the input and output latency values should ideally be a few milliseconds.

If the latency is too high to allow comfortable realtime VST instrument playback from a keyboard, you can use another MIDI sound source for live playback and recording, and switch to the VST instrument for playback.

RELATED LINKS

[Selecting an Audio Driver](#) on page 12

Delay Compensation

During playback Cubase automatically compensates any delay inherent in the VST plug-ins you use.

You can specify a **Delay Compensation Threshold** in the **Preferences** dialog (VST page) so that only plug-ins with a delay higher than this threshold setting are affected.

Constrain Delay Compensation

To avoid Cubase to add latency when you play a VST instrument in realtime or record live audio, you can activate **Constrain Delay Compensation**. This minimizes the latency effects of the delay compensation, while maintaining the sound of the mix as far as possible.

Constrain Delay Compensation  is available on the **Project** window toolbar and in the **Transport** zone. You can also find it as a menu item in the **MixConsole** on the **Functions** menu.

Activating **Constrain Delay Compensation** turns off VST plug-ins which are activated for VST instrument channels, audio track channels that are record-enabled, group channels, and output channels. VST plug-ins which are activated for FX channels are disregarded. After recording or using a VST instrument **Constrain Delay Compensation** should be deactivated again in order to restore full delay compensation.


Import and Export Options

Importing MIDI Loops

You can import MIDI loops (file extension .midiloop) in Cubase. These files contain MIDI part information (MIDI notes, controllers, etc.) and all the settings that are saved in instrument track presets. This way, you can reuse instrument patterns in other projects or applications, for example.

PROCEDURE

1. Select **Media > MediaBay**.
2. Optional: In the **Results** section, open the **Select Media Types** menu, and activate **MIDI Loops** and **Plug-in Presets**.



3. In the results list, select a MIDI loop and drag it to an empty section in the **Project** window.
-

RESULT

An instrument track is created and the instrument part is inserted at the position where you dragged the file. The **Inspector** reflects all settings that are saved in the MIDI loop, for example, the VST instrument that was used, applied insert effects, track parameters, etc.

NOTE

You can also drag MIDI loops onto existing instrument or MIDI tracks. However, this only imports the part information. This means this part only contains the MIDI data (notes, controllers) that is saved in the MIDI loop, but no inspector settings or instrument parameters.

RELATED LINKS

[Presets for Instruments](#) on page 632

[Filtering According to Media Type](#) on page 558

Exporting MIDI Loops

You can export MIDI loops to save a MIDI part together with its instrument and effect settings. This allows you to reproduce patterns that you created without having to search for the correct sound, style, or effect. MIDI loops have the file extension `.midiloop`.

PROCEDURE

1. Select an instrument part.
 2. Select **File > Export > MIDI Loop**.
 3. In the **New MIDI Loop** section, enter a name for the MIDI loop.
 4. Optional: To save attributes for the MIDI loop, click the button below the **New MIDI Loop** section at the bottom left.
The **Attribute Inspector** section opens, allowing you to define attributes for your MIDI loop.
 5. Click **OK**.
-

RESULT

MIDI Loop files are saved in the following folder:

Windows: `\Users\\AppData\Roaming\Steinberg\MIDI Loops`

macOS: `/Users/<user name>/Library/Application Support/Steinberg/MIDI Loops/`

The default folder cannot be changed. However, you can create subfolders within this folder to organize your MIDI loops. To create a subfolder, click **New Folder** in the **Save MIDI Loop** dialog.

Exporting Instrument Tracks as MIDI File

You can export instrument tracks as standard MIDI files.

NOTE

- As there is no MIDI patch information in an instrument track, this information is missing in the resulting MIDI file.
 - If you activate **Export Inspector Volume/Pan**, volume and pan information of the VST instrument are converted and written into the MIDI file as controller data.
-

RELATED LINKS

[Exporting MIDI Tracks as Standard MIDI File](#) on page 157

VST Quick Controls

VST Quick Controls allow you to remote-control a VST instrument from within the **VST Instruments** window.

To show the **VST Quick Controls** on the **VST Instruments** window, activate **Show/Hide all VST Quick Controls**.

The following controls are available on each rack:



- 1 Show/Hide VST Quick Controls**
Allows you to show/hide the **VST Quick Controls** for the instrument.
- 2 VST Quick Controls**
Allow you to remote-control the parameters of the instrument.

NOTE

The number of **VST Quick Controls** that are shown depends on the size of the **VST Instruments** window.

- 3 Set Remote-Control Focus for VST Quick Controls**
Allows you to activate the **VST Quick Controls** to remote-control the instrument.

RELATED LINKS

- [Remote Controlling Cubase](#) on page 652
- [Connecting VST Quick Controls with Remote Controllers](#) on page 638
- [Activating Pick-up Mode for Hardware Controls](#) on page 651

Connecting VST Quick Controls with Remote Controllers

VST Quick Controls become powerful, if you use them together with a remote controller.

PREREQUISITE

The MIDI output on your remote unit is connected to a MIDI input on your MIDI interface.

PROCEDURE

- Select **Studio > Studio Setup**.
- In the **Devices** list, select **VST Quick Controls**.
- Open the **MIDI Input** pop-up menu, and select a MIDI input.
- Optional: Open the **MIDI Output** pop-up menu, and select a MIDI output.
- Click **Apply**.
- Activate **Learn**.
- In the **Control Name** column, select **QuickControl 1**.
- On your MIDI device, move the control that you want to connect with the first quick control.
- Select the next slot in the **Control Name** column and repeat the previous steps.

10. Click **OK**.

RESULT

The **VST Quick Controls** are now connected with control elements on your MIDI device. If you move a control element, the value of the parameter that is assigned to the corresponding **VST Quick Controls** changes accordingly.

NOTE

The remote controller setup for **VST Quick Controls** is saved globally, that is, it is independent of any projects.

RELATED LINKS

[Generic Remote](#) on page 656

Side-Chain Input for VST Instruments

You can send audio into VST 3 instruments that feature a side-chain input. Side-chaining allows you to use the output of one track to control the action of an instrument on another track.

Depending on the instrument, activating its side-chain input allows you to:

- Use the instrument as an effect plug-in on audio events.
- Use the side-chain signal as a modulation source.
- Apply ducking to the instrument, that is, reduce the volume of the instrument track when a signal is present on the audio track.

You can route the audio signal to the side-chain input of an instrument in different ways:

- To process the audio signal completely through the instrument, route the output of the audio track to the side-chain input of an instrument.
- To use both the clean audio signal and the signal processed by the instrument, route a send to the instrument side-chain.

NOTE

To hear the audio played through the instrument, you must trigger a note, either by playing MIDI events or by playing notes on your external MIDI keyboard.

RELATED LINKS

[Using Instruments as Effects on Audio Tracks](#) on page 639

Using Instruments as Effects on Audio Tracks

You can use instruments that support side-chaining to modify the audio on audio tracks. The following example shows you how to apply the parameters in Retrologue to a drum loop.

PREREQUISITE

You have a drum loop on an audio track. You have created an instrument track with Retrologue loaded.

PROCEDURE

1. In the header of the Retrologue panel, click **Activate Side-Chain**.
2. Open the **Output Routing** pop-up menu in the **Inspector** for the audio track and select the side-chain input of Retrologue.

3. On the Retrologue panel in the **Oscillator Mix** section, adjust the **Input Level** control. This adjusts the input level of the incoming audio.
4. Optional: Deactivate oscillators **OSC 1**, **OSC 2**, and **OSC 3**.
5. Do one of the following:
 - On the instrument track, create a MIDI event, set up a cycle with the left and right locators, and activate cycle mode.
 - Play notes on your MIDI keyboard.

NOTE

For this to work, your MIDI keyboard must be installed and set up.

RESULT

When a note is played, the drum loop is played back through Retrologue.

AFTER COMPLETING THIS TASK

Use Retrologue to modify the sound of your drum loop. For example, you can do the following:

- Use the filter and distortion settings on the **Synth** page.
- Modulate the input signal. To do this, select **Modulation Matrix > Destination > Oscillator > Audio Input**.
- Set up a rhythmical modulation on the **Arp** page.
- Use the effects on the **FX** page, for example the **Resonator**.

NOTE

For detailed information about Retrologue and its parameters, see the separate document **Retrologue**.

External Instruments (Cubase Pro only)

An external instrument bus is an input (return) to your audio hardware, along with a MIDI connection via Cubase and few additional settings.

External instrument busses are created in the **Audio Connections** window. All external instrument busses that you have created will appear on the **VST Instrument** pop-up menus and can be selected in the same way as any VST instrument plug-in.

If you select an external instrument, you play it via MIDI as usual (you have to create a MIDI device to play it) and the sound (synth audio output) will come in to the VST environment where you can apply processing, etc.

RELATED LINKS

[Setting Up External Instruments](#) on page 33

Installing and Managing Plug-Ins

Installing VST Plug-Ins

Cubase supports the VST 2 and VST 3 plug-in standards. You can install effects and instruments that comply with these formats.

A plug-in is a piece of software that adds a specific functionality to Cubase. The audio effects and instruments that are used in Cubase are VST plug-ins.

Effect or instrument plug-ins normally have their own installation application. Read the documentation or readme files before installing new plug-ins.

When you scan for newly installed plug-ins or relaunch Cubase, the new effects appear on the effect selectors.

Cubase comes with a number of effect plug-ins included. These effects and their parameters are described in the separate document **Plug-in Reference**.

VST Plug-In Manager

The **VST Plug-in Manager** provides lists of the effects and VST instruments that are installed on your computer. These lists are used in the selectors for VST instruments and effects.

The **VST Plug-in Manager** allows you to do the following:

- You can view lists of all effects and VST instruments that are loaded by Cubase when you launch the program.
The lists of all effects or VST instruments are created automatically every time you start Cubase. You can also initiate a rescan at any time. This ensures that these lists are always up-to-date.
- You can create your own lists of effects or instruments for use in the selectors for effects or instruments. User-defined lists are called collections.
Collections allow you to create sub-sets of the available effects or instruments, for example, to give you a better overview of the effects used in a project.


NOTE

If an installed effect or instrument cannot be loaded by Cubase, it does not appear in the list of all effects or instruments. Also, the effect or instrument is grayed out in any collections in which it is included. For example, this can happen if a copy-protection dongle required to run the effect or instrument is missing, or after uninstalling a plug-in.

VST Plug-In Manager Window

You can manage your effects and VST instruments in the **VST Plug-in Manager** window.

- To open the **VST Plug-in Manager** window, select **Studio > Plug-in Manager**.



The **VST Plug-in Manager** window shows the following:

VST Effects

This tab lists all VST effects that are loaded in Cubase. You can sort the list by name, vendor, category, etc. by clicking the corresponding column heading.

VST Instruments

This tab lists all VST instruments that are loaded in Cubase. You can sort the list by name, vendor, category, etc. by clicking the corresponding column heading.

Blacklist

This tab lists all VST effects and VST instruments that are installed on your system but not loaded in Cubase. These plug-ins might lead to stability problems or even cause the program to crash. As Cubase does not support 32-bit, all 32-bit plug-ins are shown in this list.

NOTE

You can reactivate a blacklisted 64-bit plug-in by selecting it and clicking **Reactivate**. This causes Cubase to rescan the plug-in and remove it from the blacklist. To move the plug-in back to the blacklist, you must rescan all plug-ins and restart Cubase.

Collection list

By default, the window section to the right shows the **Default** collection, which contains all effects or VST instruments loaded by the program. The **Default** collection cannot be changed.

You can compile your own collections of effects or VST instruments by clicking **New Collection** and dragging and dropping items from the list of all effects or VST instruments to the collection list.

Collections are shown in the selectors for effects/VST instruments, and all changes made to collections in the **VST Plug-in Manager** are immediately reflected in the selectors.

Search Field



Enter the name of a plug-in in the search field. The list of all effects or VST instruments is filtered to show only those plug-ins whose names contain the text that you entered.

Display Options



Allows you to choose which plug-ins are shown:

- To show all loaded plug-ins, select **Show All Plug-ins**.
- To hide all plug-ins that are part of the active collection, select **Hide Plug-ins That Are in Active Collection**.
- To show all VST 3 plug-ins that support 64-bit processing, select **Show Plug-ins That Support 64-Bit Float Processing**.

NOTE

This might take a while since all your plug-ins must be scanned.

New Folder



Allows you to create a new folder in the current collection.

Delete



Allows you to delete the selected item in the current collection.

New Collection



Allows you to create a new collection.

To create a new, empty list, select **Empty**. To create a new collection based on the list of all effects, select **Add All Plug-ins**. To create a new collection based on the current collection, select **Add Current Collection**.

User Collections



Allows you to select a different collection, and to rename or delete the current collection.

To remove unavailable plug-ins from all collections, select **Remove Unavailable Plug-ins from All Collections**.

Show VST Plug-in Information



Opens a section at the bottom of the window in which more information about the selected item is shown. If you select several plug-ins, the information for the plug-in that you have selected first is shown. In this section, you can also deactivate selected plug-ins. Deactivated plug-ins are no longer available in collections. This is useful if you have plug-ins installed that you do not want to use in Cubase.

VST Plug-in Manager Settings



Opens a section at the bottom of the window in which all current paths to VST 2 plug-ins are listed. You can add or remove folder locations by using the corresponding buttons. Click **Rescan All** to rescan your computer for plug-ins.

RELATED LINKS

[VST Plug-In Manager](#) on page 641

[VST Audio System](#) on page 13

Compiling a New Effects Collection


You can create a new collection of effects or VST instruments for use in the plug-in selectors.

PREREQUISITE

A number of effect plug-ins is correctly installed on your computer, and these plug-ins are listed on the **VST Effects** tab of the **VST Plug-in Manager** window.

PROCEDURE

1. In the **VST Plug-in Manager** window, click **New Collection** and do one of the following:
 - To create a new collection based on the list of all effects, select **Add All Plug-ins**.
 - To create a new collection based on the current collection, select **Copy Current Collection**.



2. Enter a name for the new collection and click **OK**.
3. Drag items from the list of all effects and drop them to the new collection. A line indicates the drop position.
 - Click **New Folder** to create folders and place items directly in them.
 - You can drag items to new positions within the collection.
 - Drag items from the collection list to the list of all plug-ins to delete them, or select items and click **Delete**.

RESULT

The new collection is saved automatically and made available in the plug-in selectors.

The procedure is the same for compiling collections of VST instruments.

Track Quick Controls

Cubase allows you to set up 8 different track parameters or settings as **Track Quick Controls** for quick access.

Track Quick Controls are available for the following track types:

- Audio
- MIDI
- Instrument
- Sampler
- FX Channel
- Group Channel
- VCA Fader (Cubase Pro only)


For instrument tracks and for MIDI tracks for which you assigned a VST instrument on creation, that is, that you created by loading a rack instrument, **Track Quick Controls** are automatically assigned to the **Quick Controls** of the VST instrument.

For sampler tracks, **Track Quick Controls** are automatically assigned to the sound parameters of **Sampler Control**.


NOTE

You can change the default assignment by assigning different track parameters or by loading a preset.

Assigning parameters to **Quick Controls** is done in the **Inspector** or the **MixConsole**.



Quick Controls section in the Inspector



Track Quick Controls rack in the MixConsole

Quick Controls assignments are saved with the project.

You can assign **Track Quick Controls** to an external remote control device. For this to work, you must connect **Track Quick Controls** with your remote controller.

You can automate parameter settings in the **Quick Controls** section using the **Read/Write** buttons (**R** and **W**).

RELATED LINKS

[Track Presets](#) on page 179

[Automation](#) on page 606

[Channel Racks](#) on page 328

Parameter Assignment

You can assign track, effect, and instrument parameters to **Quick Controls**.

For the parameter assignment, you can use the **Inspector** or the **MixConsole**. You can assign parameters manually, use the **QC Learn Mode**, or load an assignment preset.

RELATED LINKS

[Assigning Track Parameters to Quick Controls](#) on page 646

[Assigning Effect Parameters to Quick Controls](#) on page 647

[Using QC Learn Mode](#) on page 647

[Assigning MixConsole Parameters to Quick Controls](#) on page 648

[Setting Instrument Parameter Assignments to Default](#) on page 648

[Removing Parameter Assignments](#) on page 648

[Loading Track Quick Control Assignments as Presets](#) on page 649

Assigning Track Parameters to Quick Controls

You can assign track parameters manually.

NOTE

For instrument tracks and MIDI tracks for which you assigned a VST instrument on creation, the main parameters of the instrument are automatically assigned to the slots in the **Quick Controls** section in the **Inspector**.

PROCEDURE

1. In the **Inspector** for your track, open the **Quick Controls** section.
2. In the **Quick Controls** section, click the first slot to open a selector that lists all parameters for the track.
3. Select the parameter that you want to assign to the first **Quick Control**.

The parameter name and its value are displayed in the slot. You can change the value by dragging the slider.



4. Repeat these steps for all slots for which you want to assign track parameters.
-

RESULT

You can now control the track parameters via the **Quick Controls** section in the **Inspector** or via the **Track Quick Controls** rack in the **MixConsole**.

AFTER COMPLETING THIS TASK

You can rename a **Quick Control** by double-clicking on the name and entering a new one. This is useful if a parameter name is very long, for example.

Assigning Effect Parameters to Quick Controls

You can assign effect parameters to **Quick Control** slots directly from within plug-in panels.

NOTE

This is only available for VST 3 plug-ins that support this function.

PROCEDURE

- In the effect plug-in panel, right-click the parameter.
 - Select **Add "x" to Quick Controls** (where x is the name of the parameter) to assign the parameter to the next empty slot.
 - Select **Add "x" to Quick Controls Slot** (where x is the name of the parameter), and select the slot from the submenu to assign the parameter to a specific slot.
-

RESULT

You can now control the effect parameters via the **Quick Controls** section in the **Inspector** or via the **Track Quick Controls** rack in the **MixConsole**.

Using QC Learn Mode

The **QC Learn Mode** allows you to assign a parameter by moving controls. This applies to all automatable controls.

PROCEDURE

1. In the **Inspector** for your track, open the **Quick Controls** section.
 2. Activate **QC Learn Mode**.
 3. Select the slot to which you want to assign a parameter.
 4. Move the control.
-

RESULT

The track parameter is assigned to the corresponding control.

RELATED LINKS

[Quick Controls and Automatable Parameters](#) on page 649

Assigning MixConsole Parameters to Quick Controls

You can assign **MixConsole** parameters to **Quick Controls**.

PROCEDURE

- In the **MixConsole**, right-click the parameter that you want to assign to a **Quick Control**.
 - Select **Add “x” to Quick Controls** (where x is the name of the parameter) to assign the parameter to the next empty slot.
 - Select **Add “x” to Quick Controls Slot** (where x is the name of the parameter), and select the slot from the submenu to assign the parameter to a specific slot.

RESULT

You can now control the **MixConsole** parameters via the **Quick Controls** section in the **Inspector** or via the **Track Quick Controls** rack in the **MixConsole**.

RELATED LINKS

[Track Quick Controls](#) on page 645

[Adding Track Quick Controls in the MixConsole](#) on page 362

Setting Instrument Parameter Assignments to Default

If you have changed the parameter assignment or if you manually routed a MIDI track to a VST instrument, you can retrieve the default assignments.

PROCEDURE

1. In the **Inspector** for the instrument or MIDI track, open the **Quick Controls** section.
2. Click **Get Default QCs from Plug-in**.

RESULT

The instrument parameter assignments are set to default.

Removing Parameter Assignments

You can remove parameter assignments for individual **Quick Controls** or for all **Quick Controls** at once.


PROCEDURE

- Do one of the following:
 - To remove a parameter from a slot, click in the corresponding slot and select **No parameter** from the pop-up menu.

NOTE

You can also double-click the parameter name, press **Delete** or **Backspace**, and confirm with **Return**.

- To remove the **Quick Control** assignments for all slots, click **Remove All QC Assignments**.



Saving Track Quick Control Assignments as Presets

You can save **Quick Control** assignments as track presets.

PREREQUISITE

You have assigned track parameters to **Quick Controls**.

PROCEDURE

1. In the **Inspector** for your track, open the **Quick Controls** section.
2. In the **Quick Controls** section, click **Preset Management** .
3. Click **Save Preset**.
4. Enter a name in the **Type In Preset Name** dialog.
5. Click **OK**.

RESULT

The **Quick Control** assignment is saved as a preset.

RELATED LINKS

[Assigning Track Parameters to Quick Controls](#) on page 646

Loading Track Quick Control Assignments as Presets

You can load presets for **Quick Control** assignments.

PROCEDURE

1. In the **Inspector** for your track, open the **Quick Controls** section.
2. In the **Quick Controls** section, click **Preset Management** .
3. Select one of the presets in the upper list of the menu.

RESULT

The preset is loaded and allows you to access the channel parameters.

Quick Controls and Automatable Parameters

You can use **Quick Controls** to control all automatable parameters. This allows you to control parameters on other tracks using **Quick Controls**.


IMPORTANT

Use this function with caution, as you might accidentally modify parameters on other tracks.

PROCEDURE

1. Create a new, empty audio track and open the **Quick Controls** section.

2. Hold down the **Ctrl/Cmd** key and click the first **Quick Control** slot.
The selector lists all automatable parameters.
3. Open the **VST Mixer** folder.
The selector lists all channels that are available in the **MixConsole** of your project.



4. Assign a parameter of one particular channel to **Quick Control 1**, and another parameter of another channel to **Quick Control 2**.

RESULT

The **Quick Controls** section now allows you to control automatable parameters on different tracks.

IMPORTANT

You cannot save **Quick Control** assignments for automatable parameters on different tracks as track presets.

Showing Automated Quick Control Assignments

You can show all **Quick Control** assignments that have been automated for one track.

PROCEDURE

1. Click the track for which you want to show automated **Quick Control** assignments.
2. In the **Inspector** for your track, open the **Quick Controls** section.
3. In the **Quick Controls** section, click **Preset Management** .
4. Select **Show Automated QC Assignments**.

RESULT

The automation tracks of the automated **Quick Control** parameters open for the selected track.

NOTE

- If **Volume** is assigned as a **Quick Control** parameter, it is always shown as automated, independent of whether it is automated or not.
 - You can also show automated **Quick Control** assignments via the **Track Quick Controls** rack in the **MixConsole**.
-

Connecting Track Quick Controls with Remote Controllers

Track Quick Controls become powerful if you use them together with a remote controller.

PREREQUISITE

The MIDI output on your remote unit is connected to a MIDI input on your MIDI interface.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **Track Quick Controls**.
 3. Open the **MIDI Input** pop-up menu, and select a MIDI input.
 4. Optional: Open the **MIDI Output** pop-up menu, and select a MIDI output.
 5. Click **Apply**.
 6. Activate **Learn**.
 7. In the **Control Name** column, select **QuickControl 1**.
 8. On your MIDI device, move the control that you want to connect with the first quick control.
 9. Select the next slot in the **Control Name** column and repeat the previous steps.
 10. Click **OK**.
-

RESULT

The **Track Quick Controls** are now connected with control elements on your MIDI device. If you move a control element, the value of the parameter that is assigned to the corresponding **Track Quick Controls** changes accordingly.

NOTE

The remote controller setup for **Track Quick Controls** is saved globally, that is, it is independent of any projects.

RELATED LINKS

[Generic Remote](#) on page 656

Activating Pick-up Mode for Hardware Controls

Pick-up Mode allows you to change configured **Quick Control** parameters without accidentally modifying the previous values. This is useful if you want the control to pick up the parameter at the value to which it was last set. If you move a hardware control, the parameter only changes once the control reaches the previous value.

NOTE

This only applies to hardware controllers whose controls use specific ranges.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **Track Quick Controls** or **VST Quick Controls**.
 3. Activate **Pick-up Mode**.
 4. Click **OK**.
-

Remote Controlling Cubase

You can control Cubase via MIDI with a connected MIDI device.

The supported devices are described in the separate document **Remote Control Devices**. You can also use a generic MIDI controller to remote control Cubase.

NOTE

Most remote control devices are able to control both MIDI and audio channels in Cubase, but the parameter setup may be different. Audio-specific controls such as EQ are disregarded when controlling MIDI channels.

RELATED LINKS

[Generic Remote](#) on page 656

Connecting Remote Devices

You can connect your remote device via USB or via MIDI.

PROCEDURE

- Do one of the following:
 - If your remote device provides a USB MIDI port, use a USB cable to connect it to the USB port of your computer.
 - If your remote device provides a MIDI output, use a MIDI cable to connect it to a MIDI input on your MIDI interface.

NOTE

If the remote unit features feedback devices such as indicators, motorized faders, etc., connect a MIDI Out on the interface to a MIDI In on the remote unit.

RELATED LINKS

[MIDI Connections](#) on page 18

Removing the Remote Input from All MIDI Inputs

To avoid that you accidentally record data from the remote unit when you record MIDI, you must remove the remote input from **'All MIDI Inputs'**.

PROCEDURE

1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select **MIDI Port Setup**.

3. In the table on the right, deactivate **In 'All MIDI Inputs'** for the MIDI input to which you have connected the MIDI remote unit.
The **State** column reads **Inactive**.
4. Click **OK**.

RESULT

The remote unit input is removed from the **All MIDI Inputs** group.

RELATED LINKS

[MIDI Port Setup](#) on page 19

Setting Up Remote Devices


PROCEDURE

1. Select **Studio > Studio Setup**.
2. Click + in the top left corner and select a remote device from the pop-up menu to add it to the **Devices** list.

NOTE

If your device is not available in the pop-up menu, select **Generic Remote**.

3. In the **Devices** list, select the device.
Depending on the selected device, either a list of programmable function commands or a blank panel is shown in the right half of the dialog window.



4. Open the **MIDI Input** pop-up menu, and select a MIDI input.
5. Optional: Open the **MIDI Output** pop-up menu, and select a MIDI output.
6. Click **OK**.

RESULT

You can now use the MIDI device to control Cubase functions.

A bright stripe in the **Project** window and in the **MixConsole** indicates which channels are linked to the remote control device.



You can open a panel for the added device by selecting **Studio > More Options**.

AFTER COMPLETING THIS TASK

Depending on your external MIDI control device, you might need to configure the parameters.

Resetting Remote Devices

Sometimes you must reset remote devices, because the communication between Cubase and a remote device was interrupted or the handshaking protocol fails to create a connection.

PROCEDURE


1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select the remote device.
3. Click **Reset** in the lower part of the **Studio Setup** dialog to reset the selected remote device.

NOTE

To reset all devices in the **Devices** list, click **Send Reset Message to all Devices** in the top left of the dialog.

Global Options for Remote Controllers

On the page for your remote device, global functions may be available.



MIDI Input

Allows you to select a MIDI Input.

MIDI Output

Allows you to select a MIDI Output.

User Commands

Lists the controls or buttons of your remote device.

Smart Switch Delay

Allows you to specify a delay for the smart switch function. Functions that support the smart switch behavior are activated for as long as the button is pressed.

Enable Auto Select

On touch-sensitive remote control devices this automatically selects a channel when you touch a fader. On devices without touch-sensitive faders, the channel gets selected as soon as you move the fader.

Remote Devices and Automation

You can write automation using remote devices.

If your remote device does not have touch-sensitive controls and you want to replace existing automation data in **Write** mode, consider the following:

- Make sure that you move only the controller that you want to replace.
- Stop playback to deactivate **Write** mode.

This way, all data for the corresponding parameter is replaced from the position where you moved the control, up to the position where you stop playback.

Assigning Commands to Remote Devices


You can assign any Cubase command to which a key command can be assigned to remote devices.

PROCEDURE

1. Select **Studio > Studio Setup**.

2. In the **Devices** list, select your remote device.

In the **User Commands** section, the controls or buttons of your remote device are listed in the **Button** column.



3. Click in the **Category** column for the control to which you want to assign a Cubase command, and select the category from the pop-up menu.

The categories correspond to the categories in the **Key Commands** dialog.

4. Click in the **Command** column, and select the Cubase command from the pop-up menu. The available items on the pop-up menu depend on the selected category.
5. Click **Apply**.

RESULT

The selected function is assigned to the button or control on the remote device.


RELATED LINKS

[Key Commands](#) on page 973

Generic Remote

You can use a generic MIDI controller to remote control almost any function in Cubase. After setting up the **Generic Remote** device, you can control the specified parameters from the MIDI remote device.

- To open the **Generic Remote** settings, select **Studio > Studio Setup**, and from the **Devices** list, select **Generic Remote**.



The following options are available:

MIDI Input

Allows you to select the MIDI input port to which your remote device is connected.

MIDI Output

Allows you to select the MIDI output port to which your remote device is connected.

MIDI Remote Control Configuration

The upper table shows the MIDI remote control configuration of your remote device.

Cubase Control Assignment

The lower table allows you to assign Cubase controls to your remote device.

RELATED LINKS


[MIDI Remote Control Configuration](#) on page 657

[Cubase Control Assignment](#) on page 658

MIDI Remote Control Configuration

The MIDI remote control configuration is shown in the upper table of the **Generic Remote** setup page.

- To open the **Generic Remote** settings, select **Studio > Studio Setup**, and from the **Devices** list, select **Generic Remote**.



Control Name	MIDI Status	MIDI Channel	Address	Max. Value	Flags
Fader 1	Controller	1	7	127	R...
Fader 2	Controller	2	7	127	R...
Fader 3	Controller	3	7	127	R...
Fader 4	Controller	4	7	127	R...
Fader 5	Controller	5	7	127	R...
Fader 6	Controller	6	7	127	R...
Fader 7	Controller	7	7	127	R...
Fader 8	Controller	8	7	127	R...
Fader 9	Controller	9	7	127	R...
Fader 10	Controller	10	7	127	R...
Fader 11	Controller	11	7	127	R...
Fader 12	Controller	12	7	127	R...

The following options are available in the upper table:

Control Name

Double-click this field to change the name for the control, and enter the one written on the console, for example. This name is automatically reflected in the lower table.

MIDI Status

Allows you to specify the type of MIDI message sent by the control.

MIDI Channel

Allows you to select the MIDI channel on which the controller is transmitted.

Address

Allows you to specify the continuous controller number, the pitch of a note, or the address of an NRPN/RPN continuous controller.

Max. Value

Allows you to specify the maximum value that the control transmits. This value is used by the program to scale the value range of the MIDI controller to the value range of the program parameter.

Flags

Allows you to select one of the following flags:

- **Receive**
Activate this if the MIDI message should be processed on reception.
- **Transmit**
Activate this if a MIDI message should be transmitted when the corresponding value in the program changes.
- **Relative**
Activate this if the control is an endless rotary encoder, which reports the number of turns instead of an absolute value.
- **Pick-up**
Activate this if you want the control to pick up the parameter at the value to which it was last set.

The buttons and options to the right of the table have the following function:

Import

Allows you to import saved remote setup files.

Export

Allows you to export the current setup with the file extension .xml.

Add

Adds controls to the bottom of the table.

Delete

Deletes the selected control from the table.

Learn

Allows you to assign MIDI messages by learning.

Cubase Control Assignment

You can specify the Cubase control assignment in the lower table of the **Generic Remote** setup page. Each row in the table is assigned to the controller in the corresponding row in the MIDI remote control configuration table.

- To open the **Generic Remote** settings, select **Studio > Studio Setup**, and from the **Devices** list, select **Generic Remote**.

Control Name	Device	Channel/Category	Value/Action	Flags
Fader 1	VST Mixer	Audio 01	1025	..
Fader 2	VST Mixer	Audio 02	1025	..
Fader 3	VST Mixer	Audio 03	1025	..
Fader 4	VST Mixer	Audio 01	1025	..
Fader 5	VST Mixer	Stereo In	1025	..
Fader 6	VST Mixer	Stereo Out	1025	..
Fader 7	VST Mixer	6	1025	..
Fader 8	VST Mixer	7	1025	..
Fader 9	VST Mixer	8	1025	..
Fader 10	VST Mixer	9	1025	..
Fader 11	VST Mixer	10	1025	..
Fader 12	VST Mixer	11	1025	..

The following options are available:

Control Name

Reflects the control name selected in the upper table.

Device

Allows you to select the Cubase device that you want to control.

Channel/Category

Allows you to select the channel or the command category that you want to control.

Value/Action

Allows you to select the parameter of the channel that you want to control. If the **Command** device is selected, this is where you specify the **Action** of the category.

Flags

Allows you to select one of the following flags:

- **Push Button**
Activate this if the parameter should only be changed if the received MIDI message shows a value unequal to 0.
- **Toggle**

Activate this if the parameter value should be switched between minimum and maximum value each time a MIDI message is received.

You can combine **Push Button** and **Toggle** for remote controls which do not latch the state of a button. This is useful if you want to control the mute status with a device on which pressing the mute button turns it on, and releasing the mute button turns it off.

- **Not Automated**

Activate this if the parameter value should not be automated.

The buttons to the right of the table have the following functions:

Bank pop-up menu

Allows you to switch banks. This is necessary if your MIDI control device has 16 volume faders, and you are using 32 MixConsole channels in Cubase, for example.

Rename

Allows you to rename the selected bank.

Add

Adds banks to the pop-up menu.

Delete

Deletes the selected bank from the pop-up menu.

RELATED LINKS

[Assignable Devices and Functions](#) on page 659

Assignable Devices and Functions

The **Device** column in the Cubase control assignment lists the Cubase devices that you can control.

Command

Allows you to assign the Cubase commands to which a key command can be assigned. If you select **Add Track** in the **Channel/Category** column, and **Audio** in the **Value/Action** column, you can add audio tracks using your MIDI device, for example.

VST Quick Controls Manager

Allows you to assign **VST Quick Controls**. If you select **Device** in the **Channel/Category** column, and one of the **Quick Control** options in the **Value/Action** column, you can control that VST quick control using your MIDI device.

Midi Mixer

Allows you to control the functions of the **Midi Mixer** panel. If you select **Device** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function using your MIDI device.

MMC Master

Allows you to control the functions of the **MMC Master** panel. If you select **Device** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function using your MIDI device.

Mixer

Allows you to control **MixConsole** functions. If you select one of the available channels or **Selected** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function of that specific channel or of the selected channel using your MIDI device.

Transport

Allows you to control the transport functions. If you select **Device** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function using your MIDI device.

Metronome

Allows you to control metronome functions. If you select **Device** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function using your MIDI device.

VST Mixer

Allows you to control **MixConsole** functions. If you select one of the available channels or **Selected** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function of that specific channel or of the selected channel using your MIDI device.

VST Control Room

Allows you to control the functions of the **Control Room**. If you select **Device** in the **Channel/Category** column, and one of the options in the **Value/Action** column, you can control that function using your MIDI device.

NOTE

You can also control all **VST Instruments** that you added in the **Project** window, and that are listed in the **Device** column.

Assigning MIDI Messages in Learn Mode

You can assign MIDI messages in **Learn** mode.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **Generic Remote**.
 3. Activate **Learn**.
 4. Select the control in the upper table, and move the corresponding control on your MIDI device.
-

RESULT

The values for **MIDI Status**, **MIDI Channel**, and **Address** are automatically set to those of the moved control.

NOTE


If you use the **Learn** function for a control that sends a program change value, **Prog. Change Trigger** is automatically selected in the **MIDI Status** pop-up menu. This allows you to use the different values of a program change parameter to control different parameters in Cubase.

If this does not give you the result you want, try using the **Prog. Change** value instead.

The Remote Control Editor

The **Remote Control Editor** allows you to define your own mapping of VST plug-in parameters to the controls of the supported hardware controllers. This is useful if you think that the automatic mapping of plug-in parameters to remote control devices is not too intuitive.

- To open the **Remote Control Editor**, right-click the plug-in panel of the plug-in that you want to remote-control, and select **Remote Control Editor**.



1 Inspector

Contains the settings and the parameter assignment for the selected cell. The upper section contains settings for the text label. The lower section contains settings for the knob and the switches.

2 Layout Selection

Shows the name of the layout. Click to select a different layout.

3 Set up Cell Layout

Opens the **Cell Layout Configuration**, where you can specify the number of cells per page, and select the switch layout that you want to use for the pages. To specify the number of switches for a cell, activate/deactivate them.

4 Add New Hardware Layout

Adds a new layout for a particular hardware type. To remove a hardware layout, click its **Close** button.

5 Layout Section

Shows layouts that represent the hardware devices that are used to remote-control the plug-in parameters. Here you can change the parameter assignments, the name in the text label, the cell setup, and the order of cells and pages.

6 Toolbar

Shows tools for setting up the layout.

7 Status Bar


Shows information on an element when you position the mouse pointer over it in the editor window.

RELATED LINKS

[Toolbar](#) on page 662

Toolbar

Shows tools for setting up the layout.



- 1 Remove All Assignments**
Removes all parameter assignments.
- 2 Get Default Factory Layout/Copy Layout from Other Tab**
Reverts to the default settings for the current layout or copies the settings of one layout page to another.
- 3 Activate/Deactivate Learn Mode**
Activates/Deactivates the **Learn** mode for the **Remote Control Editor**.
- 4 Activate/Deactivate Assignment Inspection View**
Shows the current assignment of all cells in a layout.
- 5 Apply Current Layout**
Saves the settings. If the hardware supports this function, the changes are immediately reflected on the hardware controllers.

Control Settings


You can define the control style for switches or knobs to which you have assigned a function. This includes changing the LED ring or changing its behavior, from continuous value representation to on/off, for example.

To open the **Control Settings** panel, right-click the control.

NOTE

Not all hardware devices support all control type settings.

Control Type Settings for Knobs



The following control types are available for knobs:

Standard

A standard knob with undefined LED style.

Toggle Switch

A knob with 2 states.

LED Ring

An LED ring around the knob. The setting increases clockwise.

LED Ring (counter-clockwise)

An LED ring around the knob. The setting increases counter-clockwise.

Center Width

An LED ring that starts at the top center position, and when the settings increase, an LED is shown growing in both directions.


Center Neutral

A dial that starts at the top center position and can be moved left or right, like a pan control, for example.

Single Dot

An LED ring around the knob. The setting increases clockwise with a dot indicating the current value.

Control Type Settings for Switches



The following options are available for switches:

Momentary

Activates the assigned function as long as you hold the switch.

Increasing Stepwise

Steps through the available settings until the maximum is reached.

Decreasing Stepwise

Steps through the available settings in reverse order until the minimum is reached.

Increasing Stepwise (cycle)

Steps through the available settings, starting over with the minimum value when the maximum is reached.

Decreasing Stepwise (cycle)

Steps through the available settings in reverse order, starting over with the maximum value when the minimum is reached.

Smart Switch

Switches between 2 states every time you press the switch. Enters **Momentary** mode if you hold the switch.

Invert Control Value

Inverts the control state/value.

Hide Control When Inactive

Hides plug-in parameters when they are inactive or disabled.

Assigning Parameters to Controls

PROCEDURE

1. In the **Remote Control Editor**, click  on the toolbar to activate **Learn** mode for the editor.
 2. Select the control that you want to assign to a plug-in parameter.
 3. Do one of the following:
 - Click a parameter on the plug-in panel.
 - Double-click on a control in the **Remote Control Editor**, and select a parameter from the list of available plug-in parameters.
 4. Press **Esc** to end **Learn** mode.
-

RESULT

The parameter is assigned to the control.

NOTE

To remove the parameter assignment for a cell, activate **Learn** mode, select the cell, and press **Delete** or **Backspace**.

Editing the Layout

In the layout section, you can perform a number of editing operations and arrange the pages to your liking.

- To navigate from cell to cell, use the cursor keys.
- To step through the controls within the cells in **Learn** mode, press **Shift** and use the cursor keys.
- To step through the different layouts, use **Tab** and **Shift-Tab**.
- To copy the settings of one cell to another, select a cell, press **Alt** and drag it to another cell.
- To move a cell, drag it to an empty cell.
- To swap the contents of 2 cells, press **Ctrl/Cmd** and drag one cell to the other.

NOTE

Drag and drop also works between different pages.

- To add a page to a layout, click **Add New Page**.



- To remove a page, click **Remove Current Page**.
- To specify the label for a cell, use the top 3 text fields in the **Inspector**.

The first text field shows the long name, as it is shown in the cell. In the second field, you can enter a name that can contain up to 8 characters, and up to 4 characters in the third.

NOTE

This is useful if your hardware devices have value fields that only display a limited number of characters, for example.

Joysticks

You can use a joystick to remote-control panning operations in Cubase. This can be useful, for example, for creating smooth automation curves.

- To use a joystick for remote-controlling, connect it to your computer and restart Cubase. After restarting the application, the joystick is automatically activated.

RELATED LINKS

[Panning with a Joystick](#) on page 601

[Deactivating Joysticks](#) on page 665

Deactivating Joysticks

If you have a joystick connected to your system, but do not want to use it with Cubase, you can deactivate it.


PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select the joystick device.
The available device settings are shown to the right.
 3. Deactivate the respective option.
-

Apple Remote (macOS only)

Many Apple computers come with an Apple Remote, a small hand-held device that allows you to remotely control specific features in Cubase.

- To open the **Apple Remote Control** settings, select **Studio > Studio Setup**, and from the **Devices** list, select **Apple Remote Control**.



Control list

Lists the Apple Remote controls. Open the pop-up menu to select the Cubase parameter that you want to assign to that control.

Disable when application is not in front

Activate this if you do not want the Apple Remote to control Cubase when it does not have the focus.

By default, the Apple Remote always controls the application that has the focus on your Macintosh computer, provided that this application supports the Apple Remote.

Track Quick Controls

If you have an external remote control device, you can set it up to control up to 8 parameters of each audio track, MIDI track or instrument track, using the **Track Quick Controls** feature in Cubase.

RELATED LINKS

[Connecting Track Quick Controls with Remote Controllers](#) on page 651

VST Quick Controls

If you have an external remote control device, you can control 8 parameters of a VST instrument, using the **VST Quick Controls** feature in Cubase.

RELATED LINKS

[Connecting Track Quick Controls with Remote Controllers](#) on page 651

[VST Quick Controls](#) on page 638

MIDI Realtime Parameters and MIDI Effects

MIDI realtime means that you can change or transform MIDI events on MIDI or instrument tracks before they are sent to the MIDI outputs. This allows you to change the way MIDI data is played back.

The actual MIDI events on the track are not affected. Therefore, MIDI real time changes are not reflected in any MIDI editor.

The following functions allow you to change MIDI events in realtime:

- MIDI track parameters
- MIDI modifiers
- MIDI effects
- Transpose and Velocity on the info line

NOTE

If you want to convert the track settings to real MIDI events, select **MIDI > Freeze MIDI Modifiers** or **MIDI > Merge MIDI in Loop**.

RELATED LINKS

[Merging MIDI Events into a New Part](#) on page 691

MIDI Track Parameters

The MIDI track parameters are located in the topmost Inspector section for MIDI and instrument tracks.

These settings either affect the basic functionality for the track (mute, solo, enable record, etc.) or send out additional MIDI data to the connected devices (program change, volume, etc.).

The following track parameters allow you to change MIDI events in real time:

- MIDI Volume
- MIDI Pan
- Track Delay
- Input Transformer

RELATED LINKS

[MIDI Track Inspector](#) on page 112
[Input Transformer](#) on page 668

Input Transformer

The **Input Transformer** allows you to filter out and change MIDI data coming to a MIDI track before it is recorded.


Use the **Input Transformer** for the following purposes:

- Set up split keyboard combinations for recording left and right hands separately.
- Convert a controller such as a foot pedal into MIDI notes (for playing bass drum the right way).
- Filter out a specific type of MIDI data on one MIDI channel only.
- Turn aftertouch into any controller and vice versa.
- Invert velocity or pitch.

Input Transformer Window

To open the **Input Transformer** window, perform one of the following actions:

- Select a MIDI or instrument track, click **Input Transformer** , and select **Global**. This allows you to make settings that affect all MIDI inputs and all MIDI tracks.
- Select a MIDI or instrument track, click **Input Transformer**, and select **Local**. This allows you to make settings for the selected track only.



The **Input Transformer** window contains the following parameters:

- 1 Select Preset**
Allows you to select a preset for the **Input Transformer**.
- 2 Module selector**
Allows you to view and edit a module.
- 3 Filter conditions list**

Allows you to set up the filter conditions, determining which elements to find. The list can contain one or several conditions, each on a separate line.

4 Action list

Allows you to specify any changes that are made to the found events.

5 Function pop-up menu

Allows you to select between **Filter** and **Transform** as a basic type of editing to be performed.

Specifying Filter Conditions

PROCEDURE

1. Select a MIDI or instrument track.
2. Perform one of the following actions:
 - To make settings that affect all MIDI tracks, open the Inspector, click **Input Transformer**, and select **Global** from the pop-up menu.
 - To make settings that affect the selected MIDI track, open the Inspector, click **Input Transformer**, and select **Local** from the pop-up menu.
3. Open the **Function** pop-up menu, and perform one of the following actions:
 - Select **Filter** if you want to filter the found events.
 - Select **Transform** if you want to transform the found events.
4. Click **+** to add a line to the filter conditions list.
5. In the filter conditions list, specify the conditions to match by clicking the **Filter Target**, **Condition**, and **Parameter** columns and selecting options from the pop-up menu.
6. In the action list, specify how the found events are transformed or filtered by clicking the **Action Target**, **Operation**, and **Parameter** columns, and selecting options from the pop-up menu.

NOTE

You can also select a preset from the **Select Preset** pop-up menu to specify conditions and actions.

RESULT

The settings affect all MIDI events that you record on the track.

AFTER COMPLETING THIS TASK

In the Inspector, click **Input Transformer**, and select **Off**. Otherwise the **Input Transformer** is still active.

MIDI Modifiers

MIDI modifiers allow you to modify MIDI events during playback.

You can use them for the following purposes:

- To modify already existing MIDI events on MIDI or instrument tracks.
- To modify MIDI events that you play live.

NOTE

For live playing, select and record-enable the track, and activate **MIDI Thru Active** in the **Preferences** dialog (**MIDI** page).

MIDI Modifiers Section



NOTE

If you want to compare the result of your modifier settings with the unprocessed MIDI, you can use the bypass button in the MIDI modifiers section. If this button is activated, the MIDI modifiers settings are temporarily disabled.



Transpose

Allows you to transpose all notes on the track in semitones. Extreme transpositions can give rather strange and unwanted results.

Velocity Shift

Allows you to add a velocity value to all notes on the track. Positive values increase the velocity while negative values lower the velocity.

Velocity Compression

Allows you to add a multiplier to the velocity of all notes on the track. The value is set with a numerator and a denominator. This parameter also affects the velocity differences between the notes, thus compressing or expanding the velocity scale.

Values smaller than 1/1 compress the velocity range. Values greater than 1/1 together with negative **Velocity Shift** values expand the velocity range.

IMPORTANT

Remember that the maximum velocity is always 127, no matter how much you try to expand.

NOTE

Combine this setting with the **Velocity Shift** parameter.

Length Compression

Allows you to add a multiplier to the length of all notes on the track. The value is set with a numerator and a denominator.

Random

Allows you to introduce random variations to various properties of MIDI notes.

Range

Allows you to specify a pitch or velocity range and either force all notes to fit within this range, or exclude all notes outside this range from playback.

HMT: Follow

Activate this button to apply Hermode tuning to the notes played on this track.

HMT: Use for Analysis

Activate this option to use the notes you played on this track to calculate retuning.

Setting up Random Variations

You can set up random variations for position, pitch, velocity, and length of MIDI events using one or two random generators.

PROCEDURE

1. Select a MIDI or instrument track.
2. In the Inspector, open the **MIDI Modifiers** section.
3. Open the **Random** pop-up menu and select the note property you want to randomize.
4. Specify the limits of the randomization in the two number fields.
The values will vary between the left value and the right value. You cannot set the left value higher than the right value.
5. Play back the track to hear the randomized events.

RESULT

The corresponding properties are randomized.

NOTE

Depending on the track content, certain changes might not be immediately noticeable or might have no effect at all.

AFTER COMPLETING THIS TASK

Deactivate the random function by opening the **Random** pop-up menu and selecting **OFF**.

Setting up Ranges

You can filter out pitches or velocities that do not match a specified range, or force them to fit a specified range.

PROCEDURE

1. Select a MIDI or instrument track.
2. In the Inspector, open the **MIDI Modifiers** section.
3. Open the **Range** pop-up menu and select a mode.
4. Set the minimum and maximum values with the two fields to the right.

NOTE

You can make independent settings for the two **Range** functions.

AFTER COMPLETING THIS TASK

To deactivate the function, open the **Range** pop-up menu and select **OFF**.

Range Modes

On the **Range** pop-up menu, you can select different range modes. Values are shown as numbers, from 0 to 127, for the velocity modes and as note numbers, from C-2 to G8, for the pitch modes.

Vel. Limit

Allows you to force all velocity values to fit within the range that you specify with the **min** and **max** values. Values below the lower limit are set to the **min** value, velocity values above the higher setting are set to the **max** value.

Vel. Filter

Allows you to filter out notes with velocity values below the **min** value or above the **max** value.

Note Limit

Allows you to transpose all notes below the **min** value upwards and all notes above the **max** value downwards in octave steps.

Note Filter

Allows you to filter out notes that are lower than the **min** value or higher than the **max** value.

Applying Hermode Tuning

Hermode Tuning changes the tuning of notes that you play. It creates clear frequencies for every fifth and third interval, for example. Retuning only affects individual notes and maintains the pitch relationship between keys and notes. The retuning is a continuous process and takes the musical context into account.

PROCEDURE

1. Select a MIDI or instrument track.
2. In the Inspector, open the **MIDI Modifiers** section.
3. Activate **HMT: Follow**.
4. Activate **HMT: Use for Analysis** to use the notes you play to calculate retuning.

NOTE

If you use tracks with acoustic piano, activate **HMT: Use for Analysis** and deactivate **HMT: Follow**. This excludes the piano from being tuned which would sound unnatural.

5. Select **Project > Project Setup** to open the **Project Setup** dialog.
6. Open the **HMT Type** pop-up menu and select one of the options.
7. Play some notes.

It may take a moment until all notes are recalculated and you hear the results of the retuning.

NOTE

Notes that are produced by MIDI plug-ins are not taken into account.

RESULT

If you use a VST 3 instrument that supports Micro Tuning and Note Expression, notes are retuned dynamically while you play them. For VST instruments that support Note Expression, this also works in **MIDI Thru** mode.

If you use a track that has a VST 2 instrument loaded, the notes you play are retuned on every keystroke.


RELATED LINKS

[Hermodé Tuning](#) on page 674

Hermodé Tuning

You can select different Hermodé tuning types.

- To select a Hermodé Tuning type, select **Project > Project Setup** and select an option from the **HMT Type** pop-up menu.



The following options are available:

None

No tuning is applied.

Reference (pure 3/5)

Tunes pure thirds and fifths.

Classic (pure 3/5 equalized)

Tunes pure thirds and fifths. In conflict situations, a slight equalization is applied. This tuning type is suitable for all kinds of music.

Pop Jazz (3/5/7)

Tunes pure thirds and fifths, and natural sevenths. This tuning type should not be applied to polyphonic music. Try this with pop or jazz.

Baroque (3/5 adaptive)

Tunes pure thirds and fifths. The degree of purity changes according to the sequence of harmonies. This tuning type is suitable for church organ and polyphonic music.

Freezing MIDI Modifiers

You can apply all filter settings permanently to the selected track. The settings are applied to the events on the track, and all modifiers are set to zero.

PROCEDURE

1. Select the MIDI track.
 2. Select **MIDI > Freeze MIDI Modifiers**.
-

RESULT

The following settings are frozen:

- Several settings in the top section of the **Inspector**, such as **Delay**, **Program Selector**, and **Bank Selector**.
- The settings in the **MIDI Modifiers** section, such as **Transpose**, **Vel. Shift**, **Vel. Comp.**, and **Len. Comp.**.
- The settings in the **MIDI Inserts** section, such as arpeggiators.
- The info line settings **Transpose** and **Velocity**.

RELATED LINKS

[MIDI Track Inspector](#) on page 112

MIDI Effects

MIDI effects allow you to transform the MIDI data played back from the track in real time.

You can add new events by using MIDI effects, or change MIDI event properties like pitches, for example.

NOTE

The included MIDI effect plug-ins are described in the separate document **Plug-in Reference**.

MIDI Inserts

MIDI insert effects are inserted in the signal chain of MIDI channels. If you add an insert effect to a MIDI track, the MIDI events on the track are sent to the effect and processed by it. The whole signal passes through the effect.

- To add a MIDI insert effect, open the **MIDI Inserts** section of the MIDI track Inspector.



You can add up to four MIDI insert effects. The following parameters are available:

Bypass

Allows you to bypass all insert effects for the track.

Activate Insert

Allows you to activate/deactivate the selected effect.

Open/Close Insert Effect Editor

Allows you to open/close the control panel for the selected effect. Depending on the effect, this may appear in a separate window or below the insert slot in the Inspector.

Select Effect Type

Allows you to select and activate an effect and open its control panel. To remove an effect, select **No Effect**.

Record Output to Track

Allows you to record the output of the MIDI insert effect on a MIDI or instrument track.

NOTE

To open a separate control panel for effects that display their controls in the Inspector, press **Alt** and click **Open/Close Insert Effect Editor**.

Applying a MIDI Insert Effect

You can apply MIDI insert effects to a MIDI track.

PROCEDURE

1. Select the MIDI track.
 2. In the Inspector, open the **MIDI Inserts** section.
 3. Click **Select Effect Type** to open the MIDI effect pop-up menu.
 4. Select a MIDI effect from the pop-up menu.
-

RESULT

The effect is automatically activated and its control panel is opened, allowing you to make settings for the effect. All MIDI from the track is routed through the effect.

NOTE

The included MIDI effects are described in the separate document **Plug-in Reference**.

Recording a MIDI Insert Effect

You can record the output of a MIDI insert effect, that is, the events are created directly on a MIDI or instrument track.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. In the **Add Instrument Track** dialog, select a VST instrument.
3. On the Instrument track, activate **Record Enable**.
4. In the Inspector, open the **MIDI Inserts** section.
5. Click the first insert effect slot and select a MIDI insert effect.
6. Activate **Record Output to Track**.



7. On the **Transport** panel, activate **Record** and use your MIDI keyboard or the **On-Screen Keyboard** to play some notes.
-

RESULT

The notes that you play are modified by the MIDI insert effect and recorded directly on the track.


AFTER COMPLETING THIS TASK

You can edit the recorded MIDI events in the **Key Editor**, for example.

MIDI Sends

If you use a send effect, the MIDI events are sent both to the output of the MIDI track and to the send effect. This way, you get both the unprocessed MIDI events and the output of the MIDI effect. Note that the effect can send its processed MIDI data to any MIDI output, not necessarily to the one used by the track.

- To add a MIDI send effect, open the **MIDI Sends** section of the MIDI track Inspector.



You can add up to four MIDI send effects.

Bypass

Allows you to bypass all send effects for the track.

Activate Send

Allows you to activate/deactivate the selected effect.

Pre/Post

Activate this to send the MIDI signals to the send effects before the MIDI modifiers and insert effects.

Open/Close Send Effect Editor

Allows you to open/close the control panel for the selected effect. Depending on the effect, this may appear in a separate window or below the sends slot in the Inspector.

Select Effect Type

Allows you to select and activate an effect and open its control panel. To remove an effect, select **No Effect**.

MIDI Send Destination

Allows you to determine to which MIDI output the processed MIDI events are sent.

MIDI Send Channel

Allows you to determine on which MIDI channel the processed MIDI events are sent.

NOTE

To open a separate control panel for effects that display their controls in the Inspector, press **Alt** and click **Open/Close Send Effect Editor**.

Presets

Some of the MIDI effects come with a number of presets for instant use.



1 MIDI In/MIDI Out Activity

Indicates if the plug-in receives or transmits MIDI data.

2 Save Preset/Remove Preset

Allows you to save your settings as a preset or to remove saved presets. Saved presets are available in the **Select Preset** pop-up menu for all instances of that MIDI plug-in, and in all projects.

Transpose and Velocity on the Info Line

You can edit the transposition and the velocity for selected MIDI parts on the info line. This only affects the notes on playback.

- Use the **Transpose** field to transpose the selected parts in semitone steps. The value is added to the transposition set for the whole track.
- Use the **Velocity Offset** field to offset the velocity for the selected parts. The value is added to the velocities of the notes in the parts.

RELATED LINKS

[Transpose Functions](#) on page 299

Using MIDI devices

The MIDI Device Manager allows you to specify and set up your MIDI devices, making global control and patch selection easy.

But the MIDI Device Manager also features powerful editing functions that can be used to create MIDI device panels (Cubase Pro only). MIDI device panels are internal representations of external MIDI hardware, complete with graphics. The MIDI device panel editor provides all the tools you need to create device maps where every parameter of an external device (and even an internal device like a VST instrument) can be controlled and automated from inside Cubase.

For additional information on how to create panels for VST instruments, see the separate document **MIDI Devices**.

RELATED LINKS

[About Device panels \(Cubase Pro only\)](#) on page 687


MIDI devices – general settings and patch handling

On the following pages, we will describe how to install and set up preset MIDI devices, and how to select patches by name from within Cubase. For a description on how to create a MIDI device from scratch, please see the separate PDF document **MIDI Devices**.

About Program Change and Bank Select

To instruct a MIDI instrument to select a certain patch (sound), you send a MIDI Program Change message to the instrument. Program Change messages can be recorded or entered in a MIDI part like other events, but you can also enter a value in the Program Selector field in the Inspector for a MIDI track. This way, you can quickly set each MIDI track to play a different sound.

With Program Change messages, you are able to select between 128 different patches in your MIDI device. However, many MIDI instruments contain a larger number of patch locations. To make these available from within Cubase, you need to use Bank Select messages, a system in which the programs in a MIDI instrument are divided into banks, each bank containing 128 programs. If your instruments support MIDI Bank Select, you can use the Bank Selector field in the Inspector to select a bank, and then the Program Selector field to select a program in this bank.




Unfortunately, different instrument manufacturers use different schemes for how Bank Select messages are constructed, which can lead to some confusion and make it hard to select the

correct sound. Also, selecting patches by numbers this way seems unnecessarily cumbersome, when most instruments use names for their patches nowadays.

To help with this, you can use the MIDI Device Manager to specify which MIDI instruments you have connected by selecting from a vast list of existing devices or by specifying the details yourself. Once you have specified which MIDI devices you are using, you can select to which particular device each MIDI track is routed. It is then possible to select patches by name in the track list or Inspector.


Opening the MIDI Device Manager

Select MIDI Device Manager from the More Options submenu of the Studio menu to bring up the following window:



MIDI Device Manager dialog in Cubase Pro.

The MIDI Device Manager dialog in Cubase Artist:



Installed Devices

List of connected MIDI devices. The first time you open the MIDI Device Manager, this list will be empty.

Install Device/Remove Device

Use these buttons to install/remove devices.

Export Setup/Import Setup

Use these buttons to import/export XML Device setups.

Open Device (Cubase Pro only)

This button opens the selected device.

Output

Here you specify to which MIDI output the selected device is connected.

Commands (Cubase Artist only)

This pop-up menu lets you edit the selected device (provided that “Enable Edit” is ticked). The patch structure for the selected device is shown on the left side of the dialog.

MIDI Messages (Cubase Artist only)

This area on the right side of the dialog shows exactly which MIDI messages are sent out to select the patch highlighted in the list to the left.

When you open the MIDI Device Manager for the first time, it will be empty (because you have not installed any devices yet). On the following pages we describe how to add a pre-configured MIDI device to the list, how to edit the settings and how to define a device from scratch.

Note that there is an important difference between installing a preset MIDI device (“Install Device”) and importing a MIDI device setup (“Import Setup”):

- The presets do not include any device mapping of parameters and controls and no graphic panels.
They are simply patch name scripts. When you install a preset MIDI device, it is added to the Installed Devices list. For more information about patch name scripts, see the separate document **MIDI Devices**.
- A device setup can include device mapping, panels and/or patch information.
Device setups are also added to the list of installed devices when imported.

RELATED LINKS

[About Device panels \(Cubase Pro only\)](#) on page 687

Defining a new MIDI device (Cubase Pro only)

If your MIDI device is not included in the list of pre-configured devices (and is not a “plain” GM or XG device), you need to define it manually to make it possible to select patches by name. This is handled slightly differently for Cubase Pro and Cubase Artist.

PROCEDURE

1. In the MIDI Device Manager, click the Install Device button.
The Add MIDI Device dialog opens.
 2. Select “Define New...” and click OK.
The “Create New MIDI Device” dialog opens. For a description of the options in this dialog, see the separate document **MIDI Devices**.
 3. In the Identical Channels list, activate the MIDI channels you would like the device to use.
This means that the device will receive Program Change over any MIDI channel. For a description of Identical and Individual Channels, see the separate document **MIDI Devices**.
 4. Enter a name for the device at the top of the dialog, and click OK.
The device appears in the Installed Devices list, and the device node structure for the device is automatically shown in a new window.
 5. Select Patch Banks from the pop-up menu at the top of the window.
As you can see, the list is empty.
 6. Make sure that the Enable Edit checkbox is activated.
Now you can use the functions on the Commands pop-up menu on the left to organize the patch structure of the new device.
-

Defining a new MIDI device (Cubase Artist only)

If your MIDI device is not included in the list of pre-configured devices (and is not a “plain” GM or XG device), you need to define it manually to make it possible to select patches by name.


PROCEDURE

1. In the MIDI Device Manager, click the Install Device button.
The Add MIDI Device dialog opens.
 2. Select “Define New...” and click OK.
A dialog appears.
 3. Enter the name of the device and the MIDI channels you would like the device to use and click OK.
The device appears in the Installed Devices list.
 4. Select the device in the list.
As you can see, it contains only an Empty Bank item.
 5. Make sure that the Enable Edit checkbox is activated.
Now you can use the functions on the Commands pop-up menu on the left to organize the patch structure of the new device.
-

Installing a preset MIDI device


PROCEDURE

1. Click the Install Device button.
A dialog opens listing all pre-configured MIDI devices. For now we assume that your MIDI device is included in this list.
2. Locate and select the device in the list and click OK.
If your MIDI device is not included in the list but is compatible with the GM (General MIDI) or XG standards, you can select the generic GM or XG Device options at the top of the list.
When you select one of these options, a name dialog will appear. Enter a name for the instrument and click OK.
The device now appears in the Installed Devices list to the left.
3. Make sure that the new device is selected in the list and open the Output pop-up menu.
4. Select the MIDI output that the device is connected to.
5. If you are using Cubase, click the Open Device button.
A separate window opens for the selected device, showing a node structure in the left half of the window. At the top of this structure is the device itself, and below it the MIDI channels used by the device. For more information about the Device window, see the separate PDF document **MIDI Devices**.
6. Select Patch Banks from the pop-up menu at the top of the window.



RESULT

The Patch Banks list in the left half of the window shows the patch structure of the device. This could simply be a list of patches, but it is usually one or several layers of banks or groups containing the patches (much like a folder structure on a hard disk for example).



- You can rename a device in the Installed Devices list by double-clicking and typing – this is useful if you have several devices of the same model, and want to separate them by name instead of by number.
- To remove a device from the Installed Devices list, select it and click Remove Device.


NOTE

Note that if there already exists a panel for the device (Cubase Pro only), opening the device might open this panel first. In this case, click on the Edit button to open the Device window.


About Patch Banks

Depending on the selected device, you may find that the Patch Banks list is divided in two or more main banks. Typically, these are called Patches, Performances, Drums, etc. The reason for having several patch banks is that different “types” of patches are handled differently in the instruments. For example, while “patches” typically are “regular” programs that you play one at the time, “performances” may be combinations of programs, which could be split across the keyboard, layered, or used for multi-timbral playback, and so on.

Cubase Pro only: For devices with several banks, you will find an additional item labeled “Bank Assignment” in the pop-up menu at the top of the window. Selecting this opens a window in which you can specify for each MIDI channel which bank it should use.



Cubase Artist only: Devices with several banks have an additional tab “Bank Assignment”. Select this tab to specify for each MIDI channel which bank it should use.



The selection here will affect which bank is displayed when you select programs by name for the device in the track list or Inspector. For example, many instruments use MIDI channel 10 as an exclusive drum channel, in which case you would want to select the “Drums” (or “Rhythm Set”, “Percussion”, etc.) bank for channel 10 in this list. This would then let you choose between different drum kits in the track list or Inspector.

Limitations

There is no easy way to import a patch name script into an existing MIDI device. For a complex workaround based on XML editing, see the separate document **MIDI Devices**.

Selecting a patch for an installed device


If you return to the Project window at this point, you will find that the installed device has been added to the MIDI Output menus (in the track list and the Inspector). Now you can select patches by name, in the following way:

PROCEDURE

1. Open the Output menu (in the track list or Inspector) for the track you want to associate the installed device with, and select the device.
This directs the track to the MIDI output specified for the device in the MIDI Device Manager. The Bank and Program Selector fields in the track list and Inspector are replaced by a single Program Selector field that reads “Off”.

2. Click the Program Selector field to display a pop-up menu, hierarchically listing all the patches in the device.

The list is similar to the one displayed in the MIDI Device Manager. You can scroll the list up and down (if required), click the plus/minus signs to show or hide subgroups, etc.



You can also use a filter function here. For this, enter a search term such as **drum** in the Filter field, and press **Return** to display all sounds with **drum** in the name.

3. Click a patch in the list to select it.
This sends the appropriate MIDI message to the device. You can also scroll the program selection up or down, as with any value.
-

Renaming patches in a device

The pre-configured devices list is based on the factory-preset patches, that is, the patches included in the device when you first bought it. If you have replaced some of the factory presets with your own patches, you need to modify the device so that the patch name list matches the actual device:

PROCEDURE

1. In the MIDI Device Manager, select the device in the Installed Devices list.
2. If you are using Cubase, click Open Device.
Make sure that Patch Banks is selected on the pop-up menu at the top of the window.
3. Activate the Enable Edit checkbox.
When this is turned off (default), you cannot edit the pre-configured devices.
4. In the Patch Banks list, locate and select the patch you want to rename.
In many instruments, the user-editable patches are located in a separate group or bank.
5. Click on the selected patch in the Patch Banks list to edit its name.
6. Type in the new name and press **Return**.
7. Rename the desired patches in this way, and finish by deactivating Enable Edit again (to avoid modifying the device by accident).

NOTE

You can also make more radical changes to the patch structure in a device (adding or deleting patches, groups or banks). For example, this is useful if you expand your MIDI device by adding extra storage media such as RAM cards.

Patch Structure

Patches are structured as follows:

- Banks are the main categories of sounds – typically patches, performances and drums.
- Each bank can contain any number of groups, represented by folders in the list.
- The individual patches, performances or drum kits are represented by presets in the list.

The Commands pop-up menu contains the following items:

Create Bank

Creates a new bank at the highest hierarchical level of the Patch Banks list. You can rename this by clicking on it and typing a new name.

New Folder

Creates a new subfolder in the selected bank or folder. This could correspond to a group of patches in the MIDI device, or just be a way for you to categorize sounds, etc. When you select this item, a name dialog opens, allowing you to name the folder. You can also rename the folder afterwards by clicking it and typing in the list.

New Preset

This adds a new preset in the selected bank or folder.

When the preset is selected, the corresponding MIDI events (Program Change, Bank Select, etc.) are shown in the event display to the right. The default setting for a new preset is Program Change 0 – to change this, proceed as follows:

IMPORTANT

For details on which MIDI events are used for selecting patches in the MIDI device, consult its documentation.

- To change which Program Change value is sent out to select the patch, adjust the number in the Value column for the Program Change event.
- To add another MIDI event such as Bank Select click directly below the last event in the list and select a new event from the pop-up menu.
After adding a new event, you need to set its value in the Value column, as with Program Change.
- To replace an event, click on it and select another event from the pop-up menu.
For example, a MIDI device may require that a Bank Select message is sent first, followed by a Program Change message, in which case you would need to replace the default Program Change message with a Bank Select message and add a new Program Change after that.
- To remove an event, select it and press **Delete** or **Backspace**.

IMPORTANT

Different devices use different schemes for Bank Select. When you insert a Bank Select event, you should check the device's documentation to find out whether to

choose “CC: BankSelect MSB”, “Bank Select 14 Bit”, “Bank Select 14 Bit MSB-LSB Swapped” or some other option.

Add Multiple Presets

This opens a dialog, allowing you to set up a range of presets to be added to the selected bank or folder.

Adding Multiple Presets

PROCEDURE

1. Add the event types required for selecting a patch in the MIDI device.
This is done just as when editing the settings for a single event: clicking in the event display brings up a pop-up menu from which you can select an event type.
2. Use the Range column to set up either a fixed value or a range of values for each event type in the list.

This requires some explanation:

If you specify a single value such as 3, 15 or 127 in the Range column, all added presets will have an event of this type set to the same value.

If you instead specify a value range (a start value and an end value, separated by a dash such as 0–63), the first added preset will have an event set to the start value, the next value will be incrementally raised by one and so on, up to and including the end value.

MIDI Message Name	MIDI Message Bytes	Valid Range	Range
CC: Gen Purp 4	B0 13 0	0 - 127	0-127
Program Change	C0 0	0 - 127	7

NOTE

The number of added presets depends on the Range setting.

3. Specify a Default Name below the event display.
The added events will get this name, followed by a number. You can rename presets manually in the Patch Banks list later.
 4. Click OK.
A number of new presets have now been added to the selected bank or folder, according to your settings.
-

Other editing functions

- You can move presets between banks and folders by dragging them to the Patch Banks list.
- You can remove a bank, folder or preset by selecting it in the Patch Banks list and pressing **Backspace**.
- Cubase Pro only: If you specify more than one bank, a Bank Assignment item is added to the pop-up menu at the top of the window. Use this to assign banks to the different MIDI channels.
- Cubase Artist only: If you specify more than one bank, a Bank Assignment tab is added next to the Patch Banks tab.

RELATED LINKS

[About Patch Banks](#) on page 683

About Device panels (Cubase Pro only)

On the following pages we will describe how to use MIDI Device panels and the powerful MIDI device panel editing features of the MIDI Device Manager.

NOTE

We recommend that you first configure the patch banks, then export the device setup before editing the panels. This way, most of your settings will be saved in case of panel configuration problems.

The panels are saved in XML format. For more information, see the separate document **MIDI Devices**.

Basic concept

The panel editing features in the MIDI Device Manager can be seen as a separate application or entity within Cubase. It allows you to build device maps complete with control panels, including all parameters controllable from within Cubase.

Building more complex device maps requires that you are familiar with SysEx programming (see the separate document **MIDI Devices**). But you can also create simpler panels by assigning MIDI Control Change messages to control objects, which does not require any programming skills. Although these powerful editing features are there if you need them, you do not have to use them to use MIDI devices.

Device panels in the program

In this section we will take a look at a pre-configured MIDI device panel to illustrate how it can be used in Cubase.


Opening a device setup

PROCEDURE

1. Select **Studio > More Options > MIDI Device Manager**.
 2. Click the "Import Setup" button.
A file dialog opens.
 3. Select a setup file.
The setup files are saved in XML format, for more information see the separate document **MIDI Devices**.
 4. Click Open. The Import MIDI Devices dialog opens where you can select one or several devices for import.
A setup file can contain one or several MIDI devices.
 5. Select a device and click OK.
The device is added to the list of installed devices in the MIDI Device Manager.
 6. Select the correct MIDI output from the Output pop-up menu, select the device in the list and click the Open Device button.
The device panel opens in a separate window. The Edit button at the top opens the Edit Panel window, see the separate document **MIDI Devices**.
 7. Close the Device panel and return to the Project window.
 8. Select the device from the "Output Routing" pop-up menu for a MIDI track.
Note that for some devices, you may have to set the MIDI channel to "Any".
-

RESULT

Now the Device panel can be opened by clicking the Open Device Panels button in the Inspector or in the channel for the corresponding track in the MixConsole.




NOTE

Note that **Ctrl/Cmd**-clicking the Open Device Panels button allows you to open a subpanel via the panel browser pop-up menu.

Showing panels in the Inspector

PROCEDURE

1. In the Inspector, open the Device Panel section and click on the arrow on the right.
A "Panels" folder is shown with the selected device in a node structure below it. If you open all the folders, you can select any individual panel from the device that "fits" into the Device Panel space.



2. Select a panel from the list.
The panel opens in the Inspector.



NOTE

If you cannot see any panels in the "Panels" folder, although you have successfully set up a MIDI device with several panels, make sure that you selected the correct channel from the Channel pop-up menu, preferably "Any" to see all device panels. Also make sure that the panels fit into the space, otherwise they will not be available in the "Panels" folder.

Showing panels in the MixConsole

PROCEDURE

1. Open the MixConsole and click Racks to open the rack selector and activate the Device Panels rack.
2. Click the Panel header to expand the Device Panels rack.
3. Click the button at the right of the header.

The Panels folder is displayed like in the Inspector, but with different available panels. Just like in the Inspector, the panel has to “fit” into the available space to be selectable.

4. Select a panel.

The panel is shown in the Channel Racks section of the MixConsole.

Automating device parameters

Automation works just like for normal audio and MIDI tracks:

PROCEDURE

1. Open the device panel by clicking the Open Device Panels button in the Inspector.
2. Activate Write automation on the device panel.


You can automate the device by either moving knobs and sliders on the device panel or by drawing curves on the automation track for a selected parameter.



3. If you now go back to the Project window, there will be a MIDI Device Automation track in the track list.

If the track is hidden, select “Show All Used Automation” on the Track Folding submenu of the Project menu.

If you click in the name field, all parameters in the device are shown and can be selected for automation.



- To open another automation track for the next parameter on the pop-up menu, click the + button (“Append automation track”) at the bottom left of the automation track.

NOTE

If you wrote automation but your MIDI device is not yet connected, the panel will not display any parameter changes when playing back the track with the Read button activated.

MIDI Functions

MIDI functions allow you to permanently edit MIDI events or MIDI parts in the **Project** window or from within a MIDI editor.

Which events are affected when you use a MIDI function depends on the function, the active window and the current selection:

- In the **Project** window, the MIDI functions apply to all selected parts, affecting all events of the relevant types in them.
- In the MIDI editors, MIDI functions apply to all selected events. If no events are selected, all events in the edited parts are affected.

NOTE

Some MIDI functions only apply to MIDI events of a certain type. For example, **Delete Controllers** only applies to MIDI controller events.


RELATED LINKS

[MIDI Realtime Parameters and MIDI Effects](#) on page 668

Transpose Setup

The **Transpose Setup** dialog contains settings for transposing the selected events.

- Select the MIDI notes that you want to transpose and select **MIDI > Transpose Setup** to open the **Transpose Setup** dialog.



The following settings are available:

Semitones

Sets the amount of transposition.

Scale Correction

Transposes the selected notes to the closest note of a specific scale type. This allows you to change the key and the tonality.

- Select a root note and a scale type for the current scale in the **Current Scale** pop-up menus.

- Select a root note and a scale type for the new scale in the **New Scale** pop-up menus.

NOTE

If the new root note differs from the current root note, this leads to an entirely different key.

Use Range

Limits the transposition of notes to the note values that you specify with the **Low** and **High** settings.

NOTE

Notes that would end up outside the range after transposition, are shifted to another octave, keeping the correct transposed pitch if possible. If the range between the upper and lower limit is very narrow, the note is transposed as far as possible, that is, to notes specified with the **Low** and **High** values. If you set **Low** and **High** to the same value, all notes will be transposed to this pitch.

NOTE

You can also use the transpose track for transposing.

RELATED LINKS

[Transpose Functions](#) on page 299

Merging MIDI Events into a New Part

You can merge all MIDI events, apply MIDI modifiers and effects and generate a new part.

PROCEDURE

1. Do one of the following:
 - Mute the tracks or parts that you do not want to include in the merge.
 - Solo the track that contains the events that you want to include in the merge.
2. Set up the left and right locators to encompass the area that you want to merge.

NOTE

Only events starting within this area will be included.

3. Optional: Select a track for the new part.
If you do not select a track, a new MIDI track is created. If several MIDI tracks are selected, the new part is inserted on the first selected track.
 4. Select **MIDI > Merge MIDI in Loop....**
 5. In the **MIDI Merge Options** dialog, activate the desired options.
 6. Click **OK**.
-

RESULT

A new part is created between the locators on the destination track, containing the processed MIDI events.

RELATED LINKS

[MIDI Merge Options Dialog](#) on page 692

[Freezing MIDI Modifiers](#) on page 674

MIDI Merge Options Dialog

The following options are available:

Include Inserts

Applies MIDI insert effects and MIDI modifiers.

Include Sends

Applies MIDI send effects.

Erase Destination

Deletes MIDI data between the left and right locators on the destination track.

Include Chase

Includes events placed outside the selected part but relating to it in the processing, for example, a program change right before the left locator.

Convert VST 3

Converts all VST 3 data within the selected area to MIDI data.

RELATED LINKS

[Chase](#) on page 232

Applying Effects to a Single Part

You can apply MIDI modifiers and effects to a single part.

PROCEDURE

1. Set up your MIDI modifiers and MIDI effects the way you want them for the part.
 2. Set the locators to encompass the part.
 3. In the track list, select the track with the part.
 4. Select **MIDI > Merge MIDI in Loop...**
 5. In the **MIDI Merge Options** dialog, activate **Erase Destination**.
 6. Click **OK**.
-

RESULT

A new part is created on the same track, containing the processed events. The original part is deleted.

AFTER COMPLETING THIS TASK

Turn off or reset all MIDI modifiers and effects, so that the track plays back as before.

Dissolve Part

You can separate MIDI events in a part according to channels or pitches and dissolve the part to different tracks or lanes.

- Select the MIDI part you want to dissolve and select **MIDI > Dissolve Part** to open the **Dissolve Part** dialog.

The following settings are available:

Separate Channels

Separates MIDI events according to their channel. This is useful for MIDI parts on MIDI channel **Any** that contain events on different MIDI channels.

Separate Pitches

Separates MIDI events according to their pitch. This is useful for drum and percussion tracks, where different pitches usually correspond to separate drum sounds.

Optimized Display

Automatically removes silent areas of the resulting parts.

NOTE

This option is not available when **Dissolve to Lanes** is activated.

Dissolve to Lanes

Dissolves the part to lanes.

Dissolving Parts into Separate Channels

You can dissolve MIDI parts that contain events on different MIDI channels and distribute the events into new parts on new tracks, one for each MIDI channel found.

PROCEDURE

1. Select the parts that contain MIDI events on different channels.
 2. Select **MIDI > Dissolve Part**.
 3. Activate **Separate Channels**.
 4. Click **OK**.
-

RESULT

For each MIDI channel used in the selected parts, a new MIDI track is created and set to the corresponding MIDI channel. Each event is copied into the part on the track with the corresponding MIDI channel, and the original parts are muted.

MIDI Channel Setting

Setting a track to MIDI channel **Any** causes each MIDI event to play back on its original MIDI channel, rather than a channel set for the whole track.

There are two main situations when **Any** channel tracks are useful:

- When you record several MIDI channels at the same time.
You may for example have a MIDI keyboard with several keyboard zones, where each zone sends MIDI on a separate channel. Setting the channel to **Any** allows you to play back the recording with different sounds for each zone (since the different MIDI notes play back on separate MIDI channels).
- When you have imported a MIDI file of Type 0.
MIDI files of Type 0 contain only one track, with notes on up to 16 different MIDI channels. If you were to set this track to a specific MIDI channel, all notes in the MIDI file would be played back with the same sound; setting the track to **Any** will cause the imported file to play back as intended.

Dissolving Parts into Separate Pitches

You can dissolve MIDI parts that contain events of different pitches and distribute the events into new parts on new tracks, one for each MIDI pitch found. This is useful when the different pitches are used for separating different sounds such as MIDI drum tracks or sampler sound FX tracks. By dissolving such parts, you can work with each sound individually, on a separate track.

PROCEDURE

1. Select the parts that contain MIDI events of different pitches.
 2. Select **MIDI > Dissolve Part**.
 3. Activate **Separate Pitches**.
 4. Click **OK**.
-

RESULT

For each MIDI pitch used in the selected parts, a new MIDI track is created. Each event is copied into the part on the track for the corresponding pitch, and the original parts are muted.

Dissolve to Lanes

You can dissolve MIDI parts that contain events on different MIDI channels or pitches and distribute the events into new parts on new lanes of the original track.

Dissolving to lanes has the following advantages:

- You get a better overview of what MIDI material belongs together.
- It allows you to split up a part into different drum sounds and edit these independently.
- It allows you to split up instrument parts and still route them to the same VST instrument instance.

NOTE

To reassemble all events into one part, use **Bounce MIDI**.

RELATED LINKS

[Bouncing MIDI Parts](#) on page 694

Bouncing MIDI Parts

You can combine MIDI parts on different lanes to one MIDI part. This is useful, if you want to reassemble a drum part that you dissolved to lanes.

PROCEDURE

1. Select the MIDI parts on the different lanes that you want to combine.
 2. Select **MIDI > Bounce MIDI**.
-

RESULT

The selected MIDI parts are combined to one part. Any muted parts are removed. Transpose and velocity values that are set for the parts are taken into account.

Repeating MIDI Events of Independent Track Loops

You can repeat the MIDI events inside an independent track loop to fill up a MIDI part. This is useful, if you want to convert the events of an independent track loop to actual MIDI events.

PREREQUISITE

You have set up an independent track loop and the **Key Editor** is open. The part ends after the end of the independent track loop.

PROCEDURE

- Select **MIDI > Repeat Loop**.

RESULT

The events of the independent track loop are repeated to the end of the part. Events that are located to the right of the independent track loop in the part are replaced.

RELATED LINKS

[Setting Up the Independent Track Loop](#) on page 511

Extending MIDI Notes

You can extend MIDI notes so that they reach the next notes.

PREREQUISITE


A MIDI part with some note events is open in the **Key Editor**.

PROCEDURE

1. Select the note events that you want to extend to the next notes.
2. Select **MIDI > Functions > Legato**.

RESULT

The selected note events are extended to the start of the next notes.



NOTE

To specify a gap or overlap for this, adjust the **Legato Overlap** setting in the **Preferences** dialog (**Editing—MIDI** page).

RELATED LINKS

[Key Editor Inspector](#) on page 717

Fixing MIDI Note Lengths


You can set the length of selected MIDI notes to the **Length Quantize** value.

PREREQUISITE

A MIDI part with some note events is open in the **Key Editor**.

PROCEDURE

1. In the **Key Editor** toolbar, open the **Length Quantize** pop-up menu and select the desired note length.



2. Select the note events that you want to fix.
 3. Select **MIDI > Functions > Fixed Lengths**.
-

RESULT

The selected note events are set to the specified **Length Quantize** value.

Fixing MIDI Note Velocities

You can set the velocity of selected MIDI notes to the **Insert Velocity** value.

PREREQUISITE

A MIDI part with some note events is open in the **Key Editor**.

PROCEDURE

1. In the **Key Editor** toolbar, open the **Insert Velocity** pop-up menu and select the desired velocity value.



2. Select the note events that you want to fix.
 3. Select **MIDI > Functions > Fixed Velocity**.
-

RESULT

The selected note events are set to the specified **Insert Velocity** value.

Rendering Sustain Pedal Data to Note Lengths

You can render sustain pedal data to into note lengths. This is useful, if you recorded MIDI data with a MIDI keyboard and a sustain pedal, and you want to extend the actual MIDI notes for as long as you held the pedal, in order to edit the notes later.

PREREQUISITE

You recorded MIDI using a MIDI keyboard and a sustain pedal. The MIDI part is open in the **Key Editor**.

PROCEDURE

1. Select the note events.

2. Select **MIDI > Functions > Pedals to Note Length**.
-

RESULT

The selected notes are lengthened to match the sustain pedal off position, and the sustain controller on/off events are removed.

Deleting Overlaps

You can delete overlaps of notes that have the same or different pitches. This is useful, if your MIDI instruments cannot handle overlapping events.

PROCEDURE

1. Select the note events.
 2. Do one of the following:
 - Select **MIDI > Functions > Delete Overlaps (mono)**.
 - Select **MIDI > Functions > Delete Overlaps (poly)**.
-

RESULT

The overlapping MIDI notes are shortened, so that no note begins before another ends.

Editing Velocity

You can manipulate the velocity of notes.

PROCEDURE

1. Select the note events.
 2. Select **MIDI > Functions > Velocity**.
 3. Open the **Type** pop-up menu and activate the desired option.
 4. Optional: Enter a **Ratio**.
 5. Click **OK**.
-


RESULT

The note velocities are changed according to your settings.

RELATED LINKS

[Velocity](#) on page 697

Velocity



Add/Subtract

Adds the **Amount** value to the velocity value. You can enter positive or negative values.

Compress/Expand

Uses the **Ratio** setting (0 to 300 %) to compress or expand the dynamic range of MIDI notes. A factor higher than 1 (over 100 %) expands the differences between velocity values, while using a factor lower than 1 (under 100 %) compresses them.

- To compress the dynamic range, use ratio values below 100 %.
After compression, you can add a velocity amount to maintain the average velocity level.
- To expand the dynamic range, use ratio values above 100 %.
Before expansion, you may can adjust the velocity to a middle of the range.

Limit

Limits the velocity values so that they stay between the **Lower** and the **Upper** values.

Deleting Double Notes

You can delete double notes of the same pitch on the exact same position from selected MIDI parts. Double notes can occur when recording in cycle mode, after quantizing, for example.

PROCEDURE

1. Select the MIDI part that contains the double notes.
 2. Select **MIDI > Functions > Delete Doubles**.
-

RESULT

The double notes are automatically deleted.

Deleting Controller Data

You can delete controller data from selected MIDI parts.

PROCEDURE

1. Select the MIDI parts that contain the controller data.
 2. Select **MIDI > Functions > Delete Controllers**.
-

RESULT

The controller data is automatically deleted.

Deleting Continuous Controller Data

You can delete continuous controller data from selected MIDI parts.

PROCEDURE

1. Select the MIDI parts that contain the controller data.
 2. Select **MIDI > Functions > Delete Continuous Controllers**.
-

RESULT

The continuous controller data is automatically deleted. However, On/Off events such as sustain pedal events are kept.

Restricting Polyphonic Voices

You can restrict polyphonic voices in selected MIDI notes or parts. This is useful when you have an instrument with limited polyphony and want to make sure all notes are played.

PROCEDURE

1. Select the MIDI notes or parts that contain the voices.
 2. Select **MIDI > Functions > Restrict Polyphony**.
 3. Specify how many voices you want to use.
 4. Click **OK**.
-

RESULT

The notes are shortened as required, so that they end before the next note starts.

Thinning Out Controller Data

You can thin out controller data in selected MIDI parts. Use this to ease the load on your external MIDI devices if you have recorded very dense controller curves, etc.

PROCEDURE

1. Select the MIDI parts that contain the controllers that you want to thin out.
 2. Select **MIDI > Functions > Thin Out Data**.
-

RESULT

The controller data is thinned out.

NOTE

Cubase Pro only: This also thins out MIDI controller and VST 3 events that form part of Note Expression data.

Extracting MIDI Automation

You can convert continuous controllers of your recorded MIDI parts into MIDI track automation data, so that you can edit them in the **Project** window.

PROCEDURE

1. Select the MIDI part that contains the continuous controller data.
 2. Select **MIDI > Functions > Extract MIDI Automation**.
-

RESULT

In the **Project** window, for each of the continuous controllers in the MIDI part an automation track is created.

In the MIDI editors, the controller data is removed from the controller lane.

NOTE

This only works for continuous controllers. Data such as Aftertouch, Pitchbend, or SysEx cannot be converted to MIDI track automation data.

MIDI controller automation is also affected by the Automation Merge Mode.

RELATED LINKS

[MIDI Controller Automation](#) on page 625

[Creating a Tempo Track from Tapping \(Cubase Pro only\)](#) on page 700

Reversing the Playback Order of MIDI Events

You can invert the order of the selected events or of all events in a selected parts rhythmically. This causes the MIDI to play backwards. However, this is different from reversing an audio recording. The individual MIDI notes still play as usual, but the playback order changes.

PROCEDURE

1. Select the MIDI events or the MIDI part.
2. Select **MIDI > Functions > Reverse**.

RESULT

The playback order of the events is reversed while the individual notes still play as usual in the MIDI instrument. Technically, this function reverses the Note On message of a note within a part or selection.

Inverting the Order of Selected MIDI Events

This function inverts the order of the selected events (or of all events in the selected parts) graphically. Technically, this function turns a Note On message into a Note Off message and vice versa which can lead to rhythmic inaccuracies if the Note Off position of a note has not been quantized.

PROCEDURE

1. Select the MIDI events or the MIDI part.
2. Select **MIDI > Functions > Mirror**.

RESULT

The order of the events is inverted while the individual notes still play as usual in the MIDI instrument. Technically, this function turns a Note On message into a Note Off message and vice versa which can lead to rhythmic inaccuracies if the Note Off position of a note has not been quantized.

Creating a Tempo Track from Tapping (Cubase Pro only)

You can create a complete tempo track based on your tapping.

PREREQUISITE

You recorded some MIDI notes by tapping the tempo on your MIDI keyboard.

PROCEDURE

1. Select the recorded MIDI events or the whole part.
2. Select **MIDI > Functions > Merge Tempo from Tapping**.

RESULT

The tempo that you tapped is calculated, and a tempo curve is created in the **Tempo Track Editor**.

RELATED LINKS

[Tempo Track Editor](#) on page 893

MIDI Editors

There are several ways to edit MIDI in Cubase. You can use the tools and functions in the **Project** window for large-scale editing or the functions on the **MIDI** menu to process MIDI parts in various ways. To manually edit your MIDI data on a graphical interface, you can use the MIDI editors.

- The **Key Editor** presents notes graphically in a piano roll-style grid. The **Key Editor** also allows for detailed editing of non-note events such as MIDI controllers.
- The **Score Editor** shows MIDI notes as a musical score and provides advanced tools and functions for notation, layout, and printing.
Cubase Artist features a basic version of the **Score Editor**.
- The **Drum Editor** is similar to the **Key Editor**, but each key corresponds to a separate drum sound.
You can use the **Drum Editor** to edit drum or percussion parts.
- The **List Editor** shows all events in the selected MIDI parts as a list and allows you to view and edit their properties numerically. It also allows you to edit SysEx messages.
- The **In-Place Editor** allows you to edit MIDI parts directly in the **Project** window so that you can edit MIDI in context with other track types.
Cubase Pro only: You can also edit MIDI in the Project Browser.

RELATED LINKS

[Key Editor](#) on page 709

[Drum Editor](#) on page 750

[List Editor](#) on page 771

[Basic Score Editor \(Cubase Artist only\)](#) on page 737

[Project Browser \(Cubase Pro only\)](#) on page 911

[In-Place Editor](#) on page 785

Common MIDI Editor Functions

You can use the tools and functions within the MIDI editors to process MIDI parts in various ways.

Changing the Display Format for the Ruler

By default, the ruler shows the timeline in the display format that is selected on the transport panel.

You can change the display format for the ruler. Click the arrow button to the right of the ruler and select an option from the pop-up menu.

RELATED LINKS

[Ruler Display Formats](#) on page 47

Zooming in MIDI Editors

The MIDI editors provide several zooming options:

- The zoom sliders.



- The **Zoom** tool.



- The **Zoom** submenu in the **Edit** menu.


When you use the **Zoom** tool for zooming, you can determine if you want to zoom horizontal only or horizontal and vertical at a time.

- To activate/deactivate the corresponding option, activate/deactivate **Zoom Tool Standard Mode: Horizontal Zooming Only** in the **Preferences** dialog (**Editing—Tools** page).

Using Cut and Paste

You can use the **Cut**, **Copy**, and **Paste** options from the **Edit** menu to move or copy material within a part or between different parts.

- To insert note events at the project cursor position without affecting existing notes, select **Edit > Paste**.
- To insert note events at the project cursor position, move, and if necessary split the existing note events to make room for the pasted notes, select **Edit > Range > Paste Time**.



- 1 Data on clipboard
- 2 Cursor position
- 3 Pasted data at cursor position

Handling Note Events

Coloring Notes and Events

You can select different color schemes for the note events in the MIDI editor.

The following options are available on the **Event Colors** pop-up menu on the toolbar:

Velocity

The note events get different colors depending on their velocity values.

Pitch

The note events get different colors depending on their pitch.

Channel

The note events get different colors depending on their MIDI channel value.

Part

The note events get the same color as their corresponding part in the **Project** window. Use this option if you are working with 2 or more tracks in an editor, to see which note events belong to which track.

Grid Match

The note events get different colors depending on their time position. For example, this mode enables you to see if the notes of a chord start at the exact same beat.

Sound Slot (Cubase Pro only)

The note events get different colors depending on the articulation that has been assigned to the note in the **Expression Map Setup** dialog.

Voice

The note events get different colors depending on their voice (soprano, alto, tenor, etc.).

Chord Track

The note events get different colors depending on whether they match the current chord, scale, or both.

For all of the options except **Part**, the pop-up menu also contains a **Setup** option. This option opens a dialog in which you can specify the colors that are associated with velocities, pitches, or channels.

RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

Selecting Note Events

The selected MIDI editor determines which of the following methods apply.

Do one of the following:

- Use the **Object Selection** tool  to drag a selection rectangle around the note events that you want to select. You can also click individual events.
- Select **Edit > Select** and select one of the options.
- To select the previous or next note event, use the **Left Arrow/Right Arrow** key.
- To select several notes, press **Shift** and use the **Left Arrow/Right Arrow** key.
- To select all notes of a certain pitch, press **Ctrl/Cmd** and click on a key in the keyboard display to the left.
- To select all the following note events of the same pitch/staff, press **Shift** and double-click a note event.

RELATED LINKS

[Selecting Note Events Using the Select Submenu](#) on page 705
[Editing](#) on page 1013

Selecting Note Events Using the Select Submenu

The **Select** submenu offers you several options to select note events.

To open the **Select** submenu, select **Edit > Select**.

All

Selects all note events in the edited part.

None

Deselects all note events.

Invert

Inverts the selection. All selected note events are deselected and all notes that were not selected are selected instead.

In Loop

Selects all note events that are partially or completely inside the boundaries of the left and right locators (only visible if locators are set).

From Start to Cursor

Selects all note events that begin to the left of the project cursor.

From Cursor to End

Selects all note events that end to the right of the project cursor.

Equal Pitch - all Octaves

Selects all note events of the highlighted part that have the same pitch (in any octave) as the selected note event.

NOTE

This function requires that a single note event is selected.

Equal Pitch - same Octave

Selects all note events of the highlighted part that have the same pitch (same octave) as the selected note event.

NOTE

This function requires that a single note event is selected.

Select Controllers in Note Range

Selects the MIDI controller data within the range of the selected note events.

RELATED LINKS

[Deleting Note Events](#) on page 706

Muting Note Events

You can mute individual note events in a MIDI editor. Muting individual notes allows you to exclude note events from playback.

Do one of the following:

- Click on a note event with the **Mute** tool.
- Drag a rectangle with the **Mute** tool, enclosing all note events that you want to mute.
- Select the note events and select **Edit > Mute**.

- To unmute a note event, click it or enclose it with the **Mute** tool. You can also select a note event and select **Edit > Unmute**.

Muted notes are dimmed in the note display.

Toggle Selections

- To toggle selected elements within a selection rectangle, press **Ctrl/Cmd** and enclose the same elements within a new selection rectangle.

Once you release the mouse button, the previous selection is deselected and vice versa.

Deleting Note Events

- To delete note events, click on them with the **Erase** tool or select them and press **Backspace**.

Cutting Note Events

The **Trim** tool allows you to cut off the end or the beginning of note events.

PROCEDURE

1. Select the **Trim** tool on the toolbar.
 2. Do one of the following:
 - To trim the end of a single note event, click on the note event.
 - To trim the beginning of a single note event, press **Alt** and click the note event.
 - To trim several note events, click and drag across the note events.
 - To set the same start and end time for all edited note events, press **Ctrl/Cmd** and vertically drag along the note events.
-

Editing Note Events on the Info Line

You can move, resize, or change the velocity of note events on the info line using regular value editing.

- To apply a value change to all selected note events, press **Ctrl/Cmd** and change a value on the info line.
- To adjust the pitch or velocity of note events via your MIDI keyboard, click in the **Pitch** or **Velocity** fields on the info line, and play a note on your MIDI keyboard.

If you have several note events selected and change a value, all selected events are changed by the set amount.

Duplicating and Repeating Note Events

You can duplicate and repeat note events in the same way as events in the **Project** window.

- To duplicate the selected note events, hold down **Alt** and drag the note events to a new position.

If **Snap** is activated, it determines to which positions you can copy notes.

- To copy the selected note events and place them directly behind the original, select **Edit > Functions > Duplicate**.

If several note events are selected, all of them are copied as one unit, maintaining the relative distance between the note events.

- To create a number of copies of the selected note events, select **Edit > Functions > Repeat**, specify the number, and click **OK**.

You can also press **Alt** and drag the right edge of the note events to the right to create copies of the note events.



Finding Exact Positions with Snap


The **Snap** function restricts horizontal movement and positioning to certain positions. This helps you find exact positions in the note display when editing note events in a MIDI editor. Affected operations include moving, duplicating, drawing, sizing, etc.

- To activate/deactivate snap, click **Snap** . If you select the **Bars+Beats** display format, the snap grid is set by the quantize value on the toolbar. This makes it possible to snap to straight note values and to swing grids that have been set up in the **Quantize Panel**.
- If you select any of the other display formats, positioning is restricted to the displayed grid.

Setting Velocity Values

When you draw note events in the MIDI editor, the note events get the velocity value that is set in the **Insert Velocity** field on the toolbar. There are different methods to set the velocity.

- Use the **Edit Velocity** tool modifier. The cursor changes into a speaker, and next to the note, a field with the Note Velocity slider shows the value. Move the mouse pointer up or down to change the value.




Value changes are applied to all selected notes.

For this, a tool modifier must be assigned for the **Edit Velocity** action. You can edit the tool modifier in the **Preferences** dialog (**Tool Modifiers** page).

- Open the **Insert Velocity** pop-up menu and select a velocity value. On this menu, you can also select **Setup** and specify custom velocity values for the pop-up menu.
- Double-click the **Insert Velocity** field on the toolbar and enter a velocity value.
- Assign key commands to **Insert Velocity 1-5** and use them. This allows you to quickly switch between different velocity values when you enter note events.


Handling Several MIDI Parts

- To activate a part for editing, open the **Currently Edited Part** menu and select a part.




When you select a part from the list, it is automatically active and centered in the note display.

- To zoom in on an active part, select **Edit > Zoom > Zoom to Event**.
- To display defined borders for the active part, activate **Show Part Borders**.



If this option is activated, all parts, except the active part, are grayed out.

- To restrict editing operations to the active part, activate **Edit Active Part Only**.



- To change the size of the part, drag the part borders.
The part borders display the name of the active part.

NOTE

If the part that you open for editing is a shared copy, any editing that you perform affects all shared copies of this part. In the **Project** window, shared copies are indicated by an equal sign in the top right corner of the part.

Looping MIDI Parts

The **Independent Track Loop** function allows you to loop a MIDI part independent of the project playback.

When you activate the loop, the MIDI events within the loop are repeated continuously while other events on other tracks are played back as usual. Every time the cycle restarts, the independent track loop also restarts.

PROCEDURE

1. Activate **Independent Track Loop**  on the toolbar.

NOTE

If you activate **Independent Track Loop**, the **Link Project and Lower Zone Editor Cursors** function is automatically deactivated in the lower zone editor.

If the button is not visible, right-click the toolbar and select **Independent Track Loop** from the menu.

If you have set up a loop range in the **Project** window, it is hidden from the ruler in the MIDI editor.

2. **Ctrl/Cmd**-click in the ruler to specify the start of the independent track loop.
 3. **Alt**-click in the ruler to specify the end of the independent track loop.
-

RESULT

The independent loop range is indicated in a different color.

The start and end of the loop range are displayed on the status line.

AFTER COMPLETING THIS TASK

To repeat the events of the loop range and fill up the active MIDI part, select **MIDI > Repeat Loop**.

Key Editor

The **Key Editor** is the default MIDI editor. It displays notes graphically in a piano roll-style grid. The **Key Editor** allows for detailed editing of notes and non-note events, such as MIDI controllers.

You can open the **Key Editor** in a separate window or in the lower zone of the **Project** window. Opening the **Key Editor** in the lower zone of the **Project** window is useful if you want to access the **Key Editor** functions from within a fixed zone of the **Project** window.


To open a MIDI part in the **Key Editor**, do one of the following:

- Double-click a MIDI part in the **Project** window.
- Select a MIDI part in the **Project** window and press **Return** or **Ctrl/Cmd-E**.
- Select a MIDI part in the **Project** window and select **MIDI > Open Key Editor**.
- In the **Key Commands** dialog in the **Editors** category, assign a key command for **Open Key Editor**. Select a MIDI part in the **Project** window and use the key command.


NOTE

If you select **MIDI > Set up Editor Preferences**, the **Preferences** dialog opens on the **Editors** page. Make your settings to specify if you want the editors to open in a separate window or in the lower zone of the **Project** window.

The **Key Editor** window:



The **Key Editor** in the lower zone of the **Project** window:



The **Key Editor** is divided into several sections:

- 1 **Toolbar**
Contains tools and settings.
- 2 **Status line**
Informs about the mouse time position, the mouse note position, and the current chord.
- 3 **Info line**
Displays note event information about a selected MIDI note.
- 4 **Ruler**
Displays the timeline.
- 5 **Inspector**
Contains tools and functions for working with MIDI data.
- 6 **Note display**
Contains a grid in which MIDI notes are displayed as boxes.
- 7 **Controller display**
The area below the note display consists of one or multiple controller lanes.

NOTE

You can activate/deactivate the status line, the info line, and the controller lanes by clicking **Set up Window Layout** on the toolbar and activating/deactivating the corresponding options.

Toolbar

The toolbar contains tools and settings for the **Key Editor**.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

Static Buttons

Solo Editor



Solos the editor during playback if the editor has the focus.

Record in Editor



Enables the recording of MIDI data in the editor if the editor has the focus.

NOTE

This only works if **MIDI Record Mode** is set to **Merge** or **Replace**.

Left Divider

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

Auto-Scroll

Link Project and Lower Zone Editor Cursors



Links timelines, cursors, and zoom factors of the lower zone editor and the **Project** window.

NOTE

You cannot activate **Link Project and Lower Zone Editor Cursors** if **Independent Track Loop** is active.

Auto-Scroll



Keeps the project cursor visible during playback. The **Switch Auto-Scroll Settings** pop-up menu allows you to activate **Page Scroll** or **Stationary Cursor** and to activate **Suspend Auto-Scroll when Editing**.

Switch Auto-Scroll Settings



Allows you to specify the auto-scroll settings.

Tool Buttons

Object Selection



Allows you to select events.

Draw



Allows you to draw events.

Erase



Allows you to delete events.

Trim



Allows you to trim events.

Split



Allows you to split events.

Mute



Allows you to mute events.

Glue



Allows you to glue together events of the same pitch.

Zoom



Allows you to zoom in/out. Hold **Alt** and click to zoom out.

Line



Allows you to create a series of contiguous events.

Time Warp (Cubase Pro only)



Allows you to drag a musical position to a certain position in time.

Acoustic Feedback

Acoustic Feedback



Automatically plays back events when you move or transpose them, or when you create them by drawing.

Auto Select Controllers

Auto Select Controllers



Automatically selects controller data of the selected MIDI notes.

Independent Track Loop

Independent Track Loop



Activates/Deactivates the independent track loop.

NOTE

If you activate **Independent Track Loop**, the **Link Project and Lower Zone Editor Cursors** function is automatically deactivated in the lower zone editor.

Show Note Expression Data

Show Note Expression Data



Shows note expression data.

Multiple Part Controllers

Show Part Borders




Shows/Hides part borders for the active MIDI part within the left and right locators.

Edit Active Part Only



Restricts editing operations to the active part.

Currently Edited Part



Lists all parts that were selected when you opened the editor, and allows you to activate a part.

Indicate Transpositions

Indicate Transpositions



Allows you to display the transposed pitches of MIDI notes.

Insert Velocity

Insert Velocity



Allows you to specify a velocity value for new notes.

Nudge Palette

Trim Start Left



Increases the length of the selected event by moving its start to the left.

Trim Start Right



Decreases the length of the selected event by moving its start to the right.

Move Left



Moves the selected event to the left.

Move Right



Moves the selected event to the right.

Trim End Left



Decreases the length of the selected event by moving its end to the left.

Trim End Right



Increases the length of the selected event by moving its end to the right.

Transpose Palette

Move Up



Transposes the selected event up by a half note.

Move Down



Transposes the selected event down by a half note.

Move Up More



Transposes the selected event up by an octave.

Move Down More



Transposes the selected event down by an octave.

Snap

Snap On/Off



Activates/Deactivates the snap function.

Snap Type



Allows you to select one of the following snap types:

- **Grid**  snaps events to the grid that is selected in the **Quantize Presets** pop-up menu.
- **Grid Relative**  keeps the relative positions when snapping events to the grid.
- **Events**  snaps events to the start or end of other events.
- **Shuffle**  changes the order of events if you drag one event to the left or right of other events.
- **Magnetic Cursor**  snaps events to the cursor position.
- **Grid + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu or to the cursor position.
- **Events + Cursor**  snaps events to the start or end of other events or to the cursor position.
- **Grid + Events + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu, to the start or end of other events or to the cursor position.

Grid Type



Allows you to select one of the following grid types:

- **Use Quantize** activates a grid where events snap to the value that is selected in the **Quantize Preset** pop-up menu.
- **Adapt to Zoom** activates a grid where events snap to the zoom level.

Quantize

Iterative Quantize On/Off



Activates/Deactivates iterative quantize.

Quantize Presets



Allows you to select a quantize or a groove preset.

Apply Quantize



Applies the quantize settings.


Open Quantize Panel



Opens the **Quantize Panel**.

Length Quantize

Length Quantize



Allows you to set a value for quantizing event lengths.

Step/MIDI Input

Step Input



Activates/Deactivates MIDI step input.

MIDI Input/Note Expression MIDI Input



Activates/Deactivates MIDI input and note expression MIDI input.

Move Insert Mode



Moves all note events to the right of the step input position to the right to make room for the inserted event when you insert notes.

NOTE

This only works if **Step Input** is activated.

Record Pitch



Includes the pitch when you insert notes.

Record NoteOn Velocity



Includes the NoteOn velocity when you insert notes.


Record NoteOff Velocity



Includes the NoteOff velocity when you insert notes.

Event Colors

Event Colors



Allows you to select event colors.

Edit VST Instrument

Edit VST Instrument



Opens the VST Instrument that the track is routed to.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls

Open in Separate Window



This button is available in the lower zone editor. It opens the editor in a separate window.

Open in Lower Zone



This button is available in the editor window. It opens the editor in the lower zone of the **Project** window.

Set up Window Layout



Allows you to set up the window layout.

Set up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.


RELATED LINKS

[Zooming in MIDI Editors](#) on page 703

Status Line

The status line shows information about the mouse time position, the mouse note position, and the current chord.

To show or hide the status line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Status Line**.



The on/off status of the status line in the **Key Editor** window and in the lower zone editor are independent of each other.

Mouse Time Position

Displays the exact time position of the mouse pointer, depending on the selected ruler display format. This lets you edit or insert notes at exact positions.

Mouse Note Position

Displays the exact pitch of the mouse pointer position. This facilitates finding the right pitch when entering or transposing notes.

Current Chord Display

When the project cursor is positioned over notes that form a chord, the chord is displayed here.

RELATED LINKS

[Looping MIDI Parts](#) on page 708

Info Line

The info line shows values and properties of the selected events. If several notes are selected, the values for the first note are displayed in color.

To show or hide the info line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Info Line**.

Start	End	Length	Pitch	Velocity	Channel	Off Velocity	Articulations	Release Length	Voice	Text
1. 2. 1. 0	1. 3. 1. 0	0. 1. 0. 0	A5	100	1	64	None	0. 0. 0. 0	--	

Length and position values are displayed in the selected ruler display format.

The on/off status of the info line in the **Key Editor** window and in the lower zone editor are independent of each other.


RELATED LINKS

[Editing Note Events on the Info Line](#) on page 706

[Changing the Display Format for the Ruler](#) on page 702

Key Editor Inspector

In a MIDI editor, the inspector is located left of the note display. The inspector contains tools and functions for working with MIDI data.



Expression Map (Cubase Pro only)

Allows you to load an expression map. Expression maps are useful for working with articulations.

Note Expression (Cubase Pro only)

Contains functions and settings related to Note Expression.

Chord Editing

Allows you to enter chords instead of single notes.

Quantize

Allows you to access the main quantize parameters. These are identical with the functions on the **Quantize** panel.

Transpose

Allows you to access the main parameters for transposing MIDI events.

Length

Contains length-related options, similar to the **Functions** submenu of the **MIDI** menu.

- To change the length of the selected MIDI events or all events of the active part if no events are selected, use the **Scale Length/Scale Legato** slider. At the maximum value, the notes reach the beginning of the next note.
- To make the new length settings permanent, click **Freeze MIDI Lengths** to the right of the **Scale Length/Scale Legato** slider.
- To fine-tune the distance between consecutive notes, use the **Overlap** slider. At **0 Ticks**, the **Scale Length/Scale Legato** slider extends each note so that it reaches the next note exactly. Positive values cause the notes to overlap and negative values allow you to define a small gap between the notes.
- To use the **Legato** function or slider to extend a note until the next selected note, activate **Between Selected**.

This is identical with activating the **Legato Mode: Between Selected Notes Only** option in the **Preferences** dialog.

Setup

Allows you to open a dialog to edit the **Inspector** settings for the editor. Click **Setup Inspector** , and from the pop-up menu, select **Setup**.

NOTE

These sections are also featured by the **Inspector** for the editor in the lower zone.

RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

[Note Expression Inspector Section](#) on page 801


[Quantize Panel](#) on page 269

[Transpose Functions](#) on page 299

[Opening the Editor Inspector](#) on page 54

Note Display

The note display is the main area in the **Key Editor**. It contains a grid in which note events are shown as boxes.



The width of a box corresponds to the note length. The vertical position of a box corresponds to the note number (pitch), with higher note events higher up in the grid. The piano keyboard helps you to find the right note number.

Controller Display

The area at the bottom of the **Key Editor** window is the controller display. It contains the controller events.

To show or hide the controller display, click **Set up Window Layout** on the toolbar, and activate or deactivate **Controller Lanes**.

The on/off status of the controller lanes in the **Key Editor** window and in the lower zone editor are independent of each other.

The controller display consists of one or several controller lanes that show one of the following properties or event types:

- Velocity values of the notes
- Pitchbend events
- Aftertouch events
- Poly Pressure events
- Program Change events
- System Exclusive events
- Any type of continuous controller event

Velocity values are shown as vertical bars in the controller display. Each velocity bar corresponds to a note event in the note display. Higher bars correspond to higher velocity values.



Events other than velocity values are shown as blocks. The block corresponds to the event values. The beginning of an event is marked by a curve point.

NOTE

Unlike note events, controller events have no length. The value of a controller event in the display is valid until the beginning of the next controller event.

Key Editor Operations

This section describes the principal editing operations within the **Key Editor**.

Inserting Note Events with the Object Selection Tool

You can insert note events with the **Object Selection** tool.

PREREQUISITE

You have set up the length for the note events quantize value in the **Length Quantize** pop-up menu of the toolbar.

PROCEDURE

- In the note display, double-click with the **Object Selection** tool at the position where you want to insert a note.


RESULT

A note is inserted at the position where you double-clicked with the length that you have set up in the **Length Quantize** pop-up menu.

Drawing Note Events with the Draw Tool

The **Draw** tool allows you to insert single note events in the note display.

When you move the cursor inside the note display, its position is indicated on the status line. Its pitch is indicated both on the status line and on the piano keyboard to the left.



- To draw a note, click in the note display.
The note event has the length that is set on the **Length Quantize** pop-up menu.
- To draw longer note events, click and drag in the note display.
The length of the note event is a multiple of the Length Quantize value. If **Length Quantize** is set to **Quantize Link**, the note value is determined by the quantize grid. The **Snap** function is taken into account.

NOTE

To temporarily switch from the **Object Selection** tool to the **Draw** tool, hold down **Alt**.

Modifying Note Values while Inserting Notes

When inserting note events, you can modify specific note values on the fly.

- To edit the note velocity, drag upwards or downwards.

- To edit the note pitch, hold down **Alt** and drag upwards or downwards.
- To edit the note length, drag to the left or to the right.
- To edit the time position, hold down **Shift** and drag to the left or to the right.

NOTE

You can activate/deactivate **Snap** temporarily by holding down **Ctrl/Cmd**.

Drawing Note Events with the Line Tool

In the note display, the **Line** tool allows you to draw a series of contiguous note events along different line shapes.

- To create contiguous note events, click and drag in the note display.
- To restrict movement to horizontal, press **Ctrl/Cmd** and drag.
The notes have the same pitch.

If **Snap** is activated, the note events and controller events are positioned and sized according to the **Quantize** and **Length Quantize** values.

RELATED LINKS

[The Line Tool Modes](#) on page 721

The Line Tool Modes

The **Line** tool allows you to create a series of contiguous note events along different line shapes. You can also edit multiple controller events simultaneously.

To select a different line mode, click **Line** and select a mode from the menu.



The following line modes are available:

Line

If this option is activated, you can click and drag to insert note events in the note display along a straight line in any angle. Use this option to edit controller data along a straight line in the controller display.

Parabola, Sine, Triangle, Square

These modes insert note events along different curve shapes.

Paint

This mode allows you to insert note events by painting in the note display.

Moving and Transposing Note Events

There are several options to move and transpose note events.

- To move note events in the editor, select the **Object Selection** tool and drag them to a new position.
All selected note events are moved, maintaining their relative positions. **Snap** is taken into account.

- To allow only horizontal or only vertical movement, hold down **Ctrl/Cmd** while dragging.
- To move note events via the **Nudge Palette** buttons on the toolbar, select the note events and click a **Nudge Palette** button.
This moves the selected note events by the **Snap** value in the drum sound list.
- To move note events to the project cursor position, select the note events and select **Edit > Move to > Cursor**.
- To move a note event via the info line, select a note event and edit the **Position** or **Pitch** on the info line.
- To transpose note events, select the note events and use the **Transpose Palette** buttons on the toolbar or the **Up Arrow/Down Arrow** keys.
Transpose is also affected by the global transpose setting.
- To transpose note events via the **Transpose Setup** dialog, select the note events and select **MIDI > Transpose Setup**.
- To transpose note events in steps of one octave, press **Shift** and use the **Up Arrow/Down Arrow** keys.

NOTE

- When you move selected note events to a different position, any selected controllers for these note events move accordingly.
- You can also adjust the position of note events by quantizing.


RELATED LINKS

[Transpose Setup](#) on page 690

Resizing Note Events

Do one of the following:

- To resize the note event, position the **Object Selection** tool at the start or the end of a note event and drag the mouse cursor to the left or right.
- To apply time-stretching and Note Expression data (Cubase Pro only) to a controller that is associated with the note event that you resize, activate **Sizing Applies Time Stretch** for the **Object Selection** tool before you resize the note.



- To move the start or end positions of the selected notes in steps according to the **Length Quantize** value on the toolbar, use the **Trim Start/End** buttons on the **Nudge** palette.
- Select the note and adjust its length on the info line.
- Select **Draw**  and drag left or right within the note display to draw a note.
The resulting note event length is a multiple of the **Length Quantize** value on the toolbar.
- Select **Trim**  and cut off the end or the beginning of note events.

RELATED LINKS

[Using the Setup Options](#) on page 994

[Editing on the Info Line](#) on page 48

[Using the Trim Tool](#) on page 723


[Resizing Events with the Object Selection Tool - Sizing Applies Time Stretch](#) on page 195

Using the Trim Tool

The Trim tool allows you to change the length of note events by cutting off the end or the beginning of notes. Using the Trim tool means moving the note-on or the note-off event for one or several notes to a position defined with the mouse.

PROCEDURE

1. Select **Trim**  on the toolbar.
The mouse pointer changes to a knife symbol.
2. To edit a single note, click on it with **Trim** .
The range between the mouse pointer and the end of the note will be removed. Use the mouse note info on the status line to find the exact position for the trim operation.
3. To edit several notes, click and drag with the mouse across the notes.



By default, the Trim tool cuts off the end of notes. To trim the beginning of notes, press **Alt** while dragging. When dragged across several notes, a line is displayed. The notes will be trimmed along this line. If you press **Ctrl/Cmd** while dragging, you will get a vertical trim line, allowing you to set the same start or end time for all edited notes. You can change the **Trim** tool key commands in the **Preferences** dialog (**Editing—Tool Modifiers** page).

Splitting Note Events

- To split the note at the position that you point, click on a note with **Split** .
If several notes are selected, they are all split at the same position. The snap setting is taken into account.
- To split all notes that are intersected by the project cursor position, select **Edit > Functions > Split at Cursor**.
- To split all notes that are intersected by the left or right locator at the locator positions, select **Edit > Functions > Split Loop**.

Gluing Note Events

You can glue together note events of the same pitch.

- To glue note events, select **Glue**  and click on a note event.
The note event is glued together with the next note event of the same pitch. The result is a long note event that spans from the start of the first note to the end of the second note. The properties (velocity, pitch, etc.) of the first note event apply.

Changing the Pitch of Chords

You can use the chord type buttons to change the pitch of chords.

PROCEDURE

1. In the **Inspector**, open the **Chord Editing** section.
2. In the note display, select the notes that you want to edit.
If the chord is recognized, the root note, chord type, and tensions are indicated in the **Chord Type** field. This also works with arpeggiated notes.

3. In the **Chord Editing** section, activate one of the **Triads** buttons or **4-Note Chords** buttons.
The selected notes are transposed so that they fit the selected chord type.
 4. Use the **Up Arrow/Down Arrow** keys to change the pitch of the chord.
-

Changing the Voicing of Chords

PROCEDURE

1. In the **Inspector**, open the **Chord Editing** section.
 2. In the note display, select the notes that you want to edit.
 3. In the **Chord Editing** section, use the **Inversions** buttons and the **Drop Notes** buttons to change the voicing.
-

RESULT

The selected notes are transposed so that they fit the selected chord type.

Chord Editing Section

The **Chord Editing** section in the **Inspector** allows you to insert and edit chords, and change voicings.



Chord Type

Shows the chord type of the selected chords.

Add to Chord Track

Adds the chord indicated in the **Chord Type** field to the chord track. The chord event is inserted at the position on the chord track that corresponds to the position of the MIDI notes. Any existing chord events at this position are overwritten.

Match with Chord Track

Applies the chord events from the chord track to the selected notes in the MIDI editor. The chord event that is effective at the position of the first selected note is applied to the selected notes, which are then transposed. Only the basic chord type is applied. Tensions are not taken into account.

Only the first effective chord event is applied.

Triads

Allows you to insert triads to the note display. You can also click one of the **Triads** buttons to transpose the selected notes so that they fit to the selected chord type.

4-Note Chords

Allows you to insert 4-note chords to the note display. You can also click one of the **4-Note Chords** buttons to transpose the selected notes so that they fit to the selected chord type.

Inversions - Move highest note to bottom



Inverts the highest note of a chord. The corresponding notes are transposed by as many octaves as needed.

Inversions - Move lowest note to top



Inverts the lowest note of a chord. The corresponding notes are transposed by as many octaves as needed.

Drop Notes - Move the second highest note an octave lower



Moves the second highest note of a chord down by one octave.

Drop Notes - Move the third highest note an octave lower



Moves the third highest note of a chord down by one octave.

Drop Notes - Move the second and fourth highest notes an octave lower



Moves the second and fourth highest notes of a chord down by one octave.

Create Chord Symbols

Performs a chord analysis of the selected notes. If nothing is selected, the whole MIDI part is analyzed.

Inserting Chords

You can use the tools in the **Chord Editing** section of the **Inspector** to insert and edit chords.

PROCEDURE

1. In the Inspector, open the **Chord Editing** section.
 2. Select the **Insert** tool  to the right of the chord type that you want to insert.
 3. Click in the note display and drag to the left or right to determine the length of the chord. Drag up or down to determine its pitch.
To change the chord type while you insert chords, hold **Alt** and drag up or down.
If **Acoustic Feedback** is activated, you hear the chord while dragging. A tooltip indicates the root note and chord type of the inserted chord. **Snap** and **Length Quantize** are taken into account.
-

Applying Chord Events to Note Events

You can apply chord events from the chord track to notes in the MIDI editor.

PREREQUISITE

Create a chord track and add chord events.

PROCEDURE

1. Open the MIDI editor.
 2. In the **Inspector**, open the **Chord Editing** section.
 3. Select **Match with Chord Track**.
-

RESULT

The first chord event of the chord track is applied to the selected notes. Only the basic chord type is applied. Tensions are not taken into account.

Drum Map Handling

When a drum map is assigned to a MIDI or instrument track, the **Key Editor** displays the drum sound names as defined by the drum map. This allows you to use the **Key Editor** for drum editing, for example, when editing drum note lengths or when editing several parts to identify drum events.

The name of the drum sound is displayed in the following locations:

- On the info line in the **Pitch** field.
- On the status line in the **Mouse Note Position** field.
- In the note event if the zoom factor is high enough.
- When dragging a note event.

Expression Map Handling (Cubase Pro only)

When an expression map is assigned to a MIDI track, the musical articulations that are defined for that map are displayed in the following locations of the **Key Editor**:

- On the info line in the **Articulations** field.
- On the controller lane.
- In the note event if the vertical zoom factor is high enough.

Note Expression Data (Cubase Pro only)

The **Key Editor** is the main editor for working with Note Expression.

RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

Editing Note Events via MIDI Input

You can directly hear your editing results. Editing the properties of note events via MIDI can be a quick way to, for example, set the velocity value of a note event.

PROCEDURE

1. In the **Key Editor**, select the note event that you want to edit.
2. Click **MIDI Input**  on the toolbar.
Editing via MIDI is enabled.
3. Use the note buttons on the toolbar to decide which properties are changed by the MIDI input.

You can enable editing of pitch, note-on and/or note-off velocity. For example, with the following setting, the edited notes get the pitch and velocity values of the notes input via MIDI, but the note-off velocities remain as they are.



4. Play a note on your MIDI instrument.
-

RESULT

The selected note gets the pitch, note-on velocity and/or note-off velocity of the played note. The next note in the edited part is automatically selected to allow quick editing of a series of notes.

AFTER COMPLETING THIS TASK


To try another setting, select the note again and play a note on your MIDI instrument.

Step Input

Step input, or step recording, allows you to enter note events or chords one at a time without worrying about the exact timing. This is useful, for example, when you know the part that you want to record but are not able to play it exactly as you want it.

PROCEDURE

1. On the toolbar, activate **Step Input** .
2. Use the note buttons to the right to determine which properties are included when you insert the note events.
For example, you can include the note-on velocity and/or note-off velocity of the played notes. You can also deactivate the pitch property, in which case all notes get a pitch C3, no matter what you play.
3. Click anywhere in the note display to set the start position of the first note event or chord. The step input position is shown as a vertical line in the note display.



4. Specify the note event spacing and length with the **Quantize** and **Length Quantize** pop-up menus.
The note events that you insert are positioned according to the **Quantize** value and have the length of the **Length Quantize** value.

NOTE

If **Length Quantize** is set to **Quantize Link**, the note length is also determined by the **Quantize** value.

5. Play the first note event or chord on your MIDI instrument.
The note event or chord appears in the editor and the step input position advances by one quantize value step.

NOTE

If **Move Insert Mode** is activated, all note events to the right of the step input position are moved to make room for the inserted note event or chord.



6. Continue in the same way with the rest of the note events or chords.

You can adjust the **Quantize** or **Length Quantize** values to change the timing or note event lengths. You can also move the step input position manually by clicking anywhere in the note display.


To insert a rest, press the **Right Arrow** key. This advances the step input position by one step.

7. When you are done, click **Step Input** again to deactivate step input.
-

Using the Controller Display


The Controller Display displays the controller events. By default, the controller display has a single lane that shows one event type at a time. However, you can add as many lanes as you need. The use of several controller lanes allows you to view and edit different controllers at the same time.

Each MIDI track has its own controller lane setup (number of lanes and selected event types). When you create new tracks, they get the last used controller lane setup.



The controller display with lanes.

- To add a controller lane, click **Create Controller Lane**  or open the **Controller Selection and Functions** menu and select **Create Controller Lane**.




- To remove a controller lane, open the **Controller Selection and Functions** pop-up menu and select **Remove this Lane**.
This hides the lane from view. It does not affect the events in any way.
If you remove all lanes, the controller display is hidden. To bring it back, click **Create Controller Lane**.
- To show/hide multiple lanes, open the **Controller Lane Setup** pop-up menu, and select **Show/Hide Controller Lanes**.
- To reset the controller display to show only the velocity lane, open the **Controller Lane Setup** pop-up menu, and select **Velocity Only**.
- To automatically show all controller lanes with controller data, open the **Controller Lane Setup** pop-up menu, and select **Show Used Controllers**.

Selecting the Controller Event Type

Each controller lane shows one event type at a time. You can select which event type to display on a controller lane.

- To select which type is displayed, open the **Controller Selection and Functions** pop-up menu and select an event type.



Setting up Available Continuous Controllers


In the **MIDI Controller Setup** dialog, you can specify which continuous controllers are available for selection.

NOTE

The **MIDI Controller Setup** dialog can be opened from different areas in the program. The settings are global, that is, the setup you choose here affects all areas of the program where MIDI controllers can be selected.

PROCEDURE

1. Select **Controller Selection and Functions > Setup**.



2. In the **MIDI Controller Setup** dialog, move all the controllers that you need to the list on the left and move the controllers that you do not need to the list on the right.
3. Click **OK**.

Handling Controller Lane Presets

Once you have made up your controller lane setup, you can save it as a controller lane preset. For example, you can have a preset with one velocity lane and another preset with a combination of several controller lanes, such as velocity, pitchbend, or modulation.

Saving a Controller Lane Setup as Preset

You can save a controller lane setup via the **Controller Lane Setup** pop-up menu.

PROCEDURE

1. Click **Controller Lane Setup** .
2. Select **Add Preset**.
3. In the **Type In Preset Name** dialog, enter a name for the preset.
4. Click **OK**.

RESULT

Your controller lane setup is now available as a controller lane preset.

NOTE

To apply a saved preset, open the **Controller Lane Setup** pop-up menu and select the preset.

NOTE

To remove or rename a preset, open the **Controller Lane Setup** pop-up menu and select **Organize Presets**. A dialog opens, where you can remove and rename presets.

Adding Events in the Controller Display

- To create a new event in the velocity controller display, click with the **Draw** tool or the **Line** tool in the event display.
- To create a new event for any other event type, click with the **Draw** tool or the **Line** tool in the controller display.

NOTE

In the **Key Editor**, you can also add modulation controller events (CC1) by copying note events from the event display and pasting them on the controller lane.

Editing Events in the Controller Display

All controller values can be edited with the **Draw** tool or the **Line** tool. If you have selected more than one controller event on a controller lane, the controller lane editor is displayed.

- To edit events in the velocity controller display, use the **Draw** tool or the **Line** tool and drag the event.



The **Object Selection** tool automatically switches to the **Draw** tool when you move the pointer into the controller display.

When you move the pointer in the controller lane, the corresponding event type value is displayed below the event type name.

In velocity mode, no new controller events are added this way.

- To edit the values of any other event type in the controller display, press **Alt** and drag, or use the **Draw** tool or the **Line** tool and drag.



When you move the pointer inside a controller lane, the event type value changes corresponding to the pointer movement. The event type value is displayed below the event type name, left of the controller display.

- If there is more than one note at the same position, their velocity bars overlap on the controller lane. If none of the notes are selected, all notes at the same position are set to the same velocity value when you draw.

To edit the velocity of only one of the notes at the same position, first select the note in the note display.

- To select all events on a controller lane, open the **Controller Lane Setup** pop-up menu and select the **Select all Controller Events** option.
- To use the **Object Selection** tool to select events in the velocity controller display, press **Alt**.
- To cut, copy, and paste events in the controller display select the event and select **Edit > Cut/Copy/Paste**.
When pasting events, the events on the clipboard are added, starting at the project cursor position and maintaining their relative distances. If a pasted event ends up at the same position as an existing event of the same type, the old event is replaced.

NOTE

If the speaker icon (Acoustic Feedback) is activated on the toolbar, the notes are played back when you adjust the velocity. This allows you to audition your changes.

RELATED LINKS

[Controller Event Editor](#) on page 735

Editing Events in the Controller Display Using the Line Tool

You can draw and edit events in the controller display with the **Line** tool.

Line Mode

In **Line** mode, you can draw events in a straight line.

- To draw a straight line in the controller display, click where you want the ramp to start and drag the cursor to where you want the ramp to end.



NOTE

If **Snap** is activated, the **Length Quantize** value determines the density of created controller curves. For very smooth curves, use a small **Length Quantize** value or deactivate **Snap**. To avoid over-dense controller curves, which can cause MIDI playback to stutter, use a medium-low density.

Parabola Mode

In **Parabola** mode, you can draw events on a parabola curve. This gives more natural curves and fades. The result depends on the direction from which you draw the parabola.



You can use modifier keys to determine the shape of the parabola curve.

- To reverse the parabola curve, press **Ctrl/Cmd**.
- To change the position of the whole curve, press **Alt**.
- To increase or decrease the exponent, press **Shift**.

NOTE

If **Snap** is activated, the **Length Quantize** value determines the density of created controller curves. For very smooth curves, use a small **Length Quantize** value or deactivate **Snap**. To avoid

over-dense controller curves, which can cause MIDI playback to stutter, use a medium-low density.

Sine, Triangle, and Square Mode

The **Sine**, **Triangle**, and **Square** modes create events with values that are aligned with continuous curves.



In these modes, the quantize value determines the period of the curve that is the length of one curve cycle and the **Length Quantize** value determines the density of the events. The lower the **Length Quantize** note value becomes, the smoother the curve gets.

NOTE

If **Length Quantize** is set to **Quantize Link** and you enter data in **Sine**, **Triangle** or **Square** mode, the density of the events depends on the zoom factor.

You can use modifier keys to determine the shape of the curve.

- To change the phase of the beginning of the curve, press **Ctrl/Cmd**.
- To change the position of the whole curve, press **Alt-Ctrl/Cmd**.
- To change the maximum position of the triangle curve or the pulse of the square curve in **Triangle** and **Square** mode, press **Shift-Ctrl/Cmd**. This creates sawtooth curves.
- You can also set the curve period freely by holding down **Shift** when you insert events in **Sine**, **Triangle**, or **Square** mode. Activate **Snap**, **Shift**-click and drag to set the length of one period. The period length will be a multiple of the quantize value.

Paint Mode

In **Paint** mode, you can draw in multiple notes.

The quantize value determines the density of created controller curves. For very smooth curves, use a small quantize value or deactivate **Snap**. However, this creates a large number of MIDI events, which can cause MIDI playback to stutter in some situations. A medium-low density is often sufficient.

Editing Events using the Draw Tool

You can draw and edit events in the controller display with the **Draw** tool. The **Draw** tool has the same functionality as the **Line** tool in **Paint** mode.

- To change the velocity of a single note, click on its velocity bar and drag the bar up or down.

NOTE

When you move the pointer inside a controller lane, the event type value changes corresponding to the pointer movement. The event type value is displayed below the event type name, left of the controller display.

Editing Articulations (Cubase Pro only)

You can add and edit musical expressions or articulations in the controller lane.


RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

Editing Dynamics (Cubase Pro only)

Provided that the dynamics mapping is set up and activated for the track, you can insert 12 dynamics symbols in the lower part of the **Articulations/Dynamics** lane.

- To insert a dynamics symbol, click in the controller lane with the **Draw** tool.
A mezzo forte symbol is inserted.
- To select another dynamics symbol for an event, click on the triangle in the upper left corner of the event and select a symbol from the pop-up menu.
If several events are selected, the same symbol is applied to all events.



- To step through the available dynamics symbols, use the mouse wheel or the **One down** and **One up** key commands.
If several events are selected, they all change in increments, that is, relative to the original values.
- To modify the settings for the dynamics symbols, open the **Controller Selection and Functions** pop-up menu and select **Dynamics Mapping Setup**.

Moving and copying dynamics events is identical to working with other events on the controller lane.


RELATED LINKS

[Moving Events in the Controller Display](#) on page 736

Using Continuous Controllers


When a continuous controller is selected for a controller lane, additional data is displayed on the controller lane. This is due to the fact that MIDI controller data can be recorded or entered either for an automation track or for a MIDI part.

If automation data already exists for a controller, this is indicated by an asterisk that is displayed next to the controller name on the **Controller Selection and Functions** pop-up menu.



If the automation data is controller data that you have entered in a MIDI editor, the data is displayed on the controller lane. If the controller data was recorded on an automation track in the **Project** window, no events are displayed on the controller lane.

If conflicting controller data exists in different places, you can specify what happens on playback by making settings for the automation merge mode. The resulting curve is displayed in addition to the curve that you entered on the controller lane.



- 1 The controller curve before the part starts. This curve depends on the existing controller data and on the selected merge mode.
- 2 Controller curve entered on the controller lane.
- 3 Resulting controller curve if controller automation was also recorded on a track. These values depend on the selected automation merge mode.

On the controller lane, you can also see the controller curve that is applied before the part starts. This tells you which controller value is being used at the starting point of the part so that you can choose the start value accordingly.

The start value also depends on the automation merge mode.

RELATED LINKS

[MIDI Controller Automation](#) on page 625

[Automation Merge Modes](#) on page 625

Poly Pressure Events

Poly Pressure events are events that belong to a specific note number (key). That is, each Poly Pressure event has the following editable values: the note number and the amount of pressure.

When **Poly Pressure** is selected on the **Controller Selection and Functions** pop-up menu, value fields for the note number and for the amount are shown to the left of the controller display.

Adding Poly Pressure Events

PROCEDURE

1. Open the **Controller Selection and Functions** pop-up menu and select **Poly Pressure**.
2. Click on the keyboard display to set the note number.
The selected note number is displayed in the upper value field to the left of the controller display.

NOTE

This only works for the topmost lane. If you have selected Poly Pressure for several controller lanes, you have to type in the note number directly in the lower value field to the left of each lane.

3. Use the **Draw** tool to add a new event.
-

Editing Poly Pressure Events

PROCEDURE


1. Open the **Controller Selection and Functions** pop-up menu and select **Poly Pressure**.
 2. Click the arrow button next to the note number to the left of the controller lane.
A pop-up menu appears and lists all note numbers for which there already are Poly Pressure events.
 3. Select a note number from the pop-up menu.
The Poly Pressure events for the selected note number are shown in the controller lane.
 4. Use the **Draw** tool to edit the events.
To edit events without adding new events, press **Ctrl/Cmd+Alt** while drawing.
Poly Pressure events can also be added and edited in the **List Editor**.
-

Controller Event Editor

The controller event editor allows you to perform additional scaling operations for selection ranges on existing controller curves.

- To open the controller event editor, activate the **Object Selection** tool and drag a selection rectangle on the controller lane.

The controller event editor features the following smart controls for specific editing modes:



1 Tilt Left

If you click in the upper left corner of the editor, you can tilt the left part of the curve. This allows you to tilt the event values at the start of the curve upwards or downwards.

2 Compress Left

If you **Alt**-click in the upper left corner of the editor, you can compress or expand the left part of the curve. This allows you to compress or expand the event values at the start of the curve.

3 Scale Vertically

If you click in the middle of the upper border of the editor, you can scale the curve vertically. This allows you to raise or lower the event values of the curve in percent.

4 Move Vertically

If you click on the upper border of the editor, you can move the entire curve vertically. This allows you to raise or lower the values of the event values of the curve.

5 Compress Right

If you **Alt**-click in the upper right corner of the editor, you can compress or expand the right part of the curve. This allows you to compress or expand the event values at the end of the curve.

6 Tilt Right

If you click in the upper right corner of the editor, you can tilt the right part of the curve. This allows you to tilt the event values at the end of the curve upwards or downwards.

7 Scale Around Relative Center

If you **Alt**-click in the middle right border of the editor, you can scale the curve relative to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

8 Scale Around Absolute Center

If you click in the middle right corner of the editor, you can scale the curve absolute to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

9 Stretch

If you click on the lower border of the editor, you can stretch the curve horizontally. This allows you to move the event values of the curve to the left or to the right.

Editing Selection Ranges

The controller lane editor allows you to perform additional scaling operations for selection ranges on existing controller curves.

- To open the controller lane editor, use the **Object Selection** tool to create a selection rectangle on the controller lane, encompassing the controller events that you want to edit. For velocity lanes, press **Alt** to get the **Object Selection** tool.

NOTE

- The controller lane editor is not available for **Articulation** or **Dynamics** lanes.
 - For velocity lanes, the editor also opens if you select multiple MIDI notes in the note display.
-
- To switch the controller lane editor to vertical scaling mode, press **Shift** and click on any of the smart controls.
 - To move the whole selection up/down or left/right, click on a controller event inside the editor and drag the curve.
 - To restrict the direction to horizontal or vertical movement, depending on the direction in which you start dragging, press **Ctrl/Cmd** when dragging.

NOTE

Snap is taken into account when moving controller curves horizontally.

Moving Events in the Controller Display

You can move events in a controller lane.

PROCEDURE

1. Select the events that you want to move with the **Object Selection** tool.
You can also click and drag to create a selection rectangle that encompasses the events that you want to move.
 2. Click on a curve point inside the selection and drag the events.
-

RESULT

The events inside the selection are moved to the new position. Snap is taken into account.

NOTE

If **Auto Select Controllers** is activated on the **Key Editor** toolbar, selecting notes also selects the corresponding controller events. Moving events in the note display also moves the corresponding controller events.

RELATED LINKS

[Selecting Controllers within the Note Range](#) on page 737

Deleting Events in the Controller Display

IMPORTANT

If there is more than one note at the same position, there is only one visible velocity bar. Make sure that you delete only the notes that you want to delete.

- To delete events, click on them with the **Erase** tool or select them and press **Backspace**. You can also delete notes by deleting their velocity bars in the controller display. If there is more than one note at the same position, there may still only be one velocity bar visible. Make sure that you delete only the desired notes!

Selecting Controllers within the Note Range

A note range lasts until the start of the next note or the end of the part. Selected controllers for notes are moved when the corresponding notes are moved.

You can select the controllers within the range of the selected notes.

- To always select the corresponding controllers when you select a note event, activate **Auto Select Controllers** .
- To select the controllers within the note range, select **Edit > Select > Select Controllers in Note Range**.
For this to work, only 2 notes have to be selected.

Basic Score Editor (Cubase Artist only)

The basic **Score Editor** is available in Cubase Artist. It shows MIDI notes as a musical score. This offers basic score editing and printing.

You can open the **Score Editor** in a separate window or in the lower zone of the **Project** window. Opening the **Score Editor** in the lower zone of the **Project** window is useful if you want to access the **Score Editor** functions from within a fixed zone of the **Project** window.


To open a MIDI part in the **Score Editor**, do one of the following:

- Select a MIDI part in the **Project** window and select **MIDI > Scores > Open Score Editor**.
- Select a MIDI part in the **Project** window and press **Ctrl/Cmd-R**.


NOTE

If you select **MIDI > Set up Editor Preferences**, the **Preferences** dialog opens on the **Editors** page. Make your settings to specify if you want editors to open in a separate window or in the lower zone of the **Project** window.

The **Score Editor** window:



The **Score Editor** in the lower zone of the **Project** window:



The **Score Editor** is divided into several sections:

- 1 **Toolbar**
Contains tools and settings.
 - 2 **Status line**
Informs about the mouse time position, the mouse note position, and the current chord.
 - 3 **Info line**
Displays note event information about a selected MIDI note.
 - 4 **Extended toolbar**
Contains note value buttons and enharmonic shift buttons.
- To open one or several parts in the **Score Editor**, select one or several tracks or any number of parts, and select **MIDI > Open Score Editor**.
If you have selected parts on several tracks, you get one staff for each track. The staves are tied together by barlines and placed in the order of the tracks in the **Project** window.

- To rearrange the staves, close the editor and in the **Project** window, rearrange the tracks. Then reopen the **Score Editor**.

NOTE

You can activate/deactivate the status line, the info line, the tools, and the filters by clicking **Set up Window Layout** on the toolbar and activating/deactivating the corresponding options.

Toolbar

The toolbar contains tools and various settings for the **Score Editor**.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

Static Buttons

Solo Editor



Solos the editor during playback if the editor has the focus.

Record in Editor



Enables the recording of MIDI data in the editor if the editor has the focus.

NOTE

This only works if **MIDI Record Mode** is set to **Merge** or **Replace**.

Tool Buttons

Object Selection



Allows you to select events.

Erase



Allows you to delete events.

Insert Note



Allows you to insert notes.

Split



Allows you to split events.

Glue



Allows you to glue together events of the same pitch.

Insert Text



Allows you to insert text.

Auto-Scroll

Auto-Scroll



Keeps the project cursor visible during playback.

Insert Velocity

Insert Velocity



Allows you to specify a velocity value for new notes.

Snap

Snap Type



Allows you to select one of the following snap types:

- **Grid**  snaps events to the grid that is selected in the **Quantize Presets** pop-up menu.
- **Grid Relative**  keeps the relative positions when snapping events to the grid.

Quantize

Iterative Quantize On/Off



Activates/Deactivates iterative quantize.

Quantize Presets



Allows you to select a quantize or a groove preset.

Apply Quantize



Applies the quantize settings.


Open Quantize Panel



Opens the **Quantize Panel**.

Length Quantize

Length Quantize



Allows you to set a value for quantizing event lengths.

Step/MIDI Input

Step Input



Activates/Deactivates MIDI step input.

MIDI Input/Note Expression MIDI Input



Activates/Deactivates MIDI input and note expression MIDI input.

Move Insert Mode



Moves all note events to the right of the step input position to the right to make room for the inserted event when you insert notes.

NOTE

This only works if **Step Input** is activated.

Record Pitch



Includes the pitch when you insert notes.

Record NoteOn Velocity



Includes the NoteOn velocity when you insert notes.

Record NoteOff Velocity



Includes the NoteOff velocity when you insert notes.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls

Open in Separate Window



This button is available in the lower zone editor. It opens the editor in a separate window.

Open in Lower Zone



This button is available in the editor window. It opens the editor in the lower zone of the **Project** window.

Set up Window Layout



Allows you to set up the window layout.

Set up Toolbar




Opens a pop-up menu where you can set up which toolbar elements are visible.

Status Line

The status line is displayed below the toolbar. It shows important information about the mouse position and the chord display. Select the notes that form (compose) the chord to make the status line appear in the **Current Chord Display**.

To show or hide the status line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Status Line**.



The on/off status of the status line in the **Score Editor** window and in the lower zone editor are independent of each other.

Mouse Time Position

Displays the exact time position of the mouse pointer, depending on the selected ruler display format. This lets you edit or insert notes at exact positions.

Mouse Note Position

Displays the exact pitch of the mouse pointer position. This facilitates finding the right pitch when entering or transposing notes.

Current Chord Display

When the project cursor is positioned over notes that form a chord, this chord is displayed here.

Info Line

The info line shows values and properties of the selected MIDI notes. If several notes are selected, the values for the first note are displayed in color.

To show or hide the info line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Info Line**.

Start	End	Length	Pitch	Velocity	Channel	Off Velocity	Voice	Text
6. 4. 4. 0	7. 1. 1. 0	0. 0. 1. 0	C-2	100	1	64	Alto	Note

The on/off status of the info line in the **Score Editor** window and in the lower zone editor are independent of each other.

RELATED LINKS

[Changing the Display Format for the Ruler](#) on page 702

Extended Toolbar

The extended toolbar contains note value buttons and enharmonic shift buttons.

To show or hide the extended toolbar, click **Set up Window Layout** on the toolbar, and activate or deactivate **Tools**.



Note Value Buttons

Allows you to select a note value for input. The  and  options are for triplet and dotted note values.

The selected note value is displayed in the Length value field on the toolbar and in the **Insert Note** tool shape.

To resize all selected notes to the same note value, press **Ctrl/Cmd** and click one of the note value buttons.

Enharmonic Shift

Allows you to manually select whether a note is displayed with flat or sharp accidentals. The **Off** button resets the notes to original display. The other options are **double flats**, **flats**, **No** (no accidentals shown, regardless of pitch), **sharps**, and **double sharps**.

RELATED LINKS

[Enharmonic Shift](#) on page 748

Score Display

The main area of the **Score Editor** window shows the notes in the edited parts on one or several staves. Parts on different tracks are shown on different staves.



- If you are editing one or several parts on the same track, as much of them as possible is shown on several staves, comparable with a score on paper.
- If you are editing parts on several tracks, they are put on a grand staff. A grand staff is composed of multiple staves that are tied together by barlines.
- The number of bars that are displayed on the screen depends on the size of the window and the number of notes in each bar.
- The end of the last part is indicated by a double barline.

All MIDI input is directed to one of the tracks, which is called the active staff. The active staff is indicated by a rectangle to the left of the clef symbol.



- To change the active staff, click on the staff that you want to activate.

Score Editor Operations (Cubase Artist only)

This section describes the principal editing operations within the **Score Editor**.

Improving the Score Display

When you open the **Score Editor** for a part that was recorded in real time, the score may not look as legible as you expect. The **Score Editor** can ignore the minor time variances in performance

and make a neater score. To achieve this, the **Staff Settings** dialog provides settings that determine how the program displays the music.


Staff Settings Dialog

This dialog allows you to change how Cubase displays the music.

IMPORTANT

The settings that you make in this dialog are independent for each staff (track), but common for a piano staff that you have created with the **Split** option.

To open the **Staff Settings** dialog, double-click in the area to the left of the staff, or select a staff and select **MIDI > Scores > Staff Settings**.



NOTE

The time signature follows the time signatures that are set in the **Tempo Track** editor. These settings are common to all tracks/staves in the score.

Staff Mode

The **Staff Mode** determines how the staff is shown.

- In **Single** mode, all notes in the part are shown in the same staff.
- In **Split** mode, the part is split on the screen into a bass and treble clef, as in a piano score. The **Split Point** value determines where you want the split to occur. Notes above and including the split note appear on the upper staff, and notes below the split note appear on the lower staff.

Before and after setting a split at C3:



Display Quantize

This section allows you to change the way Cubase displays scores.

IMPORTANT

These display values are only used for the graphical display in the **Score Editor**. They do not affect the playback.

Notes

Determines the smallest note value to be displayed and the smallest position to be recognized and properly displayed. Set this to the smallest significant note position used in your music.

For example, if you have notes on odd 16th note positions, set this value to 16. The **T** values are for triplet note values. This setting is partly overridden by **Auto Quantize**.

Rests

This value is used as a recommendation. Cubase does not display rests smaller than this value, except where necessary. In effect, this setting also determines how the length of notes is displayed. Set this value according to the smallest note value (length) that you want to be displayed for a single note, positioned on a beat.

Auto Quantize

Allows you to make your score look as legible as possible. **Auto Quantize** allows you to mix straight notes with tuplets (triplets) in a part. However, **Auto Quantize** also uses the (display) quantize value. If there is no appropriate note value for a certain note or group of notes, it uses the set quantize value is used to display it.

Generally, only activate this option if your music contains mixed triplets and straight notes. If the part is imprecisely played and/or complex, **Auto Quantize** may have a problem figuring out exactly what you mean.

Dev.

If this option is activated, triplets/straight notes are detected even if they are not exactly on the beat. However, if you know that your triplets/straight notes are perfectly recorded, either through quantizing or entered by hand, deactivate this option.

This option is only available if **Auto Quantize** is activated.

Adapt

If this option is activated, the program guesses that when one triplet is found, there are probably more triplets surrounding it. Activate this option if not all of your triplets are detected.

This option is only available if **Auto Quantize** is activated.

Clef and Key

In this section, you can set the correct clef and key.

Clef/Key Display

Allows you to select the clef or key via the scrollbar.

Lower Staff

Sets the clef and key to the lower staff.

Auto Clef

If this option is activated, Cubase attempts to guess the correct clef, judging from the pitch of the music.

Display Transpose

In this section, you can specify a separate display transpose setting for each staff (track). This transposes the notes in the score without affecting how the notes are played back. This allows

you to record and play back a multi staff arrangement and still score each instrument according to its own transposition.

Semitones

Allows you to manually set a display transpose value.

Instrument

Allows you to select the instrument for which you are scoring.

Interpretation Options

In this section, you can make additional settings on how the score is displayed.

Clean Lengths

If this option is activated, notes that are considered to be chords are shown with identical lengths. Longer notes are displayed shorter than they are. Notes with very short overlaps are also cut off. This is similar to the **No Overlap** option, but with a more subtle effect.

No Overlap

If this option is activated, one note is never shown as overlapping another, lengthwise. This allows long and short notes that start at the same point to be displayed without ties. The long notes are cut off in the display. This makes the music more legible.

A sample measure with **No Overlap** deactivated:




A sample measure with **No Overlap** activated:




Syncopation

If this option is activated, syncopated notes are shown in a more legible way.

A dotted quarter note at the end of a bar when **Syncopation** is deactivated:



A dotted quarter note at the end of a bar when **Syncopation** is activated:



Shuffle

If this option is activated and you have played a shuffle beat, the beat is displayed as straight notes, not as triplets. This is very common in jazz notation.

Quantize Value

When you move the mouse pointer over the score, the **Mouse Time Position** field on the status line tracks your movement and shows the current position in bars, beats, 16th notes, and ticks.

The quantize value controls the positioning on screen. If you set the value to 1/8, you can only insert and move notes to 8th note positions, at quarter notes, at half bars, or at bar positions.

It is recommended to set the quantize value to the smallest note value in the piece. This does not stop you from inputting notes at coarser positions. However, if you set the quantize value to a too small note value, it is easier to make mistakes.



With the quantize value set to 1/8, you can only input notes at 8th note positions.

You can also use the **Quantize Panel** to create other quantize values, irregular grids, etc.

Creating Notes

In the score display, the **Insert Note** tool allows you to create notes. However, you must first set the note value (length) and spacing.

PROCEDURE

1. Set the note value in one of the following ways:
 - Click the note symbols on the extended toolbar.
 - Select an option from the **Length Quantize** pop-up menu on the toolbar.
2. Select the **Insert Note** tool.
If you selected the note value via the extended toolbar buttons, the **Insert Note** tool is automatically selected.
3. Open the **Quantize Presets** pop-up menu on the toolbar and select a quantize value.
4. Move the mouse over the staff to find the correct position.
The position is displayed on the **Mouse Time Position** display on the status line. The position snaps to the grid that is defined by the quantize value.
5. Move the mouse vertically to find the correct pitch.
The **Mouse Note Position** display on the status line shows the pitch at the pointer position.
6. Click in the staff.

RESULT

The note appears in the score. The notes get the insert velocity value that is set in the **Insert Velocity** field on the toolbar.

NOTE

If the notes that you enter appear to have the wrong note value you may have to adjust the **Display Quantize** settings. For example, you enter a 1/32 note that is displayed as a 1/16 note.

RELATED LINKS

- [Setting Velocity Values](#) on page 707
- [Display Quantize](#) on page 744

Moving and Transposing Notes

PROCEDURE

1. Open the **Quantize Presets** pop-up menu on the toolbar and select a quantize value.
 2. If you want to hear the pitch of the note while moving, activate **Acoustic Feedback** on the toolbar.
 3. Select the notes that you want to move.
 4. Click one of the selected notes and drag it to a new position and/or pitch.
The horizontal movement of the note is snaps to the current quantize value. The position boxes on the toolbar show the position and pitch for the dragged note.
To restrict moving to one direction, press **Ctrl/Cmd** while dragging.
-

Duplicating Notes

PROCEDURE

1. Open the **Quantize Presets** pop-up menu on the toolbar and select a quantize value.
 2. Select the notes that you want to duplicate.
 3. Press **Alt** and drag the notes to their new position.
To restrict moving to one direction, press **Ctrl/Cmd** while dragging.
-

Changing the Note Length

The displayed note length is not necessarily the actual note length. It also depends on the note values and rest values for **Display Quantize** in the **Staff Settings** dialog. This is important to remember when you change the length of a note.

You can change the length of a note in the following ways:

- Select the notes that you want to change and **Ctrl/Cmd**-click on one of the note icons on the extended toolbar.
All the selected notes are assigned to the length of the clicked note.
- Select the notes that you want to change and edit the length values on the info line.

RELATED LINKS

[Improving the Score Display](#) on page 743

[Editing Note Events on the Info Line](#) on page 706

Splitting and Gluing Note Events

- To split 2 notes that are strung together by a tie, click on the tied note head with the **Cut** tool.
- The note is divided into 2, with the respective length of the main and the tied note.
- To glue a note to the next note with the same pitch, click on a note with the **Glue** tool.

Enharmonic Shift

You can perform an enharmonic shift on notes that are not displayed with the accidentals you wish.

PROCEDURE

1. Select the notes that you want to shift.
 2. Click one of the enharmonic shift buttons on the extended toolbar.
-

RELATED LINKS

[Extended Toolbar](#) on page 742

Flipping Stems

The direction of the note stems is automatically selected according to the note pitches. However, you can change this manually.

PROCEDURE

1. Select the notes for which you want to flip the stem direction.

2. Select **MIDI > Scores > Flip Stems**.
-

Working with Text

You can use the **Text** tool to add comments, articulation, or instrumentation advice and other text strings anywhere in the score display.

Adding Text

PROCEDURE

1. On the toolbar, select the **Text** tool.



2. Click anywhere in the score.
A blinking cursor indicates that you can enter text.
 3. Enter the text and press **Return**.
-

Editing Text

- To edit existing text, double-click it with the **Object Selection** tool.
This opens the text for editing. Use the **Up Arrow**, **Down Arrow**, **Left Arrow**, **Right Arrow** keys to move the cursor, delete characters with the **Delete** or **Backspace** keys, press **Return** when you are finished.
- To delete text blocks, select them with the **Object Selection** tool and press **Backspace** or **Delete**.
- To move text blocks, drag them to a new position.
- To duplicate text blocks, press **Alt** and drag them to a new position.

Changing the Text Font, Size, and Style

You can change the font, size, and style of the text that you have added to the score display.


PROCEDURE

1. Do one of the following:
 - To change the settings for a specific text block, click on the text with the **Object Selection** tool.
 - To set the default settings for all new text blocks, unselect any selected text block and change the settings.
 2. Select **MIDI > Scores > Set Font**.
 3. In the **Font Settings** dialog, make your settings.
 4. Click **Apply**.
 5. Optional: Select another text block, adjust the settings, and click **Apply**.
-

Set Font Dialog

In this dialog, you can change the font, size, and style of the text that you have added to the score display.

To open the **Set Font** dialog, select **MIDI > Scores > Set Font**.



Font

Allows you to specify the font for the text. Which fonts are available on the pop-up menu depends on the fonts that you have installed on your computer.

IMPORTANT

Do not use the Steinberg fonts. These are special fonts used by the program, for example, for score symbols, and not suited for common text.

Size

Sets the size of the text.

Frame

Allows you to enclose the text in a rectangular (box) or oval frame.

Font Options

Determine whether the text is formatted bold, italic, and/or underlined.

Printing the Score

PROCEDURE

1. Open the parts that you want to print in the **Score Editor**.
2. Select **File > Page Setup** and make sure that all your printer settings are correct.

IMPORTANT

If you change your setting for paper size, scale, and margins now, the score may change its look.

3. Click **OK**.
 4. Select **File > Print**.
 5. In the **Print** dialog, make your settings.
 6. Click **Print**.
-

Drum Editor

The **Drum Editor** is the editor to use when you are editing drum or percussion parts.

You can open the **Drum Editor** in a separate window or in the lower zone of the **Project** window. Opening the **Drum Editor** in the lower zone of the **Project** window is useful if you want to access the **Drum Editor** functions from within a fixed zone of the **Project** window.

To open a MIDI part in the **Drum Editor**, do one of the following:

- Select a MIDI part in the **Project** window and select **MIDI > Open Drum Editor**.


If the MIDI track has a drum map assigned and **Editor Content Follows Event Selection** and **Use Drum Editor when Drum Map is assigned** are activated in the **Preferences** dialog (**Editors** page), you can do the following to open a MIDI part in the **Drum Editor**:

- Double-click a MIDI part in the **Project** window.
- Select a MIDI part in the **Project** window and press **Return** or **Ctrl/Cmd-E**.
- Select a MIDI part in the **Project** window and select **MIDI > Open Drum Editor**.
- In the **Key Commands** dialog in the **Editors** category, assign a key command for **Open Drum Editor**. Select a MIDI part in the **Project** window and use the key command.


NOTE

If you select **MIDI > Set up Editor Preferences**, the **Preferences** dialog opens on the **Editors** page. Make your settings to specify if you want the **Drum Editor** to open in a separate window or in the lower zone of the **Project** window.

The **Drum Editor** window:



The **Drum Editor** in the lower zone of the **Project** window:



The **Drum Editor** is divided into several sections:

- 1 **Toolbar**
Contains tools and settings.
- 2 **Status line**
Informs about the mouse time position and the mouse note position.
- 3 **Info line**
Displays information about the selected event.
- 4 **Inspector**
Contains tools and functions for working with MIDI data.
- 5 **Drum sound list**
Lists all drum sounds.
- 6 **Drum map**
Lets you select the drum map for the edited track or a list of drum sound names.
- 7 **Ruler**
Displays the time line.
- 8 **Note display**
Contains a grid in which notes are displayed.
- 9 **Controller display**
The area below the note display consists of one or multiple controller lanes.

NOTE

You can activate/deactivate the status line, the info line, and the controller lanes by clicking **Set up Window Layout** on the toolbar and activating/deactivating the corresponding options.

Toolbar

The toolbar contains tools and various settings for the **Drum Editor**.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

Static Buttons

Solo Instrument (Requires Drum Map)



Solos the instrument during playback.

NOTE

This only works if there is a drum map assigned.

Solo Editor



Solos the editor during playback if the editor has the focus.

Record in Editor



Enables the recording of MIDI data in the editor if the editor has the focus.

NOTE

This only works if **MIDI Record Mode** is set to **Merge** or **Replace**.

Left Divider

Left Divider



Allows you to use the left divider. Tools that are placed to the left of the divider are always shown.

Drum Sound Visibility

Drum Visibility Agents



Allows you to determine which drum sounds are displayed in the drum sound list.

Auto-Scroll

Link Project and Lower Zone Editor Cursors



Links timelines, cursors, and zoom factors of the lower zone editor and the **Project** window.

NOTE

You cannot activate **Link Project and Lower Zone Editor Cursors** if **Independent Track Loop** is active.

Auto-Scroll



Keeps the project cursor visible during playback. The **Switch Auto-Scroll Settings** pop-up menu allows you to activate **Page Scroll** or **Stationary Cursor** and to activate **Suspend Auto-Scroll when Editing**.

Switch Auto-Scroll Settings



Allows you to specify the auto-scroll settings.

Tool Buttons

Object Selection



Allows you to select events.

Drumstick



Allows you to draw events.

Erase



Allows you to delete events.

Zoom



Allows you to zoom in/out. Hold **Alt** and click to zoom out.

Mute



Allows you to mute events.

Line



Allows you to create a series of contiguous events.

Time Warp (Cubase Pro only)



Allows you to drag a musical position to a certain position in time.

Acoustic Feedback

Acoustic Feedback



Automatically plays back events when you move or transpose them, or when you create them by drawing.

Auto Select Controllers

Auto Select Controllers



Automatically selects controller data of the selected MIDI notes.

Independent Track Loop

Independent Track Loop



Activates/Deactivates the independent track loop.

NOTE

If you activate **Independent Track Loop**, the **Link Project and Lower Zone Editor Cursors** function is automatically deactivated in the lower zone editor.

Multiple Part Controls

Show Part Borders




Shows/Hides part borders for the active MIDI part within the left and right locators.

Edit Active Part Only



Restricts editing operations to the active part.

Currently Edited Part



Lists all parts that were selected when you opened the editor, and allows you to activate a part.

Insert Velocity

Insert Velocity



Allows you to specify a velocity value for new notes.

Notes Length

Insert Length



Allows you to determine a length for newly created notes.

Show Note Length On/Off



Shows drum notes as boxes that display the note length.

Nudge Palette

Trim Start Left



Increases the length of the selected event by moving its start to the left.

Trim Start Right



Decreases the length of the selected event by moving its start to the right.

Move Left



Moves the selected event to the left.

Move Right



Moves the selected event to the right.

Trim End Left



Decreases the length of the selected event by moving its end to the left.

Trim End Right



Increases the length of the selected event by moving its end to the right.

Transpose Palette

Move Up



Transposes the selected event up by a half note.

Move Down



Transposes the selected event down by a half note.

Move Up More



Transposes the selected event up by an octave.

Move Down More



Transposes the selected event down by an octave.

Snap

Snap On/Off



Activates/Deactivates the snap function.

Snap Type



Allows you to select one of the following snap types:

- **Grid**  snaps events to the grid that is selected in the **Quantize Presets** pop-up menu.
- **Grid Relative**  keeps the relative positions when snapping events to the grid.
- **Events**  snaps events to the start or end of other events.
- **Shuffle**  changes the order of events if you drag one event to the left or right of other events.

- **Magnetic Cursor**  snaps events to the cursor position.
- **Grid + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu or to the cursor position.
- **Events + Cursor**  snaps events to the start or end of other events or to the cursor position.
- **Grid + Events + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu, to the start or end of other events or to the cursor position.

Grid Type



Allows you to select one of the following grid types:

- **Use Quantize** activates a grid where events snap to the value that is selected in the **Quantize Preset** pop-up menu.
- **Adapt to Zoom** activates a grid where events snap to the zoom level.
- **Use Snap from Drum Map** activates a grid where events snap to the **Snap** value that is selected in the drum map.

Quantize

Iterative Quantize On/Off



Activates/Deactivates iterative quantize.

Quantize Presets



Allows you to select a quantize or a groove preset.

Apply Quantize



Applies the quantize settings.

Open Quantize Panel



Opens the **Quantize Panel**.

Step/MIDI Input

Step Input



Activates/Deactivates MIDI step input.

MIDI Input/Note Expression MIDI Input



Activates/Deactivates MIDI input and note expression MIDI input.

Move Insert Mode



Moves all note events to the right of the step input position to the right to make room for the inserted event when you insert notes.

NOTE

This only works if **Step Input** is activated.

Record Pitch



Includes the pitch when you insert notes.

Record NoteOn Velocity



Includes the NoteOn velocity when you insert notes.


Record NoteOff Velocity



Includes the NoteOff velocity when you insert notes.

Event Colors

Event Colors



Allows you to select event colors.

Edit VST Instrument

Edit VST Instrument



Opens the VST Instrument that the track is routed to.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Window Zone Controls

Open in Separate Window



This button is available in the lower zone editor. It opens the editor in a separate window.

Open in Lower Zone



This button is available in the editor window. It opens the editor in the lower zone of the **Project** window.

Set up Window Layout



Allows you to set up the window layout.

Set up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.

RELATED LINKS

[Zooming in MIDI Editors](#) on page 703

Status Line

The status line is displayed below the toolbar. It displays important mouse information.

To show or hide the status line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Status Line**.



The on/off status of the status line in the **Drum Editor** window and in the lower zone editor are independent of each other.

Mouse Time Position

Displays the exact time position of the mouse pointer, depending on the selected ruler display format. This lets you edit or insert notes at exact positions.

Mouse Note Position

Displays the exact pitch of the mouse pointer position. This facilitates finding the right pitch when entering or transposing notes.

Track Loop Start/Track Loop End

If **Independent Track Loop** is activated on the toolbar and you set up a loop, the start/end position is displayed.

RELATED LINKS

[Toolbar](#) on page 753

Info Line

The info line shows values and properties of the selected events. If several notes are selected, the values for the first note are displayed in color.

To show or hide the info line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Info Line**.



Length and position values are displayed in the selected ruler display format.

The on/off status of the info line in the **Drum Editor** window and in the lower zone editor are independent of each other.

RELATED LINKS

[Editing Note Events on the Info Line](#) on page 706

Drum Editor Inspector

The Inspector is located to the left of the note display. The inspector contains tools and functions for working with MIDI data.



Expression Map

Allows you to load an expression map. Expression maps are useful for working with articulations.

Quantize

Allows you to access the main quantize parameters. These are identical with the functions on the **Quantize Panel**.

Length

Contains length-related options, similar to the **Functions** submenu of the **MIDI** menu.

- To change the length of the selected MIDI events or all events of the active part if no events are selected, use the **Scale Length/Scale Legato** slider. At the maximum value the notes reach the beginning of the next note.
- To make the new length settings permanent, click **Freeze MIDI Lengths** to the right of the **Scale Length/Scale Legato** slider.
- To fine-tune the distance between consecutive notes, use the **Overlap** slider. At **0 Ticks**, the **Scale Length/Scale Legato** slider extends each note so that it reaches the next note exactly. Positive values cause the notes to overlap and negative values allow you to define a small gap between the notes.
- To use the **Legato** function or slider to extend a note until the next selected note, activate **Between Selected**.

This is identical with activating the **Legato Mode: Between Selected Notes Only** option in the **Preferences** dialog.

Setup

Allows you to open a dialog to edit the **Inspector** settings for the editor. Click **Setup Inspector** , and from the pop-up menu, select **Setup**.

NOTE

These sections are also featured by the editor **Inspector** for the editor in the lower zone.

RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

[Note Expression Inspector Section](#) on page 801

[Quantize Panel](#) on page 269

[Transpose Functions](#) on page 299


[Opening the Editor Inspector](#) on page 54

Note Display

The note display of the **Drum Editor** contains a grid in which note events are shown.



The notes are displayed as diamond symbols. If you activate **Show Note Length On/Off** on the toolbar, notes are displayed as boxes and show the note length.



The vertical position of the notes corresponds to the drum sound list to the left, while the horizontal position corresponds to the note's position in time.

RELATED LINKS

[Toolbar](#) on page 753


Controller Display

The area at the bottom of the **Drum Editor** window is the controller display.

It consists of one or several controller lanes that show one of the following properties or event types:

- Velocity values of the notes
- Pitchbend events
- Aftertouch events
- Poly Pressure events
- Program Change events
- System Exclusive events
- Any type of continuous controller event

Velocity values are shown as vertical bars in the controller display. Each velocity bar corresponds to a note in the note display. Higher bars correspond to higher velocity values.



Events other than velocity values are shown as blocks. The block corresponds to the event values. The beginning of an event is marked by a curve point.

When you select a line in the drum sound list, only the velocity controller events that belong to the note events on this line are displayed in the controller display.

If you select more than one line in the drum sound list, the controller lane shows all velocity controller events for all notes on the selected lines. This is useful when you have to adjust the controller values between different drum sounds.

NOTE

Unlike note events, controller events have no length. The value of a controller event in the display is valid until the beginning of the next controller event.

Drum Sound List

The drum sound list lists all drum sounds by name and allows you to adjust and manipulate the drum sound setup in various ways.

Pitch	Instrument	Snap	Mute	I-Note	O-Not	Chan	Output
C1	Bass Drum	1/16		C1	C1	10	Track
C#1	Side Stick	1/16		C#1	C#1	10	Track
D1	Acoustic Snare	1/16		D1	D1	10	Track
D#1	Hand Clap	1/16		D#1	D#1	10	Track
E1	Electric Snare	1/16		E1	E1	10	Track
F1	Low Floor Tom	1/16		F1	F1	10	Track
F#1	Closed Hi-Hat	1/16		F#1	F#1	10	Track
G1	High Floor Tom	1/16		G1	G1	10	Track
G#1	Pedal Hi-Hat	1/16		G#1	G#1	10	Track
A1	Low Tom	1/16		A1	A1	10	Track

NOTE

The number of columns in the list depends on whether a drum map is selected for the track or not.

Pitch

Note number of the drum sound.

Instrument

Name of the drum sound.

Snap

This is used when entering and editing notes.

Mute

Allows you to mute drum sounds.

I-Note

Input note for the drum sound. When you play this note, it is mapped to the corresponding drum sound and automatically transposed according to the **Pitch** setting for the sound.

O-Note

The MIDI output note that is sent out every time the drum sound is played back.

Chan

The MIDI channel, on which the drum sound is played back.

Output

MIDI output on which the drum sound is played back.

RELATED LINKS

[Muting Notes and Drum Sounds](#) on page 767

[Drum Maps](#) on page 767

Drum Sound Visibility

The **Drum Visibility Agents** on the drum editor toolbar allow you to determine which drum sounds are shown in the drum sound list.



- To open the visibility agents, click **Drum Visibility Agents** on the toolbar.

Show All Drum Sounds

Shows all drum sounds as defined in the selected drum map.

NOTE

In this mode, you can edit the order of the drum sound list manually.

Show Drum Sounds with Events

Shows only the drum sounds for which events are available in the selected MIDI part.

Show Drum Sounds in use by Instrument

Shows all drum sounds for which a pad etc. is in use for the instrument. This option is only available if the instrument can provide this information.

Reverse Drum Sound List

Reverses the order of the sounds displayed in the drum sound list.

Drum Map and Names Menus

Below the drum sound list are pop-up menus that are used for selecting a drum map for the edited track or, if no drum map is selected, a list of drum sound names.



RELATED LINKS

[Drum Maps](#) on page 767

Drum Editor Operations

This section describes the general editing operations within the **Drum Editor**.

Inserting Note Events

You can insert note events with the **Object Selection** tool or the **Drumstick** tool.

PREREQUISITE

You have set up the **Insert Length** on the toolbar to determine the length of the inserted note. If **Insert Length** is set to **Drum-Map Link**, the note gets the length of the **Snap** value set for the sound in the drum sound list. You have activated **Snap**.

NOTE

If you want to snap positions according to the **Quantize Presets** setting on the toolbar, activate **Use Quantize**.

PROCEDURE

- Perform one of the following actions:
 - Select the **Object Selection** tool and double-click in the event display.
 - Select the **Drumstick** tool and click in the event display.

NOTE

To temporarily switch from the **Object Selection** tool to the **Drumstick** tool, hold down **Alt**.

RESULT

A note event is inserted.

Inserting Multiple Note Events

You can insert multiple note events of the same pitch with the **Object Selection** tool or the **Drumstick** tool.

PREREQUISITE

You have set up the **Insert Length** on the toolbar to determine the length of the inserted note. If **Insert Length** is set to **Drum-Map Link**, the note gets the length of the **Snap** value set for the sound in the drum sound list. You have activated **Snap**.

NOTE

If you want to snap positions according to the **Quantize Presets** setting on the toolbar, activate **Use Quantize**.

PROCEDURE

- Perform one of the following actions:
 - On the toolbar, select the **Object Selection** tool, double-click in the event display and drag to the right.
 - On the toolbar, select the **Drumstick** tool, click in the event display and drag to the right.
-

RESULT

The note events are inserted.

RELATED LINKS

[Toolbar](#) on page 753

Modifying Note Values While Inserting Notes

When inserting note events, you can modify specific note values on the fly.

- To edit the note velocity, drag upwards or downwards.
- To edit the note pitch, hold down **Alt** and drag upwards or downwards.
- To edit the note length, drag to the left or to the right.

NOTE

If you want to edit the note length in the **Drum Editor**, you must deactivate **Snap** and activate **Show Note Length On/Off**. Otherwise, the note is repeated.

- To edit the time position, hold down **Shift** and drag to the left or to the right.

NOTE

You can activate/deactivate **Snap** temporarily by holding down **Ctrl/Cmd**.

Changing the Note Length

You can change the note length in the drum editor with the **Object Selection** tool or with the **Drumstick** tool.

PREREQUISITE

You have activated **Show Note Length On/Off** on the drum editor toolbar.

PROCEDURE

1. Move the mouse pointer to the beginning or the end of the note that you want to edit.
The mouse pointer turns into a double arrow.
2. Drag to the left or to the right to adjust the length.
An info box with the current length value is displayed.
3. Release the mouse button.

RESULT

The note length is changed. **Snap** is taken into account.

Deleting Note Events

PROCEDURE

- Perform one of the following actions:
 - Select the **Erase** tool and click the event.
 - Select the **Object Selection** tool and double-click the event.
 - Select the **Drumstick** tool and click the event.
-

RESULT

The note event is deleted.

Deleting Multiple Note Events

You can delete multiple note events of the same pitch with the **Object Selection** tool or the **Drumstick** tool.

PREREQUISITE

To delete multiple note events with the **Object Selection** tool, **Snap** must be activated.

PROCEDURE

- Do one of the following:
 - On the toolbar, select the **Object Selection** tool, double-click the first event you want to delete, and drag to the right.
 - On the toolbar, select the **Drumstick** tool, click the first event you want to delete, and drag to the right.
-

RESULT

The note events are deleted.

Moving and Transposing Note Events

There are several options to move and transpose note events.

- To move note events in the editor, select the **Object Selection** tool and drag them to a new position.
All selected note events are moved, maintaining their relative positions. **Snap** is taken into account.
- To allow only horizontal or only vertical movement, hold down **Ctrl/Cmd** while dragging.
- To move note events via the **Nudge Palette** buttons on the toolbar, select the note events and click a **Nudge Palette** button.
This moves the selected note events by the **Snap** value in the drum sound list.
- To move note events to the project cursor position, select the note events and select **Edit > Move to > Cursor**.
- To move a note event via the info line, select a note event and edit the **Position** or **Pitch** on the info line.
- To transpose note events, select the note events and use the **Transpose Palette** buttons on the toolbar or the **Up Arrow/Down Arrow** keys.
Transpose is also affected by the global transpose setting.
- To transpose note events via the **Transpose Setup** dialog, select the note events and select **MIDI > Transpose Setup**.
- To transpose note events in steps of one octave, press **Shift** and use the **Up Arrow/Down Arrow** keys.

NOTE

- When you move selected note events to a different position, any selected controllers for these note events move accordingly.
 - You can also adjust the position of note events by quantizing.
-

RELATED LINKS

[Transpose Setup](#) on page 690

Muting Notes and Drum Sounds

IMPORTANT

The mute state for drum sounds is part of the drum map. All other tracks using this map are affected.

- To mute individual notes, click or enclose them with the **Mute** tool, or select **Edit > Mute**.
- To mute a drum sound in a drum map, click in the **Mute** column for the drum sound.

Pitch	Instrument	Snap	Mute	I-Note	O-Not	Chan	Output
C1	Bass Drum	1/16	■	C1	C1	10	Track
C#1	Side Stick	1/16	■	C#1	C#1	10	Track
D1	Acoustic Snare	1/16	■	D1	D1	10	Track
D#1	Hand Clap	1/16	■	D#1	D#1	10	Track

- To mute all other drum sounds, click **Solo Instrument (Requires Drum Map)** on the toolbar.

RELATED LINKS

[Selecting a Drum Map for a Track](#) on page 770

Drum Maps

A drum kit in a MIDI instrument is most often a set of different drum sounds with each sound placed on a separate key. For example, the different sounds are assigned to different MIDI note numbers. One key plays a bass drum sound, another a snare, and so on.

Different MIDI instruments often use different key assignments. This can be troublesome if you have made a drum pattern using one MIDI device and then want to try it on another. When you switch devices, it is very likely that your snare drum becomes a ride cymbal or your hi-hat becomes a tom, etc., because the drum sounds are distributed differently in the instruments.

To solve this problem and to simplify several aspects of MIDI drum kits, such as using drum sounds from different instruments in the same drum kit, Cubase features drum maps. A drum map is a list of drum sounds with a number of settings for each sound. When you play back a MIDI track for which you have selected a drum map, the MIDI notes are filtered through the drum map before they are sent to the MIDI instrument. The map determines which MIDI note number is sent out for each drum sound and which sound is played on the receiving MIDI device.

When you want to try your drum pattern on another instrument, you simply switch to the corresponding drum map, and your snare drum sound remains a snare drum sound.

If you want to have the same drum maps included in your projects, you can load these into the template.

NOTE

Drum maps are saved with the project files. If you have created or modified a drum map, use the **Save** function to save it as a separate XML file to make it available for loading into other projects.


RELATED LINKS

[Saving a Project Template File](#) on page 86

Drum Map Setup Dialog

This dialog allows you to load, create, modify, and save drum maps.

To open the **Drum Map Setup** dialog, select **Drum Map Setup** from the **Map** pop-up menu or the **MIDI** menu.



The list on the left shows the loaded drum maps. The sounds and settings of the selected drum map are displayed on the right.

NOTE

The settings for the drum sounds are the same as in the **Drum Editor**.

Use Head Pairs (Cubase Pro only)

If this option is activated, 2 head symbols for each drum sound are displayed in the drum sound list.

Edit in Scores (Cubase Pro only)

If this option is activated, you can change the settings for the score drum map directly in the score.

Output

Allows you to select the output for the drum map sounds.

Drum Sound List

Lists all drum sounds and their settings. To audition a drum sound, click the leftmost column.

NOTE

If you audition a sound in the **Drum Map Setup** dialog and the sound is set to MIDI output **Default**, the output that is selected on the **Output** pop-up menu in the lower left corner is used. When auditioning a default output sound in the **Drum Editor**, the MIDI output selected for the track is used.

The **Functions** pop-up menu contains the following options:

New Map

Adds a new drum map to the project. The drum sounds are named “Sound 1, Sound 2, etc.” and have all parameters set to default values. The map is named “Empty Map”.

To rename the drum map, click the name in the list and type in a new name.

New Copy

Adds a copy of the selected drum map to create a new drum map. You can then change the drum sound settings of the copy and rename the drum map in the list.

Remove

Removes the selected drum map from the project.

Load

Allows you to load drum maps into your project.

Save

Allows you to save the drum map that is selected in the list on disk. Drum map files have the extension .drm.

Edit head pairs

Allows you to customize the note pairs.

RELATED LINKS


[Drum Map Settings](#) on page 769

[Channel and Output Settings](#) on page 770

Drum Map Settings

A drum map consists of settings for 128 drum sounds, one for each MIDI note number.

- To get an overview of the drum map settings, open the **Drum Editor** and use the **Map** pop-up menu below the drum sound list to select the **GM Map** drum map.



The GM map is set up according to the General MIDI standard.

You can change all drum map settings except the pitch directly in the drum sound list or in the **Drum Map Setup** dialog. These changes affect all tracks that use the drum map.

RELATED LINKS

[Drum Sound List](#) on page 762

[Drum Map Setup Dialog](#) on page 768

Importing Drum Maps from Virtual Instruments

You can import your drum map settings to an instrument track that is routed to Groove Agent SE.

PREREQUISITE

To import your drum map settings to an instrument track, the track has to be routed to Groove Agent SE or another drum instrument that supports drum maps.

PROCEDURE

1. Load a drum kit in Groove Agent SE.
2. In the Inspector for the track, open the **Drum Maps** pop-up menu and select **Create Drum Map from Instrument**.
The drum map is created for the kit that is assigned to the MIDI port and channel selected in the Inspector.
3. Open the **Drum Maps** pop-up menu again and select **Drum Map Setup**.

4. In the list on the left, select the kit that you have loaded in the instrument.
-

RESULT

The sounds and settings of the instrument are displayed in the **Drum Map Setup**.

NOTE

Instrument and pattern pads are both exported to the drum map. If they share keys, the pattern pads get priority, that is, their settings are included in the drum map.

Channel and Output Settings

You can set separate MIDI channels and/or MIDI outputs for each sound in a drum map. When a drum map is selected for a track, the MIDI channel settings in the drum map override the MIDI channel setting for the track.

You can select different channels and/or outputs for different sounds. This allows you to construct drum kits with sounds from several different MIDI devices, etc.

- To make a drum sound use the channel of the track, set the channel in the drum map to **Any**.
- To make the sound use the MIDI output that is selected for the track, set the MIDI output for a sound in a drum map to **Default**.
- To send the sound to a specific MIDI output, select any other option.
- To select the same MIDI channel or MIDI device for all sounds in a drum map, click in the **Channel** column, press **Ctrl/Cmd**, and select a channel or output.
- If you make specific MIDI channel and output settings for all sounds in a drum map, you can switch between drum maps to send your drum tracks to another MIDI instrument.

Selecting a Drum Map for a Track

- To select a drum map for a MIDI track, open the **Map** pop-up menu in the Inspector or in the **Drum Editor** and select a drum map.
- To deactivate the drum map functionality in the **Drum Editor**, open the **Map** pop-up menu in the Inspector or in the **Drum Editor** and select **No Drum Map**.
Even if you do not use a drum map, you can still separate sounds by name using a name list.

NOTE

Initially, the **Map** pop-up menu only contains **GM Map**.

I-Notes, O-Notes and Pitches

Going through the following theory helps you make the most out of the drum map concept – especially if you want to create your own drum maps.

A drum map is a kind of filter that transforms notes according to the settings in the map. It does this transformation twice; once when it receives an incoming note, that is when you play a note on your MIDI controller, and once when a note is sent from the program to the MIDI sound device.

The following example shows a modified drum map with a bass drum sound that has different pitch, I-note, and O-note values.

Pitch	Instrument	Snap	M	I-Note	O-Note	Chann
C1	Bass Drum	1/16		C1	C1	10
C#1	Side Stick	1/16		C#1	C#1	10
D1	Acoustic Snare	1/16		D1	D1	10
D#1	Hand Clap	1/16		D#1	D#1	10

I-Notes (Input Notes)

When you play a note on your MIDI instrument, the program looks for this note number among the I-notes in the drum map. If you play the note A1, the program finds that this is the I-note of the bass drum sound.

This is where the first transformation happens: the note gets a new note number according to the pitch setting for the drum sound. In our case, the note is transformed to a C1 note, because that is the pitch of the bass drum sound. If you record the note, it is recorded as a C1 note.

For example, you can place drum sounds near each other on the keyboard so that they can be easily played together, move sounds so that the most important sounds can be played from a short keyboard, play a sound from a black key instead of a white. If you never play your drum parts from a MIDI controller but draw them in the editor you do not need the I-note setting.

O-Notes (Output Notes)

The next step is the output. This is what happens when you play back the recorded note, or when the note you play is sent back out to a MIDI instrument in real time (MIDI Thru):

The program checks the drum map and finds the drum sound with the pitch of the note. In our case, this is a C1 note and the drum sound is the bass drum. Before the note is sent to the MIDI output, the second transformation takes place: the note number is changed to that of the O-note for the sound. In our example, the note sent to the MIDI instrument is a B0 note.

The O-note settings let you set things up so that the bass drum sound really plays a bass drum. If you are using a MIDI instrument in which the bass drum sound is on the C2 key, you set the O-note for the bass drum sound to C2. When you switch to another instrument (in which the bass drum is on C1) you want the bass drum O-note set to C1. Once you have set up drum maps for all your MIDI instruments, you can select another drum map when you want to use another MIDI instrument for drum sounds.

Setting Pitches of Notes According to their O-Note Settings

You can set the pitch of notes according to their O-note settings. This is useful if you want to convert a track to a regular MIDI track with no drum map and still have the notes play back the correct drum sound.

It is a typical use case to export your MIDI recording as a standard MIDI file. If you first perform an O-note conversion, you make sure that your drum tracks play back as intended when they are exported.

- To perform an O-note conversion, select **MIDI > O-Note Conversion**.


RELATED LINKS

[Exporting MIDI Tracks as Standard MIDI File](#) on page 157

List Editor

The **List Editor** shows all events in the selected MIDI parts as a list, allowing you to view and edit their properties numerically. It also allows you to edit SysEx messages.

- To open a MIDI part in the **List Editor**, select a MIDI part in the **Project** window and select **MIDI > Open List Editor**.



The **List Editor** is divided into several sections:

- 1 Toolbar
- 2 Status line
- 3 Event list
- 4 Filters bar
- 5 Ruler
- 6 Event display
- 7 Value display

NOTE

The filters, the status line, and the value display can be activated/deactivated by clicking **Set up Window Layout** on the toolbar and activating/deactivating the corresponding options.

Toolbar

The toolbar contains tools and various settings for the **List Editor**.

- To show or hide the toolbar elements, right-click the toolbar and activate or deactivate the elements.

Static Buttons

Solo Editor



Solos the editor during playback if the editor has the focus.

Record in Editor



Enables the recording of MIDI data in the editor if the editor has the focus.

NOTE

This only works if **MIDI Record Mode** is set to **Merge** or **Replace**.

Auto-Scroll

Auto-Scroll



Keeps the project cursor visible during playback.

Switch Auto-Scroll Settings



Allows you to specify the auto-scroll settings.

Tool Buttons

Object Selection



Allows you to select events.

Draw



Allows you to draw events.

Erase



Allows you to delete events.

Zoom



Allows you to zoom in/out. Hold **Alt** and click to zoom out.

Mute



Allows you to mute events.

Trim



Allows you to trim events.

Acoustic Feedback

Acoustic Feedback



Automatically plays back events when you move or transpose them, or when you create them by drawing.

Independent Track Loop

Independent Track Loop



Activates/Deactivates the independent track loop.

Multiple Part Controls

Show Part Borders




Shows/Hides part borders for the active MIDI part within the left and right locators.

Edit Active Part Only



Restricts editing operations to the active part.


Currently Edited Part



Lists all parts that were selected when you opened the editor, and allows you to activate a part.

Insert Type

Insert Event Type



Allows you to determine an event type for newly created events.

Insert Velocity

Insert Velocity



Allows you to specify a velocity value for new notes.

Nudge Palette

Trim Start Left



Increases the length of the selected event by moving its start to the left.

Trim Start Right



Decreases the length of the selected event by moving its start to the right.

Move Left



Moves the selected event to the left.

Move Right



Moves the selected event to the right.

Trim End Left



Decreases the length of the selected event by moving its end to the left.

Trim End Right



Increases the length of the selected event by moving its end to the right.

Snap

Snap On/Off



Activates/Deactivates the snap function.

Snap Type



Allows you to select one of the following snap types:

- **Grid**  snaps events to the grid that is selected in the **Quantize Presets** pop-up menu.
- **Grid Relative**  keeps the relative positions when snapping events to the grid.
- **Events**  snaps events to the start or end of other events.
- **Shuffle**  changes the order of events if you drag one event to the left or right of other events.
- **Magnetic Cursor**  snaps events to the cursor position.
- **Grid + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu or to the cursor position.
- **Events + Cursor**  snaps events to the start or end of other events or to the cursor position.
- **Grid + Events + Cursor**  snaps events to the quantize grid that is selected in the **Quantize Presets** pop-up menu, to the start or end of other events or to the cursor position.

Quantize

Iterative Quantize On/Off



Activates/Deactivates iterative quantize.

Quantize Presets



Allows you to select a quantize or a groove preset.

Apply Quantize



Applies the quantize settings.


Open Quantize Panel



Opens the **Quantize Panel**.

Length Quantize

Length Quantize



Allows you to set a value for quantizing event lengths.

Step/MIDI Input

Step Input



Activates/Deactivates MIDI step input.

MIDI Input/Note Expression MIDI Input



Activates/Deactivates MIDI input and note expression MIDI input.

Move Insert Mode



Moves all note events to the right of the step input position to the right to make room for the inserted event when you insert notes.

NOTE

This only works if **Step Input** is activated.

Record Pitch



Includes the pitch when you insert notes.

Record NoteOn Velocity



Includes the NoteOn velocity when you insert notes.


Record NoteOff Velocity



Includes the NoteOff velocity when you insert notes.

Event Colors

Event Colors



Allows you to select event colors.

Right Divider

Right Divider



Allows you to use the right divider. Tools that are placed to the right of the divider are always shown.

Edit VST Instrument

Edit VST Instrument



Opens the VST Instrument that the track is routed to.

Window Zone Controls

Show/Hide Right Zone



Allows you to show/hide the right zone.

Set up Window Layout



Allows you to set up the window layout.

Set up Toolbar



Opens a pop-up menu where you can set up which toolbar elements are visible.

RELATED LINKS

[Using the Setup Options](#) on page 994

Status Line

The status line is displayed below the toolbar. It displays important information about the mouse position.

To show or hide the info line, click **Set up Window Layout**  on the toolbar, and activate or deactivate **Status Line**.



The on/off status of the status line in the **List Editor** window and in the lower zone editor are independent of each other.

Mouse Time Position

Displays the exact time position of the mouse pointer, depending on the selected ruler display format. This allows you to edit or insert notes at exact positions.

Current Chord Display

When the project cursor is positioned over notes that form a chord, this chord is displayed here.

Track Loop Start/End

If **Independent Track Loop** is activated on the toolbar, its start/end position are displayed.

RELATED LINKS

[Toolbar](#) on page 753

Filters Bar

The filters bar allows you to hide events from view, based on their type and other properties.

To show or hide the status line, click **Set up Window Layout** on the toolbar, and activate or deactivate **Filters**.



Show Section

The **Show** section allows you to set up filters.

No Focus

No filter is applied.

Event Types

Only events of the same event type as the selected type will be shown. This is the same as activating event types in the **Hide** section.

Event Types and Data 1

Only events of the same event type as the selected type and with the same **Data 1** value are shown. For example, if a note event is selected, only notes with the same

pitch are shown. If a controller event is selected, only controllers of the same type are shown.

Event Channels

Only events with the same MIDI channel value as the selected event are shown.

Presets (Cubase Pro only)

Allows you to use a preset.

Setup (Cubase Pro only)

Opens the **Logical Editor**. Here you can create complex filter settings.

When you apply any of the **Logical Editor** presets or use the **Logical Editor** to create filter settings yourself, only the events that meet the specified criteria are visible.

Hide Section

The **Hide** section allows you to hide specific event types from view.

RELATED LINKS

[Filtering the Event List](#) on page 781

[Logical Editor](#) on page 860

Event List

The **Event List** lists all events in the selected MIDI parts, in the order in which they are played back from top to bottom. The list allows you to perform detailed numerical editing of the event properties.

The following options are available:

>

An arrow in this column indicates the event that starts closest before the project cursor position. You can use this column for auditioning when you are editing in the list.

- To move the cursor to the start of the event, click in the auditioning column of an event.
- To move the cursor position and start/stop playback, double-click in the column for an event.

Type

Event type. Cannot be changed.

Start

Starting position of the event, displayed in the format selected for the ruler. Changing it has the same effect as moving the event.

NOTE

If you move the event past any other event in the list, the list is resorted. The list always shows the events in the order in which they are played back.

End

Allows you to view and edit the end position of a note event. Editing resizes the note event.

Length

Displays the length of the note event. Changing this resizes the note event and automatically changes the **End** value.

Data 1

Data 1 or **Value 1** property of the event. Its content depends on the event type. For notes, this is the pitch, for example. Where applicable, the values are displayed in the most relevant form. For example, the **Data 1** value for notes is displayed as a note number in the format that was selected in the **Preferences** dialog.

Data 2

Data 2 or **Value 2** property of the event. The content of this depends on the event type. For notes, this is the note-on velocity value, for example.

Data 3

The **Data 3** or **Value 3** property of the event. This value is only used for note events, where it corresponds with the note-off velocity.

Channel

MIDI channel of the event. This setting is normally overridden by the channel setting for the track. To make a MIDI event play back on its own channel, set its track to the **Any** channel in the **Project** window.

Comment

Allows you to add comments to some event types.

Event Display

The **Event Display** displays events graphically. The vertical position of an event in the display corresponds to its entry in the list, that is, to the playback order. The horizontal position corresponds to the actual event position in the project. In the event display, you can add new parts or events, and drag events to another position.

Value Display

The value display to the right of the event display is a tool for quick viewing and editing of multiple values, for example, velocities or controller amounts. The values are shown as horizontal bars, with the bar length corresponding to the value.

To show or hide the value display, click **Set up Window Layout** on the toolbar, and activate or deactivate **Value Display**.



The value that is displayed for an event depends on the event type. The following table shows what is displayed and edited in the **Data** columns and the value display:

Event type	Data 1	Data 2	Value display
Note	Pitch (note number)	Note-on velocity	Velocity
Controller	Controller type	Controller amount	Controller amount
Program change	Program number	Not used	Program number

Event type	Data 1	Data 2	Value display
Aftertouch	Aftertouch amount	Not used	Aftertouch amount
Pitchbend	Bend amount	Not used	Bend amount
SysEx	Not used	Not used	Not used

NOTE

For note events, there is also a value in the **Data 3** column, which is used for note-off velocity.

NOTE

For SMF and text events, no values are displayed.


List Editor Operations

This section describes the principal editing operations within the **List Editor**.


Drawing Events

The **Draw** tool allows you to insert single events in the event display.

When you move the cursor inside the event display, its position is indicated on the status line. The snap function is taken into account.



- To change the event type that you want to draw, select it from the **Insert Event Type** pop-up menu.



- To draw an event, click in the event display.
The note event gets the length that is set on the **Length Quantize** pop-up menu. Notes get the insert velocity value set in the **Insert Velocity** field on the toolbar.
- To draw longer note events, click and drag in the event display.

The length of the event is a multiple of the **Length Quantize** value. If **Length Quantize** is set to **Quantize Link**, the event value is determined by the quantize grid.

Filtering the Event List

You can filter the event list with the **Filters** bar that is displayed below the toolbar in the **List Editor**.

- To filter the event list based on complex criteria, open the **Show** pop-up menu and select a filter.
- To hide an event type, activate the corresponding checkbox on the **Filters** bar.
- To hide all event types except one, press **Ctrl/Cmd** and click the checkbox of the event type that you want to view.

If you **Ctrl/Cmd**-click again, all checkboxes are cleared.

Editing in the Event List

- To edit the values of several events, select the events and edit the value for one event. The values of the other selected events are also changed. Any initial value differences between the events are maintained.
- To set the values of all selected events to the same value, press **Ctrl/Cmd** and edit the value for one event.
- For SysEx events, you can only edit the **Start** position in the list. However, when you click the **Comment** column, the **MIDI SysEx Editor** opens, in which you can perform detailed editing of system exclusive events.

NOTE

When you trim the beginning of a note in the **List Editor**, the note may move to a different position in the list, since other events may begin earlier than the edited event.

RELATED LINKS

[SysEx Messages](#) on page 782

Editing in the Event Display

The event display allows you to edit the events graphically using the tools on the toolbar. You can edit single events as well as several selected events simultaneously.

- To move an event, drag it to a new position.
Moving the event past any other event in the display resorts the list. The list always shows the events in the order in which they are played back. As a result, the vertical position of the event in the display also changes.
- To make a copy of an event, press **Alt** and drag it to a new position.
- To resize a note, select it and drag its end point with the **Object Selection** tool.
- To mute or unmute an event, click on it with the **Mute** tool.
You can mute or unmute several events simultaneously by enclosing them in a selection rectangle with the **Mute** tool.
- You can select a color scheme for the events with the **Event Colors** pop-up menu on the toolbar.
- To delete an event, select it and press **Backspace** or **Delete**, or click on it with the **Erase** tool.

RELATED LINKS

[Coloring Notes and Events](#) on page 703

Editing in the Value Display

- To edit values in the value display, click and drag.
The mouse pointer automatically takes on the shape of the **Draw** tool when you move it over the value display.

SysEx Messages

SysEx (System Exclusive) messages are model-specific messages for setting various parameters of a MIDI device. This makes it possible to address device parameters that would not be available via normal MIDI syntax.

Every major MIDI manufacturer has its own SysEx identity code. SysEx messages are typically used for transmitting patch data, for example, the numbers that make up the settings of one or more sounds in a MIDI instrument.

Cubase allows you to record and manipulate SysEx data in various ways.

RELATED LINKS

[Using MIDI devices](#) on page 679

Bulk Dumps

In any programmable device, the settings are saved as numbers in computer memory. If you change these numbers, you will change the settings. Normally, MIDI devices allow you to dump (transmit) all or some settings in the device's memory in the form of MIDI SysEx messages.

A dump is therefore, among other things, a way of making backup copies of the settings of your instrument: sending such a dump back to the MIDI device restores the settings.

If your instrument allows the dumping of a few or all of its settings via MIDI by activating some function on the front panel, this dump will probably be recordable in Cubase.

Recording a Bulk Dump

IMPORTANT

If your MIDI instrument does not offer a way to initiate a dump, you have to send a Dump Request message from Cubase to start the dump. In that case, use the **MIDI SysEx Editor** to insert the specific Dump Request message (refer to the instrument's documentation) at the beginning of a MIDI track. When you activate recording, the Dump Request message is played back (sent to the instrument), the dump starts and is recorded.

PROCEDURE

1. In the **Preferences** dialog, select **MIDI > MIDI Filter**.
2. In the **Record** section, deactivate the **SysEx** checkbox to make sure that the recording of SysEx data is not filtered.
This way, SysEx messages are recorded but not echoed back to the instrument. This can lead to unpredictable results.
3. Activate recording on a MIDI track and initiate the dump from the front panel of the instrument.
4. When you have finished recording, select the new part and select **MIDI > List Editor**.

This allows you to check that the SysEx dump was recorded. There should be one or several SysEx events in the part/event list.

Transmitting a Bulk Dump Back to a Device

PREREQUISITE

Route the MIDI track with the System Exclusive data to the device. Check your device's documentation to find details about which MIDI channel should be used, etc.

PROCEDURE

1. Solo the track.
 2. Make sure that the device is set up to receive SysEx messages.
 3. If necessary, put the device in **Standby to Receive System Exclusive** mode.
 4. Play back the data.
-

Recording and Transmitting Bulk Dumps

- Do not transmit more data than you need. If all you want is a single program, do not send all. Otherwise, it could get too difficult to find the recognized program. Usually, you can specify exactly which data you want to send.
- If you want the sequencer to dump the pertinent sounds to your instrument whenever you load a project, put the SysEx data in a silent count-in before the project itself starts.
- If the dump is very short, for example, a single sound, you can put the dump in the middle of the project to quickly re-program a device. However, you can achieve the same effect by using Program Change. This is preferable, since less MIDI data is sent and recorded. Some devices may be set up to dump the settings for a sound as soon as you select it on the front panel.
- If you create parts with useful SysEx dumps, you can put these on a special muted track. To make use of these parts, drag them to an empty unmuted track and play them back.
- Do not transmit several SysEx dumps to several instruments at the same time.
- Make a note of the current device ID setting of the instrument. If you change this, the instrument may later refuse to load the dump.

Recording SysEx Parameter Changes

Often, you can use SysEx to remotely change individual settings in a device, for example, opening a filter, selecting a waveform, changing the decay of the reverb, etc. Many devices are also capable of transmitting changes that are made on the front panel as SysEx messages. These can be recorded in Cubase, and thus incorporated into a regular MIDI recording.

For example: you open up a filter while playing some notes. In that case, you record both the notes and the SysEx messages that are generated when you open the filter. When you play back the recording, the sound changes exactly as it did when you recorded it.

PROCEDURE

1. In the **Preferences** dialog, select **MIDI > MIDI Filter** and make sure that **SysEx** is deactivated in the **Record** section.
 2. Make sure that the instrument is set to transmit changes of front panel controls as SysEx messages.
 3. Record.
-


AFTER COMPLETING THIS TASK

In the **List Editor**, check if the events were recorded properly.

MIDI SysEx Editor

While SysEx events are displayed in the **List Editor/Project Browser** (Cubase Pro only), it is not their entire content that is displayed. Only the beginning of the message is displayed in the **Comment** column for the event. The event is not editable. You can only move the event, the same way you would move it in the **List Editor**.

- To open the **MIDI SysEx Editor** for a SysEx event, click in the **Comments** column for the event in the **List Editor/Project Browser**.



The display shows the entire message on one or several lines. SysEx messages always begin with F0 and end with F7 and a number of arbitrary bytes in between. If the message contains more bytes, so that they do not entirely fit on one line, it continues on the next line. The Address indication to the left helps you find out on which position in the message a certain value is located.

You can edit all values except for the first (F0) and the last ones (F7).

In the **MIDI SysEx Editor**, the bytes are displayed as follows:

- In the main display, values are shown in hexadecimal format.
- To the right of the main display, values are shown in ASCII format.
- At the bottom of the dialog, the selected value is shown in ASCII, binary, and decimal formats.

Adding and Deleting Bytes

- To add a byte, open the **MIDI SysEx Editor** and click **Insert**. The byte is added before the selected byte.
- To delete a byte, open the **MIDI SysEx Editor**, select a byte, and click **Delete**.
- To delete the complete SysEx message, select it in the List Editor and press **Delete** or **Backspace**.

Editing Byte Values

You can edit the selected byte value in the main display of the **MIDI SysEx Editor**, or in the ASCII, decimal, and binary displays.

- To edit the selected value, open the **MIDI SysEx Editor**, click on a byte, and type in the value.

Importing and Exporting SysEx Data

You can import SysEx data from disk and export the edited data to a file.

The file has to be in MIDI SysEx (.syx) binary format. Only the first dump in a SYX file will be loaded.


- To import SysEx data, open the **MIDI SysEx Editor** and click **Import**.
- To export SysEx data, open the **MIDI SysEx Editor** and click **Export**.

NOTE

Do not confuse this format with MIDI files, which have the extension .mid.

In-Place Editor

The **In-Place Editor** allows you to edit MIDI notes and controllers directly in the **Project** window, for quick and efficient editing in context with other tracks.



The **In-Place Editor** expands the MIDI track to show a miniature **Key Editor**. When you select a MIDI note, the **Project** window info line shows the same information about the note as the info line in the **Key Editor**. You can perform the same editing here as in the **Key Editor**.

RELATED LINKS

[Editing Note Events on the Info Line](#) on page 706

Opening the In-Place Editor

- To open the **In-Place Editor** for the selected tracks, select **MIDI > Open In-Place Editor**.
- To open the **In-Place Editor** for a single MIDI track, click **Edit In-Place** in the track list.



Toolbar

The toolbar contains tools and settings for the **In-Place Editor**.

To open the toolbar, click on the triangle in the upper right corner of the track list for the edited track.



Acoustic Feedback

Acoustic Feedback



Automatically plays back events when you move or transpose them, or when you create them by drawing.


Multiple Part Controls

Edit Active Part Only



Restricts editing operations to the active part.

List of Parts in Editor



Lists all parts that were selected when you opened the editor, and allows you to activate a part.

Indicate Transpositions

Indicate Transpositions



Allows you to display the transposed pitches of MIDI notes.

Auto Select Controllers

Auto Select Controllers



Automatically selects controller data of the selected MIDI notes.

Insert Velocity


Insert Velocity



Allows you to specify a velocity value for new notes.

Length Quantize


Length Quantize



Allows you to set a value for quantizing event lengths.

Event Colors

Event Colors



Allows you to select event colors.

Transpose Palette

Move Up



Transposes the selected event up by a half note.

Move Down



Transposes the selected event down by a half note.

Move Up More



Transposes the selected event up by an octave.

Move Down More



Transposes the selected event down by an octave.

Working with the In-Place Editor

- To zoom or scroll the **In-Place Editor**, point at the left part of the piano keyboard display so that the pointer changes to a hand. Then drag to the right or left to zoom in or out vertically, and drag up or down to scroll the editor.
- To add or remove controller lanes, right-click below the controller name field and select an option from the context menu.
- To close the **In-Place Editor** for one track, click **Edit In-Place** in the track list or double-click below the controller display in the **In-Place Editor**.
- To open/close the **In-Place Editor** for one or several selected tracks, use the **Edit In-Place** key command.
- You can drag notes from one **In-Place Editor** to another.

NOTE

The **Snap** button and **Snap Type** pop-up menu on the **Project** window toolbar control snapping in the **In-Place Editor**, but the snap grid is set using the **Quantize** pop-up menu.

Expression Maps (Cubase Pro only)

Expression maps allow you to set up a map for all your articulations. This allows you to audition a project including articulations.

You can select expression maps in the **Inspector** for MIDI or instrument tracks, and specify the sound mapping and characteristics for all your articulations.

If you select an expression map for a MIDI or instrument track, the articulations defined in the map are automatically applied during playback. Cubase recognizes the expressions scored for the MIDI part and searches the sound slots in the expression map for a sound that matches the defined criteria.

When a matching sound slot is found, the current note is either modified, or the MIDI channel, program change or key switch information is sent to the instrument selected on the **Output Routing** pop-up menu for the track, so that a different sound is played. When no sound slot is found that matches the articulations used in the part, the closest match is used.

When you enter articulations in a MIDI part, you must set up an expression map in a way that the right sounds in the connected VST or MIDI instrument are triggered.

Expression maps also allow you to link your articulations with remote keys on a MIDI input device and map these to sounds that can be played by a MIDI device or VST instrument. This way, you can enter notes and articulations using a remote MIDI device and have these automatically recorded and played back correctly by Cubase.

Expression maps are useful in the following situations:

- When you want to enter musical articulations directly in the Key Editor, Drum Editor, Score Editor, or In-Place Editor, without having to record MIDI data first.
- When you want to play/record music in realtime and control articulation changes while playing.
- When you open and edit projects from other users. By using expression maps, you can map the articulation information to a different instrument set or content library quickly and easily.

Expression maps are available for MIDI and instrument tracks. You can create your own expression maps or download expression maps for orchestra libraries and virtual instruments from the Steinberg web site.

NOTE

You can also use the Note Expression functions to add musical articulations directly on your MIDI notes in the Key Editor.

RELATED LINKS

[Articulations](#) on page 789

[Creating and Editing Expression Maps](#) on page 790

[Groups](#) on page 792

[Note Expression](#) on page 800

Articulations

Musical articulations define how specific notes are sung or performed on a given instrument. They can also define the relative volume of notes or the changes in pitch.

The following articulation types are available:

- **Directions**
 Directions, such as pizzicato, are valid for all notes from their insert position, to the insert position of the next direction. They are applied to a continuous range of notes, or even an entire piece of music.
- **Attributes**
 Attributes, such as accents, or staccato, are valid for single notes.

Expression Map Setup


The **Expression Map Setup** window allows you to load, create, and set up expression maps.

Do one of the following to open the **Expression Map Setup** window:

- Select **MIDI > Expression Map Setup**.
- In the **Inspector** for a MIDI or instrument track, open the **Expression Map** section, click **Select Expression Map for the track** and select **Expression Map Setup** from the pop-up menu.

NOTE

You can also open the **Expression Map** section in the **Inspector** of the **Key Editor**, **Drum Editor** or **Score Editor**.



The following sections are available:

- 1 Expression Maps**
 Allows you to load, save, add, and remove expression maps. Loaded or added expression maps are shown in the **Maps** list.
- 2 Sound Slots**
 Shows the sound slots that correspond to the expression map that is selected in the **Expression Maps** section.

3 Output Mapping

Shows the output mapping that corresponds to the sound slot that is selected in the **Sound Slots** section.

4 Articulations

Allows you to organize articulations in groups.

5 Remote Settings

Allows you to set up remote keys for triggering articulations via a MIDI input device. Here, you can also specify if you want to use key switches or program change messages to play a certain sound slot.

RELATED LINKS

[Expression Maps \(Cubase Pro only\)](#) on page 788

[Adding Sound Slots](#) on page 791

[Output Mapping](#) on page 793

[Articulations](#) on page 789

[Remote Settings](#) on page 794

Expression Maps in the Project Window

Expression maps are available in the **Project** window, from within the **Inspector** for MIDI and instrument tracks.

- In the **Inspector** for a MIDI or instrument track, open the **Expression Map** section, click **Select Expression Map for the track** and from the pop-up menu select **Expression Map Setup**.



- 1 Indicates that an expression map is used for the track.
- 2 Shows which remote key is being pressed.
- 3 Marks the slot that is played back. This allows you to see whether the correct sound slot is used when you record articulations with an external device, such as a MIDI keyboard.

Creating and Editing Expression Maps

Creating Expression Maps

You can create expression maps from scratch.

PROCEDURE

1. In the **Inspector** for a MIDI or instrument track, open the **Expression Map** section.
2. Click **Select Expression Map for the track**.
3. From the pop-up menu, select **Expression Map Setup**.



The **Expression Map Setup** opens.

4. In the **Expression Maps** section, click + to create a new map.



5. Enter a name for the expression map.

Adding Sound Slots

You must create sound slots for each articulation that you want to add.

PREREQUISITE

The **Expression Map Setup** window is open and an expression map is selected in the **Expression Maps** section.

PROCEDURE

- Do one of the following:
 - In the **Sound Slots** section, use the first default sound slot that is added automatically when a new map is created.
 - Click **Add Sound Slot** to add a new sound slot.
- Click the articulation column **Art. 1** for the sound slot, and select an articulation from the menu.

NOTE

If a specific articulation is not available on the pop-up menu, select **Add Custom Articulation** to define your own articulations. This adds a default articulation that you can define in the **Articulations** section.

- Optional: Click the **Name** column and enter a name for the sound slot.
The names of the sound slots are displayed in the **Inspector** for the track.
- Optional: Click the articulation columns **Art. 2**, **Art. 3**, **Art. 4** for the sound slot, and select an articulation from the menu.
This allows you to create a complex articulation, made of several different single articulations for the sound slot. For each new articulation, an additional entry is added in the **Articulations** section.
- Click the **Remote** column for the sound slot and specify the key on your external device that triggers this sound slot.
- Optional: Click the **Col** column to assign a color to the sound slot.

When working in the MIDI editors, you can color your events according to the color of the sound slots.

RESULT

The sound slots are added and the articulations are available. You can create as many sound slots as you need.

If Cubase finds the sound slot, the current note is either modified, for example reduced in length or played louder, or the MIDI channel, program change or key switch information is sent to the connected instrument (the instrument selected on the **Output Routing** pop-up menu for the track), so that a different sound is played.

If no sound slot is found that matches the articulations used in the part, the closest match is used.

RELATED LINKS

[Expression Maps in the Project Window](#) on page 790

[Remote Settings](#) on page 794

Articulations

You can edit the articulations that you added for the sound slots in the **Articulations** section of the **Expression Map Setup** window.

The following settings are available:

Art.

Click this column to choose whether you want to insert the articulation as a symbol or a text string. If you select **Symbol**, a dialog with the available symbols opens. If you select **Text**, you can directly enter the desired text.

Type

Click this column to specify whether you want to add an attribute or a direction. If you select **Attribute**, only single notes are influenced by the articulation symbol. If you select **Direction**, the articulation symbol is valid from its insertion position until the next articulation start.

Description

Click this column to enter a text such as the name of the symbol or the long name of a direction.

Group

Click this column to sort articulations in groups and prioritize them.

RELATED LINKS

[Groups](#) on page 792

Groups

Groups allow you to sort the articulations in order to prioritize and combine them.

The groups themselves are exclusive. Articulations that are in the same group cannot be used together. You can place articulations that cannot be combined, such as arco (bowed) and pizzicato (plucked) for violin in the same group.


Groups represent the musical importance, with group 1 having the highest priority. This is useful if an expression map does not find an exact match for your data and tries to identify the sound which matches most criteria. If two sounds are found which have the same articulation in group 1, the sound that also matches group 2 is preferred and so on.

Output Mapping

The **Output Mapping** section allows you to map sound slots to specific sound characters of an instrument. The available sounds depend on the instrument that is selected for the MIDI or instrument track.

NOTE

Some virtual instruments require multiple key switches or combinations of key switches and controllers to select a particular articulation. In this case, click + to add multiple output events to a single sound slot.



You can make the following settings for the slots:

Status

Allows you to specify a note-on, program change, or controller message for the selected sound slot.

Data 1/Data 2

Allows you to specify key switches for the selected sound slot. This allows you to switch between a bowed and a pizzicato violin, or to switch to another program containing a different articulation.

You can also create expressions by editing the incoming MIDI data:

Channel

Allows you to specify the MIDI channel for the selected sound slot. This allows you to switch to a different program.

Length

Allows you to specify the note length for the selected sound slot. This way, you can create staccato or tenuto sounds.

Transpose

Allows you to specify a transpose value for the selected sound slot. This way, you can select different articulations in some sample libraries, in which different articulations are located on different octaves.

Velocity

Allows you to specify the velocity for the selected sound slot. This way, you can create accents.

Min. Pitch/Max. Pitch

Allows you to specify a minimum and a maximum pitch for the selected sound slot.

Min. Velocity/Max. Velocity

Allows you to specify a minimum and a maximum velocity for the selected sound slot, to make sure that the sample mapped to a particular range is used. This way, you can use instruments that have different velocity ranges on the same key.


Remote Settings

The remote settings allow you to specify key switches or program change messages to trigger specific sound slots.

NOTE

If you do not plan to record or trigger articulations via a MIDI input device, you do not need to specify remote keys.

Active remote keys are indicated in the **Inspector** for the track.



Key Switches/Program Change Messages pop-up menu

Allows you to select if you want to use **Key Switches** or **Program Change Messages** to switch sound slots.

NOTE

If you use key switches, these keys are used to insert articulations instead of notes.

Latch Mode

If this is activated, the key you press on your MIDI input device is valid until you press the next key. If this is deactivated, the key is valid for as long as you hold it. When you release it, the first sound slot is played.

IMPORTANT

Latch Mode can only be activated/deactivated globally, not for single expression maps.

Root Note

Allows you to specify the first key on your external device that you want to use as a remote key. This allows you to automatically adjust existing remote key assignments to suit your needs, for example when you use a MIDI keyboard with a very wide or very narrow key range.

Set Remote Keys

Allows you to automatically assign a range of keys on your external device to the sound slots in the expression map.


RELATED LINKS

[Expression Maps in the Project Window](#) on page 790

[Set Remote Keys](#) on page 795

Set Remote Keys

The **Set Remote Keys** dialog allows you to assign a range of keys on your external device to the sound slots in the expression map.



Start Key

Allows you to specify the first key on the MIDI input device that you want to trigger a sound slot.

Key Mapping

Allows you to specify with which keys on your device you want to trigger the sound slots.

Extracting Expression Maps from VST Instruments

You can extract mapping information from VST 3 instruments and convert it into a new expression map. This way, you can set up expression maps for the instruments you often work with.

PROCEDURE

1. Load the VST instrument that you want to use and assign it to a MIDI or instrument track.
2. Load an instrument preset that contains key switches.
Included with Cubase are several track presets that are pre-configured for use with expression maps. They contain sounds that make use of key switches and have different articulations. These presets have the suffix **VX**.
3. In the **Inspector** for the MIDI or instrument track, open the **Expression Map** section.
4. Click **Select Expression Map for the track**.



5. From the pop-up menu select **Import Key Switches**.
The **Expression Map Setup** opens.



6. Make the desired settings, enter a name for the map, and click **Save**.

RESULT

The expression map is saved and you can load it from the **Select Expression Map for the track** pop-up menu on the **Expression Map** section of the **Inspector**.

RELATED LINKS

[Creating Expression Maps](#) on page 790
[Track Presets](#) on page 179

Saving Expression Maps

If you have created and set up your expression map, you must save it.

PROCEDURE

1. In the **Expression Maps Setup** window, select the expression map in the **Expression Maps** section.
2. Click **Save**.
3. In the file dialog, specify a file name and a location for the expression map, and click **Save**.

RESULT

The expression map is saved.

Loading Expression Maps

PROCEDURE

1. In the **Inspector** for a MIDI or instrument track, open the **Expression Map** section.
2. Click **Select Expression Map for the track** and from the pop-up menu, select **Expression Map Setup**.
The **Expression Map Setup** opens.
3. In the **Expression Maps** section on the left, click **Load**.
4. In the file dialog, locate and select the expression map that you want to load, and click **Open**.

The expression map is now available in the **Expression Maps** section.

5. Repeat the steps for all the maps that you want to make available, and close the dialog.
-

RESULT

All loaded maps are available on the **Expression Map** pop-up menu in the **Inspector**.

RELATED LINKS

[Creating and Editing Expression Maps](#) on page 790

Inserting Articulations

Inserting Articulations on Controller Lanes

You can insert articulation symbols on the controller lane of the **Key Editor**, **Drum Editor**, and **In-Place Editor**.

PROCEDURE

1. Select the MIDI part.
2. Open the **Key Editor**, **Drum Editor**, or **In-Place Editor**.
3. In the controller display, open the **Controller Selection and Functions** menu and select **Articulations/Dynamics**.

All articulations that are specified for the selected expression map are shown on different rows on the controller lane. The different groups are separated by lines, and articulations that belong to the same group are shown in the same color.

4. Select the **Draw** tool, and in the controller display, click at the exact position of the first note to which you want to apply this articulation.

The note beginnings are displayed as vertical lines on the controller display.

RESULT

The attribute in the controller lane is now automatically connected to the corresponding note.

NOTE

If you delete an attribute by selecting it and pressing **Delete** or **Backspace**, the note is deleted as well. If this is not what you want, deselect the articulation in the **Articulations** field in the info line instead.

IMPORTANT

When you insert articulation symbols, make sure that they do not conflict with other articulations.

RELATED LINKS

[Inserting Articulations via the Info Line](#) on page 798

Inserting Articulations in the Score Editor

You can insert articulation symbols in the **Score Editor**.

PROCEDURE

1. Select the MIDI part.

2. Select **Scores > Open Score Editor**.
3. In the **Symbols Inspector**, open the **Expression Map** section.
4. Activate the articulation symbol, and click at the desired position in the note display.

IMPORTANT

When you insert articulation symbols, make sure that they do not conflict with other articulations.

RESULT

The articulation symbols inserted in the note display are shown in a different color so that you can distinguish them from other score symbols.



NOTE

You can view and change the colors in the **Preferences** dialog (**Score-Colors for Additional Meanings** page).

To delete an articulation symbol, select it and press **Delete** or **Backspace**.

Inserting Articulations via the Info Line

You can insert articulation symbols via the info line of the **Key Editor**, **Drum Editor**, and **Score Editor**.

PROCEDURE

1. Select a MIDI note in the event display of the **Key Editor**, **Drum Editor**, or **Score Editor**.
 2. On the info line, click **Articulations** to open a pop-up menu with all note attributes that are available in the expression map, and select the desired attribute.
-

RESULT

The name of the active attribute is now shown in the **Articulations** field.

NOTE

If you want to delete the attribute, deselect the articulation in the **Articulations** field in the info line.

IMPORTANT

When you insert articulation symbols, make sure that they do not conflict with other articulations.

RELATED LINKS

[Groups](#) on page 792

Inserting Articulations in the List Editor

You can insert articulation symbols via the comment column of the **List Editor**. This only works if your MIDI part already contains some articulation symbols.

PROCEDURE

1. Select a MIDI note in the event display of the **List Editor**.
 2. Click the **Comment** column to open a pop-up menu with all note attributes that are available in the expression map, and select the desired attribute.
-

RESULT

The name of the active attribute is now shown in the **Comment** column.

NOTE

If you want to delete the attribute, deselect the articulation in the **Comment** column.

IMPORTANT

When you insert articulation symbols, make sure that they do not conflict with other articulations.

Note Expression

Note expression allows you to show and edit controller events on MIDI note events in the event display.

Note expression associates controller events with MIDI notes, so that they are treated as a unit. When you quantize, move, copy, duplicate, or delete MIDI notes, all their associated controller information follows. This allows for a very intuitive and accurate editing of note-related data.

Controller event curves are shown as an overlay of the corresponding MIDI notes in the event display. All note expression data for a MIDI note is shown simultaneously.



To be able to record controller events in Cubase, you must assign MIDI control change messages to VST 3 controller parameters and MIDI controller parameters.

RELATED LINKS

[VST 3 Controller Parameters](#) on page 800

[MIDI Controller Parameters](#) on page 801

VST 3 Controller Parameters

VST 3 controller parameters are note-specific. They are suitable for polyphonic contexts, as they allow you to edit the articulation of each individual note in a chord.

VST 3 controller parameters are provided by VST instruments. To be able to work with VST 3 controller parameters, you need a VST instrument that supports them, such as HALion Sonic SE.

Which VST 3 controller parameters are available depends on the instrument.

VST 3 controller parameters allow for a value range that exceeds the MIDI range of 0 to 127.

RELATED LINKS

[HALion Sonic SE](#) on page 801

HALion Sonic SE

HALion Sonic SE is a VST 3-compatible VST instrument that can be used with note expression.

HALion Sonic SE offers the VST 3 parameters **Tuning**, **Volume**, and **Pan**, and it comes with several presets.

For detailed information about HALion Sonic SE and its parameters, see the separate document **HALion Sonic SE**.

MIDI Controller Parameters

MIDI controller parameters are channel-specific, with the exception of poly pressure messages. They affect the entire voice, regardless of whether they are inserted for a part or a note.

The fact that MIDI controller parameters are channel-specific limits the potential of note expression to monophonic (solo) performances. If you edit articulation data on one note, this affects all other notes of the same voice, that is, any other note playing on the same channel at the same time.

NOTE

If you want to use MIDI controller parameters in polyphonic performances, use controller lanes instead, for example in the **Key Editor**.

RELATED LINKS

[Using the Controller Display](#) on page 728


[Recording MIDI Control Change Messages as Note Expression Data](#) on page 816

[Converting MIDI Control Change Messages into Note Expression data](#) on page 817

Note Expression Inspector Section

The **Note Expression Inspector** section features most of the functions that you need to work with note expression.

The **Note Expression** section is divided as follows:



1 Section header/Bypass button

Shows the section name. The bypass button allows you to bypass all note expression data for the track.

2 Controller parameter list

Lists the available VST 3 and MIDI controller parameters.

3 Controller parameter settings

Allows you to make settings for the parameter that is selected in the controller parameter list.

4 Global settings

Allows you to make global settings for all parameters.

RELATED LINKS

[Controller Parameter List](#) on page 802


[Controller Parameter Settings](#) on page 803

[Global Settings](#) on page 804

Controller Parameter List

The controller parameter list shows VST 3 and MIDI controller parameters. Which VST 3 controller parameters are available depends on the instrument that is used. Which MIDI controller parameters are available depends on the settings in the **MIDI Controller Setup** dialog.

The following sections and functions are shown in the controller parameter list:



1 Visibility

Shows/Hides the parameter in the note expression event editor and in the event display.

2 Parameter filter

Allows you to filter the list of controller parameters.

3 MIDI CC

For VST 3 controllers, this shows the number of the MIDI control change message that is mapped to the parameter for recording.

4 VST 3 controllers

Lists the available VST 3 controller parameters.


5 MIDI controllers

Lists the available MIDI controller parameters.

Parameter Filter

You can filter the list of the available controller parameters. This allows for a better overview of the parameters in the list.

- To open the parameter filter, click the column header.



The following options are available:

Show only used Parameters

Shows only the parameters in the list for which data exists. These are marked with an asterisk (*) in front of the parameter name.

Make all Parameters visible

Shows all available parameters in the event display.

Make only edited Parameter visible

Shows only the selected parameter in the event display.

Load MIDI Input Assignment

Allows you to load mapping presets.

Save MIDI Input Assignment

Allows you to save mapping presets for a connected MIDI device.

MIDI Controller Setup

Opens a dialog that allows you to add MIDI controller parameters to the list.


RELATED LINKS

[Controller Parameter List](#) on page 802

[Controller Parameter Mapping](#) on page 805

Controller Parameter Settings

In this section, you can make settings for the controller parameter that is selected in the controller parameter list, for example, set up the MIDI assignment.



1 Color selector

Allows you to specify a color for the selected parameter.

2 MIDI assignment

Allows you to specify the MIDI controller assignment for the selected parameter.

3 MIDI Learn

Click this button and move the fader or knob on your external MIDI controller to assign the selected parameter to it.

4 Parameter range

Allows you to specify a value range that is used for the selected controller parameter.

Global Settings

The global settings apply to all parameters in the controller parameter list.



MIDI as Note Expression

Activate this to record MIDI controller events as note expression data.

Channel Rotation

Activate this to assign individual MIDI channels to incoming MIDI notes and their controller messages.

IMPORTANT

In order to use the **Channel Rotation** mode, the input controller must support channel rotation.

Overdub

Activate this to overdub existing note expression data.

Latch Buffer

Allows you to activate/deactivate the latch buffer that is used for overdub recording.

RELATED LINKS

[Channel Rotation](#) on page 807

Note Expression Tools

The note expression tools are available on the **Key Editor** toolbar.

Show Note Expression Data



Gives you a visual feedback of your actions. Use the slider to the right to adjust the display size of the note expression data in the event display.

Note Expression MIDI Input



Allows you to record note expression data via MIDI input.

Acoustic Feedback

Gives you an acoustic feedback of the controller events that are present at the mouse position while you enter or change note expression data.

Controller Parameter Mapping

Before you can record VST 3 events with external keyboards, you must map or assign specific MIDI controller messages, or pitchbend and aftertouch to the note expression parameters that you want to use.

NOTE

You can use the same MIDI controller message for several note expression parameters, but only one can be active at a time.

You can map the parameters via the **Inspector**, via **MIDI Learn** or by using a mapping preset.

RELATED LINKS

[Mapping Controller Parameters via the Inspector](#) on page 805

[Mapping Controller Parameters via MIDI Learn](#) on page 806


[Using Mapping Presets](#) on page 806

Mapping Controller Parameters via the Inspector

You can assign the knobs and faders of your MIDI instrument to note expression parameters via the **Inspector**.

PROCEDURE

1. In the controller parameter list, select the parameter to which you want to assign a MIDI controller.
2. In the **Global Settings** section, open the MIDI assignment pop-up menu and select the MIDI controller parameter that you want to map to the selected note expression parameter.



3. Optional: If the MIDI controller parameter you are looking for is not on the list, select **MIDI Controller Setup**, and activate the parameter in the dialog.
-

RESULT

You can now record note expression data using the controller messages that you just assigned. In the **CC** column in the **Inspector**, the number of the assigned MIDI controller message, or PB for pitchbend, or AT for aftertouch is shown if the mapping is active. MIDI controller messages that are assigned but inactive, are shown with a dot.

NOTE

The VST 3 parameter **Tuning** is automatically assigned to the pitchbend wheel of your MIDI controller. All other parameters are assigned by default to the first MIDI controller message, CC1: Modulation.

RELATED LINKS

[Global Settings](#) on page 804

Mapping Controller Parameters via MIDI Learn

The **MIDI Learn** function allows you to assign the knobs and faders of your MIDI device to note expression parameters.

PROCEDURE

1. In the controller parameter list, select the parameter to which you want to assign a MIDI controller.
 2. In the **Controller Settings** section, click **MIDI Learn**.
 3. On your MIDI device, use the knob or fader that you want to assign to the selected note expression parameter.
 4. Repeat this for all the parameters that you want to control with your MIDI device.
-

RESULT

You can now record note expression data using the controls on your MIDI device that you just assigned.

Using Mapping Presets

You can save your controller parameter mapping as a preset and load them later for use with the same MIDI device.

PROCEDURE

1. In the controller parameter list, click the **Parameter** column to open a pop-up menu.
 2. Select **Save MIDI Input Assignment**.
 3. In the file dialog that appears, specify a name and a location for the file.
-

RESULT

A file with the extension ***.neinput** is created.

You can load the mapping presets you created by selecting **Load MIDI Input Assignment** from the same the pop-up menu.

Recording

You can record note expression data together with MIDI notes or you can record note expression data for existing notes.

RELATED LINKS

[Recording Notes and Note Expression Data](#) on page 807

[Recording Note Expression Data by Overdubbing](#) on page 808

[Recording Note Expression Data via MIDI Input](#) on page 809

Recording and the Sustain Pedal

If you hold the sustain pedal (MIDI CC 64) of the connected MIDI device during recording, the following applies for VST 3 parameters:

- When a note-off event is received (when the key on the connected keyboard is released), this message is not sent to the VST 3 instrument but is instead created by the program when the sustain pedal is released.
This makes it possible for the VST 3 instrument to play back control change messages that are sent after a key was released.
- The release phase of the recorded notes ends when the sustain pedal is released.

NOTE

This does not apply for continuous controller messages.

Recording Notes and Note Expression Data

You can use an external MIDI device to record MIDI notes together with note expression data.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. Open the **Instrument** pop-up menu and select HALion Sonic SE, for example.
3. Click **Add Track**.
4. In the **Inspector**, open the **Note Expression** section.
5. In the controller parameter list, select a parameter.
6. In HALion Sonic SE, select a preset.

NOTE

In the **Presets** browser, enter `noteexp` in the search field of the **Results** section to show the presets that were created especially for use with note expression.

7. Map the controller parameters for recording.
 8. Use the mapped controls on your MIDI device to record MIDI notes together with note expression data.
-

RESULT

The notes are recorded together with the note expression data. If you activate **Show Note Expression Data** on the **Key Editor** toolbar, the note expression data is shown on the notes for which they were recorded.

RELATED LINKS

[Controller Parameter Mapping](#) on page 805
[Channel Rotation](#) on page 807

Channel Rotation

Some input controllers support channel rotation, that is, they can assign individual MIDI channels to incoming MIDI notes and their controller parameters.

Each new MIDI note event is assigned its own internal MIDI channel and all controller parameters that belong to this note event are created with the same MIDI channel. This allows a 16 voice polyphony, which is sufficient for most performances.

Channel rotation ensures a correct mapping of this data as note expression data per note event, and reduces the amount of data in comparison to the MIDI to note expression conversion method.

RELATED LINKS

[Global Settings](#) on page 804

Recording Note Expression Data by Overdubbing

You can record or replace note expression data for existing notes by overdubbing.

PREREQUISITE

Deselect all notes in the event display before you start overdubbing. This ensures that you record control change messages for all notes touched by the position cursor.

PROCEDURE

1. In the **Inspector**, open the **Note Expression** section, and activate **Overdub**.
2. Use the mapped controls on your MIDI device to record note expression data for the note that is playing.

RESULT

Only note expression data is recorded.

AFTER COMPLETING THIS TASK

Deactivate **Overdub** when you are done.

RELATED LINKS

[Global Settings](#) on page 804

Starting Overdub Recording at Specific Controller Values

When you record note expression data by overdubbing, you can activate a **Latch Buffer**. This is useful if you want to start recording at predefined initial knob or fader settings.

When Cubase receives controller data from an external MIDI device, the setting of the faders and knobs on the device is automatically written to the **Latch Buffer**. This data is then added to the notes during playback.

PROCEDURE

1. Map each control to one of the available VST 3 parameters.
2. Activate **Latch Buffer** and set the knobs and faders on the MIDI controller to the corresponding values.
3. Activate **Overdub**.
4. Use the mapped controls on your MIDI device to record note expression data for the note that is playing.

RESULT

The values for all controls are attached to the notes that are passed during overdub recording, and replace any existing controller data of the same type.

AFTER COMPLETING THIS TASK

Remove all values from the **Latch Buffer** by clicking **Reset Latch Buffer**.

NOTE

When you record in a cycle, the **Latch Buffer** is automatically reset at the end of the cycle.

Recording Note Expression Data via MIDI Input

You can record note expression data for existing notes using the **Note Expression MIDI Input**.

PROCEDURE

1. On the **Key Editor** toolbar, activate **MIDI Input** and **Note Expression MIDI Input**.



2. Select a note and move the active control on your MIDI device to replace the controller events for that note.
-

RESULT

The note is played in real time and incoming control change messages are recorded for it. Recording stops when the end of the note or the end of the release phase is reached, or when you deselect the note.

RELATED LINKS

[Adding Release Phases to Notes](#) on page 814

Note Expression Event Editor

The note expression event editor offers various modes for editing and adding note expression events.

- To open the note expression event editor, double-click a note in the event display.

NOTE

If you select several notes in the **Key Editor**, and you double-click any of them, the note expression event editor opens for all these notes. In this case, any editing affects all the notes that are present at the time position where you perform the editing.


- To close the editor, click in the event display.

The note expression event editor features the following controls:

- **Note Expression Controls**
These controls allow you to select parameters and add note expression events.
- **Smart Controls**
These allow you to edit the note expression events.

Note Expression Controls

The note expression event editor features the following specific note expression controls:



1 One-Shot Mode

If this is active and you click with the **Draw** tool anywhere in the editor, a fixed value is set.

NOTE

This mode is automatically activated for VST 3 parameters that are one-shot only.

2 Vertical Snap

Allows you to enter the pitch in semitone steps instead of as a continuous curve. This way, it is much easier to create fast pitch modulations. This is especially useful for the **Tuning** parameter.

NOTE

To temporarily switch to vertical snapping while editing, hold down **Shift**.

3 Horizontal Snap

This corresponds to the **Snap** button in the **Project** window.

4 Change Release Length

Allows you to add a release length to your note.

5 Parameter Range

Shows the current value at the cursor position. The value range differs depending on the parameter type.

6 Change Editor Size


Click this and drag up or down to change the size of the editor. This allows you to switch between 3 different window sizes.

7 Parameter Selection

Shows the selected parameter. Click this to open a pop-up menu with all the parameters that are used for the note. To make more parameters available, select them in the **Inspector**.

Smart Controls

The note expression event editor features the following smart controls for specific editing modes:



1 Tilt Left

If you click in the upper left corner of the editor, you can tilt the left part of the curve. This allows you to tilt the event values at the start of the curve upwards or downwards.

2 Compress Left

If you **Alt**-click in the upper left corner of the editor, you can compress or expand the left part of the curve. This allows you to compress or expand the event values at the start of the curve.

3 Scale Vertically

If you click in the middle of the upper border of the editor, you can scale the curve vertically. This allows you to raise or lower the event values of the curve in percent.

4 Move Vertically

If you click on the upper border of the editor, you can move the entire curve vertically. This allows you to raise or lower the values of the event values of the curve.

5 Compress Right

If you **Alt**-click in the upper right corner of the editor, you can compress or expand the right part of the curve. This allows you to compress or expand the event values at the end of the curve.

6 Tilt Right

If you click in the upper right corner of the editor, you can tilt the right part of the curve. This allows you to tilt the event values at the end of the curve upwards or downwards.

7 Scale Around Relative Center

If you **Alt**-click in the middle right border of the editor, you can scale the curve relative to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

8 Scale Around Absolute Center

If you click in the middle right corner of the editor, you can scale the curve absolute to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

9 Stretch

If you click on the lower border of the editor, you can stretch the curve horizontally. This allows you to move the event values of the curve to the left or to the right.

Navigation with the Note Expression Event Editor

You can navigate to the next/previous note while the note expression event editor is open.

- To navigate to the next/previous note, use the **Left Arrow/Right Arrow** keys.
- To step through the notes, press **Tab** and **Shift-Tab**.

Adding Note Expression Events

PROCEDURE

1. Double-click a note in the event display to open the note expression event editor.
 2. Do one of the following to select the parameter that you want to make settings for:
 - To create events for a parameter that has not been used yet, select the parameter in the **Inspector** to make it available in the editor.
 - To edit existing events, specify which parameter you want to edit by clicking on the curve, by selecting the corresponding parameter on the **Parameter Selection** pop-up menu, or by selecting the parameter in the **Inspector** in the **Note Expression** section.
 3. Select the **Draw** or the **Line** tool, and add note expression events for the selected note.
-

RELATED LINKS

[Adding Events in the Controller Display](#) on page 730

[Editing Events in the Controller Display](#) on page 730

Deleting Note Expression Events

PROCEDURE

1. Double-click the note that contains the note expression events you want to delete.
The note expression editor opens.
 2. Optional: Open the **Parameter** pop-up menu, and select the corresponding note expression parameter in the list.
 3. Drag a selection rectangle to select the range of note expression values that you want to delete.
 4. Select **Edit > Delete**.
-

RESULT

The selected note expression events are deleted from the note.

RELATED LINKS

[Adding Events in the Controller Display](#) on page 730

[Editing Events in the Controller Display](#) on page 730

Pasting Note Expression Events to Different Notes

You can copy all note expression events from one or more notes and paste them to one or more other notes.

PREREQUISITE

You have set up a key command for **Paste Note Expression** in the **Key Commands** dialog (**Note Expression** category).

PROCEDURE

1. Double-click the note that contains the note expression events.
The note expression editor opens.
 2. Select the note expression events that you want to copy.
 3. Select **Edit > Copy**.
 4. Select the note to which you want to paste the note expression events.
 5. Press the key command that you assigned to the **Paste Note Expression** command.
-

RESULT

All copied note expression events are pasted to the selected note.

If you copied note expression events from several source notes and pasted them to a number of destination notes, the following applies:

- If the number of the source and destination notes matches, the events of the first source note are pasted into the first destination note, the events of the second source note into the second destination note, etc.
- If the number of source notes is smaller than the number of destination notes, the source note events are pasted repeatedly into the destination notes in the order in which they appear.

When you copy the events from 2 source notes into 4 destination notes, for example, the first destination note gets the note expression events from the first source note, the second destination note the events of the second source note, the third destination note, the events of the first source note and the 4th destination note the events of the second source note.

RELATED LINKS

[Key Commands](#) on page 973

Pasting Note Expression Events to Different Parameters

You can copy note expression events from one parameter and paste them to a different parameter.

PROCEDURE

1. Double-click the note that contains the note expression events to open the note expression event editor.
2. Select the note expression events of the parameter that you want to copy.
3. Select **Edit > Copy**.
4. Select the parameter to which you want to paste the note expression events.
5. Select **Edit > Paste**.

RESULT

All copied note expression events are pasted to the selected parameter.

Repeating Note Expression Events

PROCEDURE

1. Double-click the note that contains the note expression events to open the note expression event editor.
2. Open the **Parameter** pop-up menu, and select the corresponding note expression parameter from the list.
3. Drag a selection rectangle to select the events that you want to repeat.
4. Click the selection, and with the mouse button pressed press **Alt** and drag.

RESULT

The selected events are copied.

Moving Note Expression Events

PROCEDURE

1. Double-click the note that contains the note expression events to open the note expression event editor.
2. Open the **Parameter** pop-up menu, and select the corresponding note expression parameter from the list.
3. Do one of the following:
 - Click the note expression event curve and drag to move all events.
 - Drag a selection rectangle to select events and drag to move the selected events.

NOTE

To restrict the direction to vertical or horizontal, you can press **Ctrl/Cmd** while dragging.

Adding Release Phases to Notes

You can add a release phase to a note. This allows you to work on the tail of a note which is still sounding after the note-off message was sent, for example.

PROCEDURE

1. Double-click a note in the event display to open the note expression event editor.
 2. Click and drag the **Change Release Length** control in the lower right corner of the editor to add a release phase.
-

RESULT

The release phase is added to the note.



NOTE

You can change the release phase for several notes by opening the editor for these notes, and holding down **Alt** while setting the release length.

AFTER COMPLETING THIS TASK

Add controller events in the release phase by overdubbing or by manually entering note expression events in the editor. When you overdub note expression events, the length of the existing release phase is used to associate newly recorded events to the notes.

NOTE

If you hold the sustain pedal of your external device during recording, the notes automatically get a corresponding release phase.

Trimming Note Expression Data

You can trim note expression data to automatically match the note length.

PROCEDURE

1. Select the notes that contain note expression data.
 2. Select **MIDI > Note Expression > Trim Note Expression to Note Length**.
-

RESULT

The note expression data is trimmed to the note length, and any data present after the end of the release phase is deleted.

Removing All Note Expression Data

You can delete all note expression data from the selected MIDI note or part.

PROCEDURE


1. Select the MIDI note or the MIDI part that contains the note expression data that you want to delete.
2. Select **MIDI > Note Expression > Remove Note Expression**.

RESULT

The note expression data is removed.

Note Expression MIDI Setup Dialog

The **Note Expression MIDI Setup** dialog allows you to specify exactly which MIDI messages are used every time you record MIDI control change messages as note expression data or you convert them.



- To open the **Note Expression MIDI Setup** dialog, select **MIDI > Note Expression > Note Expression MIDI Setup**.

The following options are available:

Controller

Activates MIDI control change messages. Specify the MIDI control change messages that you want to use in the list below.

NOTE

MIDI controller data for deactivated MIDI control change messages will end up on the controller lane.

Pitchbend

Activates pitchbend data.

Aftertouch

Activates aftertouch data.

Poly Pressure

Activates poly pressure data.

Controller Catch Range

Allows you to enter a controller catch range in ticks. This is useful to associate control change messages with a note, although they were sent slightly before the note-on message.

Load Default

Allows you to load the default settings.

Save as Default

Allows you to save the current settings as default settings.

Recording MIDI Control Change Messages as Note Expression Data

You can record MIDI control change messages as note expression data.

PROCEDURE

1. In the **Inspector**, open the **Note Expression** section and activate **MIDI as Note Expression**.
 2. Optional: Set the MIDI track to **Any** channel.
MIDI control change messages, with the exception of poly pressure, are channel-specific. By splitting polyphony to separate channels, you can avoid conflicting controller messages.
 3. Enter the notes and control change messages on your MIDI device.
-

RESULT

The controller data is now associated with the notes. If you copy, paste and move the notes, the associated controller data will follow.

NOTE

If you want to edit the MIDI notes after recording, you might need to consolidate the controller data.

RELATED LINKS

[Consolidating Note Expression Overlaps](#) on page 817

Converting MIDI Control Change Messages into Note Expression data

You can convert the MIDI control change messages on controller lanes into note expression data.

PREREQUISITE

The MIDI control change messages that you want to record are activated in the **Note Expression MIDI Setup** dialog. You have a MIDI part with controller data written on controller lanes.

PROCEDURE

1. Open the **Key Editor** for the MIDI part.
 2. Select **MIDI > Note Expression > Convert to Note Expression**.
-

RESULT

The MIDI control messages contained in the controller lanes are converted to note expression data, and the data on the controller lanes is deleted.

Cubase searches for notes that sound at the same time as the control change messages. If several notes play at the same time, the same note expression parameters are attributed to them, with the same values. Release phases are automatically created where necessary, so that no controller data is lost during this process.

IMPORTANT

If you want to edit the MIDI notes after the conversion, you might need to consolidate the controller data.

RELATED LINKS

[Note Expression MIDI Setup Dialog](#) on page 815

[Adding Release Phases to Notes](#) on page 814

Consolidating Note Expression Overlaps

If you move or quantize notes so that they overlap, and if these overlapping notes contain data for the same control change message, you might need to consolidate the note expression overlaps.

PROCEDURE

- Select **MIDI > Note Expression > Consolidate Note Expression Overlaps**.
-

RESULT

If the overlapping notes contain data for the same control change message, the controller values of the second note are used from the beginning of the overlap.

If a note is positioned entirely within a longer note and if these notes contain controller data for the same control change message, the controller values of the longer note are used until the encompassed note starts.

Distributing Notes to Different Channels

You can distribute notes to different channels. This allows you to use the note expression functions, even if you do not have a VST 3 instrument.

PREREQUISITE

You have added a multi-timbral instrument, and assigned the same sound to different channels.

PROCEDURE

1. In the **Inspector** for the corresponding MIDI track, open the **Channel** pop-up menu, and select **Any**.
 2. In the **Inspector**, open the **Note Expression** section.
 3. Enable **MIDI as Note Expression**.
 4. Record or enter MIDI notes with expression as needed.
 5. Select **MIDI > Note Expression > Distribute Notes to MIDI Channels**.
-

RESULT

The MIDI notes are distributed to different channels, starting at channel 1. You can now edit note expression for each note independently without conflicts.

Converting Note Expression Data to MIDI Controller Data

You can convert note expression data of MIDI controller parameters to MIDI controller data on controller lanes. Note expression data of VST 3 parameters cannot be converted.

PROCEDURE

- Select **MIDI > Note Expression > Dissolve Note Expression**.
-

RESULT

The note expression data is converted. If you open the controller display and show the controller lanes for the corresponding event type, the data is displayed.

Chord Functions

The chord functions provide you with many possibilities for working with chords.

The chord functions allow you to:

- Build chord progressions by adding chord events to the chord track.
- Convert chord events to MIDI.
- Use the chord track to control audio playback (Cubase Pro only) or MIDI playback.
- Use the chord track voicing to change the pitches of your MIDI.
- Extract chord events from MIDI data to get an overview of the harmonic structure of a MIDI file.
- Record chord events with a MIDI keyboard.

RELATED LINKS

[Chord Editing Section](#) on page 724

Chord Track

The chord track allows you to add chord events and scale events.

RELATED LINKS

[Scale Events](#) on page 827

[Chord Events](#) on page 820

Adding the Chord Track

PROCEDURE

- Select **Project > Add Track > Chord**.
-

RESULT

The chord track is added to your project.




Chord Events

Chord events are representations of chords that control or transpose playback on MIDI, instrument, and audio tracks (Cubase Pro only).

Chord events alter the pitches of MIDI notes and VariAudio segments (Cubase Pro only) if their tracks are set up to follow the chord track.

Chord events have a specific start position. Their end, however, is determined by the start of the next chord event. They can have a root note, a type, a tension, and a bass note:



- 1 Root note
- 2 Type
- 3 Tension
- 4 Bass note


RELATED LINKS

[Controlling MIDI or Audio Playback Using the Chord Track](#) on page 831

Chord Editor

The **Chord Editor** allows you to define or change chord events, and to add new chord events.

- To open the **Chord Editor**, double-click a chord event.



- 1 **Go to Previous Chord/Go to Next Chord**
Allow you to select the previous/next chord on the chord track for editing.
- 2 **Add Chord**
Adds a new undefined chord event on the chord track.

NOTE

This works only if the last chord event on the chord track is selected.

3 Chord definition buttons

Activate these buttons to define a root note, a chord type, a tension, and a bass note for your chord event.

NOTE

If you do not select a separate bass note, the setting is linked to the root note, so that no extra bass note is heard.

4 Keyboard display

Shows the notes of the chord event, considering the current voicing settings.

5 Define Chord by Text Input

Allows you to define a chord using the computer keyboard.

6 Activate MIDI Input

Allows you to define a chord by playing a chord on your MIDI keyboard. If the chord is recognized, it is reflected by the chord buttons and the keyboard display.

Adding Chord Events

PREREQUISITE

Add the chord track.

PROCEDURE

1. Select the **Draw** tool and click in the chord track.
An undefined chord event named X is added.
 2. Select the **Object Selection** tool and double-click the chord event.
 3. In the **Editor**, select a root note.
 4. Optional: Select a chord type, tension, and bass note.
 5. Do one of the following:
 - To close the **Editor**, click anywhere outside the **Editor**.
 - To add a new undefined chord event, click **Add Chord**.
-

RELATED LINKS

[Adding the Chord Track](#) on page 819

Defining Chords By Text Input

In the chord **Editor**, you can use the text input field to define a chord with the computer keyboard.

PROCEDURE

1. Double-click a chord event to open the chord **Editor**.
2. Click in the text input field at the bottom of the **Editor**.
3. Enter a chord by performing the following actions:
 - Define a root note, for example, C, D, E.
 - Define accidentals, for example, # or b.
 - Define the chord type, for example maj, min, dim, sus, or aug.
 - Define a chord extension, for example 7, 9, or 13.

NOTE

If you have activated **Solfège** in the **Note Name** pop-up menu in the **Preferences** dialog (**Event Display—Chords** page), you can also enter chords in this format. You must capitalize the first letter and write “Re” instead of “re”, for example. Otherwise, the chord is not recognized.

4. Press **Tab** to add a new chord and define it.

Chord Assistant

The **Chord Assistant** allows you to use a chord as a starting point to get suggestions for the next chord.

- To open the **Chord Assistant**, in the **Chord Editor**, click **Chord Assistant**.




The **Chord Assistant** has the following modes:

- List
- Proximity
- Circle of Fifths

Chord Assistant – List (Cubase Pro only)

The **List** mode of the **Chord Assistant** allows you to create harmonic chord progressions based on harmonic rules that can be more or less complex.



1 Go to Previous Chord/Go to Next Chord

Allow you to select the previous/next chord on the chord track for editing.

2 Add Chord

Adds a new undefined chord event on the chord track.

NOTE

This works only if the last chord event on the chord track is selected.

3 Suggestions

Shows suggestions for the next chord. Click a chord suggestion to select it.

4 Complexity Filter

Allows you to increase the complexity and thus the number of suggestions. The higher the complexity, the more suggestions you get.

5 Gap Mode

Activate this button to get suggestions for the chords in between 2 defined chords based on the previous and the next chord.

Deactivate this button to get suggestions for the next chord based on the previous chord.

NOTE

For this to work you must select all undefined chords in between 2 defined chords.

6 Algorithm Mode

Select **Cadence** to build up a chord progression based on cadences. Select **Common Notes** to build up a progression by specifying how many common notes the chords should share.

7 Cadence Type

NOTE

This option is only available if you selected **Cadence** as **Algorithm Mode**.

Allows you to select a cadence type for the suggestions. This way, only the chords with specific harmonic functions are suggested.


8 Chord Assistant tabs

Click the tabs to open one of the chord assistant modes.

Chord Assistant – Proximity (Cubase Pro only)

The **Proximity** mode of the **Chord Assistant** takes a set of harmonic rules into account to offer suggestions that match the origin chord.

If you open the **Chord Assistant** for a chord event, the previous event is set as origin chord. This is shown in the bottom center of the **Chord Assistant**. The further away a suggestion is situated from the origin chord in the graphic, the more complex the suggestion. The suggested chords are triads or 4-note chords.



- To assign a chord to the selected chord event and play it, click it. The last 3 suggested chords that you clicked are shown with a highlighted border.

NOTE

- If you move the mouse pointer over one of the suggestions in the **Chord Assistant**, a tooltip with suggestions for progressions is shown.
- The **Proximity** mode underlies the same rules as the **List** mode.

Adding Chord Events Based on Suggestions (Cubase Pro only)


If you do not know what your chord progression should look like, you can use the **Chord Assistant** to get suggestions for the following chords.

PREREQUISITE

Add a chord event on the chord track.

PROCEDURE

1. Double-click the chord event.
2. Click **Chord Assistant**.
3. Click **Add Chord**.
4. Do one of the following:
 - To display the suggestions in a list, click the **List** tab.



- To play a chord and assign it to the selected chord event, click it. The last 3 chords that you clicked are shown with a highlighted border.
- To define a new key, right-click the chord in the **Chord Assistant** and select **Use as Origin**, or use the **Rotate Left/Rotate Right** controls.
- To select the parallel minor chord and define it as key, click **Major/Minor**.

Auditioning Chord Events


To hear the chord events on the chord track, you must connect the chord track to the output of an instrument or a MIDI track.

PREREQUISITE

Add the chord track and some chord events.

PROCEDURE

1. Do one of the following:
 - To add an instrument track, select **Project > Add Track > Instrument**.
 - To add a MIDI track, select **Project > Add Track > MIDI**.
2. Assign a VST instrument to your instrument or MIDI track and select a sound.
3. In the chord track **Inspector**, activate **Acoustic Feedback**.
4. From the **Select Track for Auditioning** pop-up menu, select the track that you want to use for auditioning.



RESULT

The chord events on the chord track now trigger the sound of the assigned instrument on the MIDI or instrument track.

Changing How Chord Events Are Displayed

You can change how chord events are displayed. This is useful if chord events overlap each other at low zoom levels or if you do not like the font type.

PROCEDURE

1. On the chord track, activate **Resolve Display Conflicts**.




2. In the **Preferences** dialog, select **Event Display > Chords**, and set up the chord font. Here you can also determine the note name and naming format.

Scale Events

Scale events inform you which chord events fit in a specific sequence of notes that belong to a specific root note.

Cubase automatically creates scale events for your chord events.

- To show the scale events, activate **Show Scales** on the chord track.



- To audition the notes that belong to a scale event, click it.

However, you can also add and edit scale events manually.

Scale events have a specific start position. Their end is determined by the start of the next scale event.

Editing Scale Events

PREREQUISITE

Add the chord track and chord events. Deactivate **Automatic Scales** in the chord track **Inspector**.

PROCEDURE

1. On the chord track, activate **Show Scales**.
The scale lane is displayed.
2. Select the chord event.
A scale event is shown on the scale lane.
3. Do one of the following:
 - Click the first scale event on the chord track, and on the info line, select a **Root Key** and **Type**.

Start	Root Key	Type
1. 1. 1. 0	G	maj

- Double-click the scale event, and in the keyboard that appears, select a **Root Key** and **Type** of the scale.



The keys that correspond to the scale are highlighted.

Voicings

Voicings determine how chord events are set up. They define the vertical spacing and order of the pitches in a chord, but also the instrumentation and genre of a musical piece.

For example, a C chord can be spread over a wide range of pitches, and a pianist will choose different notes than a guitarist. The pianist may also play completely different pitches for different musical genres.


- You can set up voicing for the entire chord track in the chord track **Inspector**.
- You can set up voicings for individual chord events on the **Voicing** pop-up menu on the info line.

NOTE

If **Adaptive Voicings** is activated in the chord track **Inspector**, you can only change the voicings for the first chord event on the info line.

Setting up Voicings

To set up voicings for the entire chord track, you can use the chord track **Inspector**.



- 1 Voicing library**
Allows you to select **Guitar**, **Piano**, or **Basic** as a voicing library.
- 2 Voicing library subset**

NOTE

This is only available if **Guitar** or **Piano** is set as voicing library.

- Allows you to select a preset voicing library subset.
- 3 Configure voicing parameters**
Allows you to configure your own voicing parameters for a specific voicing scheme.
- 4 Adaptive Voicings**
Activate this to let Cubase set the voicings automatically. This prevents the individual voices from jumping too much.

5 Automatic Scales

Activate this to let Cubase set the scales automatically.

6 Mapping Offset

If you enter a negative number of ticks, the chord events will affect the MIDI notes that have been triggered too early.

Configure Voicing Parameters

If you click **Configure voicing parameters** in the **Voicings** section of the **Inspector**, you can configure your own voicing parameters for a specific voicing scheme.

NOTE

The **Start Voicing** section for piano, guitar, and basic voicings allows you to select a start voicing. This is only available for MIDI, instrument, and audio tracks, but not for the chord track, and only if you select **Voicings** in the **Follow Chord Track** pop-up menu.

In the **Style** section for **Piano** voicings, you can set up the following parameters:

Triads

Sets a triad. Chords with more than 3 notes are not changed.

Triads with maj9

Sets a triad with a major ninth, but without root note. Chords with more than 3 notes are not changed.

Triads with maj9 and min9

Sets a triad with a major and a minor ninth, but without root note. Chords with more than 3 notes are not changed.

4-note chords

Sets a 4-note chord without root note. Chords with less than 3 notes are not changed.

4-note chords (Open Jazz)

Sets a 4-note chord without root note and without fifth. Chords with less than 3 notes are not changed.

5-note chords

Sets a 5-note chord with a ninth. Chords with less than 4 notes are not changed.

In the **Options** section for **Piano** voicings, you can set up the following parameters:

Add Root Note

Adds a root note.

Duplicate Root

Duplicates the root note.

Fatten up

Duplicates the tenor.

In the **Voicing Range** section for **Piano** voicings, you can set up the following parameters:

Lowest Root Note

Sets the limit for the lowest root note.

Lowest Note

Sets the limit for the lowest note, except the root note.

Highest Note

Sets the limit for the highest note, except the root note.

In the **Style** section for **Guitar** voicings, you can set up the following parameters:

Triads

Sets a triad with 4, 5 or 6 voices.

4-note chords

Sets a 4-note chord with 4, 5 or 6 voices without tensions.

3-string triads

Sets a 3-string triad.

Modern Jazz

Sets 4-note, 5-note, and 6-note chords, partly without root note, but with tensions.

For **Basic** voicings only **Octave Offset from C3** is available. This allows you to determine an offset value for the octave range.

Converting Chord Events to MIDI

You can convert chord events to MIDI for further editing or for printing a lead sheet in the **Score Editor**.

PROCEDURE

1. Add an instrument track or a MIDI track.
 - To add an instrument track, select **Project > Add Track > Instrument**.
 - To add a MIDI track, select **Project > Add Track > MIDI**.
2. Do one of the following:
 - To convert all chord events to MIDI, select **Project > Chord Track > Chords to MIDI**.
 - To convert only selected chords to MIDI, select the chord events and drag them to the MIDI or instrument track.

RESULT

A new MIDI part is created, containing the chords as MIDI events.

Assigning Chord Events to MIDI Effects or VST Instruments

PREREQUISITE

Create a chord progression on the chord track and add a MIDI or instrument track to your project.

PROCEDURE

1. In the **Inspector** for the MIDI or instrument track, open the **MIDI Inserts** section.
2. Click an insert slot and select **Chorder** from the **Effect Type** pop-up menu.
The **Chorder** effect is activated, and its control panel opens.
3. On the chord track, select the chord events and drag them to the **Chorder** control panel.
The drop position determines the velocity area and the position of the first chord event. All subsequent chord events are mapped chromatically. Chord events with more than one occurrence are only assigned once.
To remap the chords, hold down **Alt** and drag again.

4. On your MIDI keyboard, hit the corresponding keys to play back the chords.
-

Assigning Chord Events to HALion Sonic SE Pads

PREREQUISITE

Create a chord progression on the chord track and add an instrument track with HALion Sonic SE as VST instrument to your project.

PROCEDURE

1. On the chord track, select the chord events and drag them to the HALion Sonic SE pads. The first chord event is mapped to the pad where you dropped it and all subsequent chord events are mapped to the following pads.
 2. Click the corresponding pads on the HALion Sonic SE keyboard to trigger the chords.
-

Controlling MIDI or Audio Playback Using the Chord Track

You can use the chord track to control audio playback (Cubase Pro only) or MIDI playback.

Using Live Transform

Live Transform allows you to transpose the MIDI input live to a chord progression on the chord track. This way, you do not have to worry about what key you hit on your MIDI keyboard as the MIDI input is transposed to match chords or scales on your chord track in real time.

PROCEDURE

1. Create a MIDI or an instrument track and activate **Record Enable**.
 2. In the **Inspector**, open the **Chords** section.
 3. Open the **Live Transform** pop-up menu and do one of the following:
 - To map the MIDI input to chord events, select **Chords**.
 - To map the MIDI input to scale events, select **Scales**.
 4. Hit some keys on your MIDI keyboard or on the **On-Screen Keyboard**.
-

RESULT

Any key that you hit is mapped in real time to the chord or scale events on the chord track.

Using Follow Chord Track

This allows you to match an existing recording to a chord progression on the chord track.

PROCEDURE

1. Select the track that you want to match to the chord track.
2. In the **Inspector**, click **Chords**.
3. Open the **Follow Chord Track** pop-up menu and select a mode.

NOTE

If this is the first time that you open this pop-up menu for the track, the **Follow Chord Track** dialog opens.

4. In the **Follow Chord Track** dialog, make your settings.

5. Click **OK**.

RESULT

The events on your track now match the chord progression on the chord track.

NOTE

If you matched your MIDI track to the chord track, some of the original MIDI notes may be muted. To hide these notes in the editors, activate **Hide Muted Notes in Editors** in the **Preferences** dialog (**Editing—Chords** page).


RELATED LINKS

[Follow Chord Track Dialog](#) on page 833

[Follow Chord Track Modes](#) on page 832

Follow Chord Track Modes

This section of the **Inspector** allows you to determine how your track follows the chord track.



The following options are available on the **Follow Chord Track** pop-up menu:

Off

Follow Chord Track is deactivated.

Chords & Scales

This maintains the intervals of the original chord or scale as far as possible.

Chords

This transposes MIDI notes to match the key note and maps them to the current chord.

Scales

This transposes MIDI notes to match the current scale. This allows a bigger variety of notes and a more natural performance.

Root Notes

This transposes MIDI notes to match the root note of the chord event. The effect corresponds to using the transpose track. This option is suitable for bass tracks.

Voicings

This transposes MIDI notes to match the voices of the selected voicing library.

Single Voice

Maps MIDI notes and VariAudio segments (Cubase Pro only) to the notes of a single voice (soprano, tenor, bass, etc.) of the voicing. Use the pop-up menu below to select the desired voice.

NOTE


If you apply this mode to a selection of tracks that contain separate voices, you can set up one track as master and the others as voicing slaves. This way, you can change the voicing of the master and the slaves will follow automatically.

RELATED LINKS

[Assigning Voices to Notes](#) on page 834

Follow Chord Track Dialog

This dialog opens the first time that you select an option from the **Follow Chord Track** pop-up menu on the **Chords** section of the **Inspector**.



Follow Directly

Activate this if your VariAudio segments (Cubase Pro only) or MIDI notes are already in accordance with the chord track. This is the case if you extracted your chords from the MIDI events on the track by selecting **Project > Chord Track > Create Chord Symbols**, for example.

Synchronize Track Data with Chord Track First

Activate **Analyze Chords** if the track data has nothing in common with the chord events. This analyzes the MIDI events and matches the found chords to the chord track. This is only available for MIDI.

Activate **Apply a Known Chord** if the track data has nothing in common with the chord events and if there are no chord changes. Specify **Root Note** and **Chord Type** of your events.

Using Map to Chord Track

This allows you to match individual parts or events to a chord progression on the chord track.

PROCEDURE

1. In the **Project** window, select the events or parts that you want to map to the chord track.
2. Select **Project > Chord Track > Map to Chord Track**.
3. From the **Mapping Mode** pop-up menu, select a mapping mode.

NOTE

If you select **Voicings** and no voices are found, **Auto** mode is used instead.

4. Click **OK**.
-

RESULT

The chords and scales of each event or part are analyzed and used for mapping. If no chords are found, Cubase assumes that the performance is in "C". The available mapping modes and voicings correspond to the **Follow Chord Track** parameters in the **Chords** section of the **Inspector**.

RELATED LINKS

[Follow Chord Track Modes](#) on page 832

Assigning Voices to Notes


You can transpose MIDI notes to match the voices of a selected voicing library.

PROCEDURE

- Select **Project > Chord Track > Assign Voices to Notes**.

RESULT

The note pitches now match the voicing of the chord track and you can still edit the MIDI notes. If you now select a note in the **Key Editor**, you see that **Voice** on the info line is assigned.



Extracting Chord Events from MIDI

You can extract chords from MIDI notes, parts, or tracks. This is useful if you have a MIDI file and want to show its harmonic structure, and use this file as starting point for further experimenting.

PREREQUISITE

Add the chord track and create MIDI notes that can be interpreted as chords. Drums, monophonic bass, or lead tracks are not suitable.

PROCEDURE

1. In the **Project** window, select a part or one or several MIDI tracks.
You can also select the MIDI tracks, parts, or notes that you want to extract in the **Key Editor**, **Score Editor**, or **In-Place Editor**.
2. Select **Project > Chord Track > Create Chord Symbols**.
3. Make your settings and click **OK**.

RESULT

The chord events are added on the chord track.

NOTE


Cubase Pro only: You can now open the **Chord Assistant** to create variations.

RELATED LINKS

[Create Chord Symbols Dialog](#) on page 835

Create Chord Symbols Dialog

This dialog allows you to determine, which MIDI data should be taken into account when extracting chord events from MIDI.



Include Bass Notes

Activate this if you want your chord events to contain a bass note.

Include Tensions

Activate this if you want your chord events to contain tensions.

Detect Arpeggios

Activate this if you want your chord events to contain arpeggiated chords, that is, chords whose notes are played one after another instead of all at once.

Interpret Sustain Pedal

Activate this if you want your chord events to contain sustain pedal chords, that is, notes that are played while the sustain pedal is held.

Ignore Notes Shorter Than

Allows you to determine the minimum length of the MIDI events that are taken into account.

Recording Chord Events with a MIDI Keyboard

You can use a MIDI keyboard to record chord events on the chord track.

PREREQUISITE

Your project contains an instrument track with **Record Enable** or **Monitor** activated.

PROCEDURE

1. On the chord track, activate **Record Enable**.
 2. On the **Transport Panel**, activate **Record**.
 3. Play some chords on your MIDI keyboard.
-

RESULT

All recognized chords are recorded as chord events on the chord track.

NOTE

The chord track uses its own voicing settings. The recorded chord events may therefore sound different.

RELATED LINKS

[Creating Events from Chord Pads](#) on page 858

Chord Pads

Chord pads allow you to play with chords, and to change their voicings and tensions. In terms of harmonies and rhythms, they allow for a more playful and spontaneous approach to composition than the chord track functions.

You can:

- Perform with chords in real time via a MIDI keyboard.
- Record your performance as MIDI events on a MIDI or instrument track or even on the chord track.

NOTE

We assume that you have a MIDI keyboard connected and set up.

RELATED LINKS

[Voicings](#) on page 828

Chord Pads


The chord pads in the lower zone of the **Project** window hold all functions that you need to work with chord pads.

To open the chord pads, select **Project > Chord Pads**.

NOTE

You can also select a MIDI or instrument track, and in the Inspector, open the **Chords** section and activate **Show/Hide Chord Pads Zone**.

The chord pads hold the following controls:



- 1 Current Player**
Shows the current player and opens a menu where you can select another player.
- 2 Current Mode**
Shows the current player mode and opens a menu where you can select another player mode.
- 3 Chord Pad**
Each chord pad can contain a chord symbol. To change it, click the **Open Editor** control on the left edge of the chord pad.
- 4 Keyboard**
Shows which keys are played when you trigger a chord pad. To zoom the keyboard, click a key and drag up or down. To scroll the keyboard, click and drag to the left or to the right.
- 5 Pads Remote Range**
The keys highlighted in blue on the keyboard correspond to the keys on your MIDI keyboard that trigger the chord pads. You can define the remote range on the **Remote Control** page of the chord pad **Settings**.
- 6 Remote Range for Voicings/Tensions/Transpose**
The keys highlighted in green on the keyboard display correspond to the keys on your MIDI keyboard that change the voicings, tensions, and transpose settings of the pads. You can activate and define these remote keys on the **Remote Control** page of the chord pad **Settings**.
- 7 Section Remote Range**
The keys highlighted in brown on the keyboard correspond to the keys on your MIDI keyboard that trigger the sections.
- 8 Activate/Deactivate Remote Control for Chord Pads**
Allows you to activate/deactivate the chord pads. If you deactivate remote control for chord pads, your MIDI keyboard no longer triggers the pads.
- 9 Functions Menu**
Opens a menu with specific functions and settings for the chord pads.
- 10 Chord Pads Presets**
Allows you to save and load presets for chord pads and players.
- 11 Show/Hide Chord Assistant**
Shows/Hides the **Chord Assistant** window that shows suggestions of chords that match the chord that you specified as the origin chord.
- 12 Show/Hide Settings**
Shows/Hides the chord settings, where you can configure different players, the pad layout, and the remote assignment.

RELATED LINKS

[Chord Pad Settings – Remote Control](#) on page 848


[Players and Voicings](#) on page 855

[Opening Chord Pads](#) on page 62

Chord Pad Controls

The chord pad controls allow you to edit the chord pads.

- To show the chord pad controls, move the mouse over a chord pad.



1 Open Editor

Opens the chord editor that allows you to select a chord for the chord pad.

2 Voicing Indicators

Shows the voicing used for the chord. Voicing indicators can only be displayed if the horizontal zoom level for the chord pads is high enough.

3 Adaptive Voicing Reference/Use X as Origin for Chord Assistant

When the active chord pad is set as adaptive voicing reference, its borders are shown in yellow. All other chord pads will follow its voicing and are set in a way that they do not get too far away from the reference.

If the chord pad is set as origin for the **Chord Assistant** window, its borders are shown in blue. This chord pad is used as a basis for the suggestions in the **Chord Assistant** window.

4 Assigned Chord

Shows the chord symbol that is assigned to the chord pad. Each chord pad can contain one chord symbol. If the name of the assigned chord is too long to display it on the chord pad, it is underlined, and the full chord name is shown in a tooltip.

5 AV (Adaptive Voicing)/L (Lock)

All chord pads follow the adaptive voicing. This is indicated by an AV symbol. If you change the voicing for a pad manually, however, adaptive voicing is deactivated.

An L symbol indicates that the chord pad is locked for editing.

6 Voicing

Allows you to set another voicing for the chord pad.

7 Tensions

Allows you to add/remove tensions for the chord.

Chord Pad Context Menu

- **Use X as Origin for Chord Assistant**

Sets the chord of the current pad as an origin chord for the chord assistant.

- **Assign Pad from MIDI Input**

Allows you to assign a chord by pressing keys on your MIDI keyboard.

- **Lock**

Allows you to lock a chord pad for editing.

- **Adaptive Voicing**

All chord pads follow the adaptive voicing. This is indicated by a check mark. If you change the voicing for a pad manually, adaptive voicing is deactivated.


- **Adaptive Voicings Reference**

Sets the current pad as adaptive voicing reference. If set, the automatic voicings for the following pads will be set in a way that they do not get too far away from the reference voicing. Only one pad can be set as adaptive voicing reference.

- **Unassign Pad**

Removes the chord assignment from the current pad.

Functions Menu



- **Show Voicing Indicators**
Allows you to activate/deactivate the voicing indicators that can be displayed at the bottom of each chord pad.
- **Assign Pads from Chord Track**
Assigns the chord events from the chord track to the chord pads in the same order as they appear on the chord track. Chord events that have more than one occurrence are only assigned once.
- **Snap Playback to Musical Grid**
Allows you to delay the playback of a triggered chord pad to the next defined musical position. This is useful if you work with an arpeggiator or with the Pattern Player.
- **Transpose All Pads**
Transposes all chord pads by a defined transpose value.
- **Lock All Pads**
Locks all chord pads for editing.
- **Unlock All Pads**
Unlocks all chord pads.
- **Unassign All Pads**
Removes the chord assignment from all pads.

Preparations

Before you can start working with the chord pads, you must add a MIDI or an instrument track with an instrument loaded, and open the chord pads.

PREREQUISITE


You have installed and set up a MIDI keyboard.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. In the **Add Instrument Track** dialog, select an instrument, and click **Add Track**.
3. On the instrument track, click **Record Enable**.
4. Select **Project > Chord Pads** to open the **Chord Pads**.

RESULT

You can now click the chord pads or press some of the assigned keys on your MIDI keyboard to trigger the preassigned chords.



- To play a suggested chord, click it.
The last 3 suggested chords that you clicked are shown with a highlighted border.
- To assign a suggestion to the next unassigned chord pad, right-click the suggested chord and select **Assign to Pad**.
You can also drag the suggested chord and drop it on a chord pad.
- To assign a suggestion to the next unassigned chord pad and use this chord as origin for further suggestions, right-click the suggested chord and select **Assign to Pad and Use as Origin**.

NOTE

The **Proximity** mode is a different representation of the list in the **Chord Assistant** window for the chord track.

RELATED LINKS

[Chord Assistant – List \(Cubase Pro only\)](#) on page 822


Chord Assistant – Circle of Fifths Mode

The **Circle of Fifths** mode of the **Chord Assistant** window shows the chords in an interactive visualization of the circle of fifths.

The origin chord that defines the current key is shown in the center of the **Chord Assistant** window. The tonic (I) of that key is displayed above the center. The outer circle shows the twelve major chords ordered in intervals of fifths.

The inner circle displays the corresponding parallel minor chords.

The roman numerals mark the chords of the current key with their scale degree. You can use these chords to create typical chord progressions. However, you can also use the other chords for more creative results.



- To play a chord, click it.
The last 3 chords that you clicked are shown with a highlighted border.
- To assign a chord to the next unassigned chord pad, right-click the suggested chord and select **Assign to Pad**.
You can also drag the suggested chord and drop it on a chord pad.
- To assign a suggestion to the next unassigned chord pad and use this chord as origin, right-click the chord and select **Assign to Pad and Use as Origin**.

NOTE

The **Circle of Fifths** is also available in the **Chord Assistant** window for the chord track.

RELATED LINKS

[Chord Assistant – List \(Cubase Pro only\)](#) on page 822

Assigning Chords to Chord Pads

Some chords are preassigned to the chord pads. But you can also assign your own chords.

To assign chords to chord pads, you can use:

- The chord **Editor** window
- The **Chord Assistant – Proximity** window
- The **Chord Assistant – Circle of Fifths** window
- Your MIDI keyboard
- The chord events from the chord track

Unassigning Chord Pads

You can clear all chord pads to start from scratch.

PROCEDURE

- To the left of the chord pads, open the **Functions Menu** and select **Unassign All Pads**.
-

Assigning Chords with the Chord Editor

If you know exactly which chord you want to assign to a specific chord pad, you can use the chord editor.

PROCEDURE


1. Move the mouse pointer to the left edge of the chord pad, and click **Open Editor**.
 2. In the chord **Editor** window, use the chord definition buttons to define a root note, a chord type, a tension, and a bass note.
The new chord is triggered automatically to give an acoustic feedback.
-

Assigning Chords with the Chord Assistant – Proximity Mode (Cubase Pro only)

If you have a chord that you want to use as a starting point to find follow-on chords, you can use the **Chord Assistant – Proximity** window.

PROCEDURE

1. Right-click the chord pad that you want to use as a starting point and activate **Use X as Origin for Chord Assistant**.



The **Chord Assistant** window opens, and the borders of the chord pad change their color to indicate that the assigned chord is now used as origin.

2. In the **Chord Assistant** window, click the chord symbols to trigger corresponding chords. The farther away the chord is from the origin chord that is regarded as the tonal center, the more complex the suggestion becomes.
3. To assign a chord, drag it from the **Chord Assistant** window and drop it on a chord pad.

NOTE

If one of the next chord pads is free, you can also right-click the chord in the **Chord Assistant** window and select **Assign to Pad**. This assigns the chord to the next free pad.

RELATED LINKS


[Chord Assistant – List \(Cubase Pro only\)](#) on page 822

Assigning Chords with the Chord Assistant – Circle of Fifths Mode

If you have a chord that you want to use as a starting point for a chord progression, but you do not know how to create such a progression, you can use the **Chord Assistant – Circle of Fifths** window.

PROCEDURE

1. Right-click the chord pad that you want to use as a starting point and activate **Use X as Origin for Chord Assistant**.



The **Chord Assistant** window opens, and the borders of the chord pad change their color to indicate that the assigned chord is now used as origin.

2. Click **5th** to switch to the circle of fifths mode.
The origin chord is displayed in the center, and the chords that belong to the scale are shown above it. The numerals indicate the scale degree of the chords. These help you to create chord progressions.
3. In the **Chord Assistant** window, click the chord symbols to trigger the corresponding chords.
4. To assign a chord, drag it from the **Chord Assistant** window and drop it on the chord pad.

NOTE

If one of the next chord pads is free, you can also right-click the chord in the **Chord Assistant** window and select **Assign to Pad**. This assigns the chord to the next free pad.

Assigning Chords with the MIDI Keyboard

If you know which chord you want to assign to a specific chord pad, you can use a MIDI keyboard.

PREREQUISITE

You have selected a MIDI track or an instrument track.

PROCEDURE

1. Right-click the chord pad that you want to use for the new chord, and select **Assign Pad from MIDI Input**.
The borders of the chord pad change their color to indicate that it is now ready for recording.
2. On your MIDI keyboard, press the keys for the chord that you want to assign.

The chord and its voicing is assigned to the chord pad, and you hear an acoustic feedback of the chord.

NOTE

The assigned voicing can be changed by the **Adaptive Voicing** setting. Therefore, if you want to keep the voicing for that specific pad, right-click the chord pad and select **Lock** from the context menu.

RELATED LINKS

[Adaptive Voicing](#) on page 855

Assigning Chords from the Chord Track

You can assign the chord events from the chord track to the chord pads.

PROCEDURE

- To the left of the chord pads, click the **Functions Menu** button, and select **Assign Pads from Chord Track**.
If chords are already assigned to the chord pads, a warning message informs you that all previous assignments will be overwritten.

RESULT

The chord events are assigned to the chord pads in the same order as they appear on the chord track.

NOTE

Chord events that have more than one occurrence on the chord track are only assigned once.

Moving and Copying Chord Pads

You can swap the chord assignments between 2 pads or copy a specific chord and its settings from one pad to another.

- To swap the chord pad assignment between 2 pads, click a chord pad and drag it to another chord pad.
While you drag, the border of the destination chord pad changes its color. When you drop the pad on another, the chord assignments are swapped.
- To copy the chord assignment of one chord pad to another pad, **Alt**-click a chord pad and drag it to another chord pad.
While you drag, the border of the destination chord pad changes its color. When you drop the pad on another, the first pad's assignment is copied to the destination chord pad.

NOTE

When you move or copy chord pads, the chord is moved or copied together with its settings, except for the Adaptive Voicings Reference.

Playing Back and Recording Chords

Playing Back Chord Pads with your MIDI Keyboard

PREREQUISITE

You have connected and set up a MIDI keyboard.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. In the **Add Instrument Track** dialog, select a VST instrument.
3. Click **Add Track**.
An instrument track with the selected VST instrument is added to your project.
4. On the instrument track, click **Record Enable**.
5. Select **Project > Chord Pads** to open the **Chord Pads** at the bottom of the **Project** window.
6. Press some keys on your MIDI keyboard to trigger the chords that are preassigned to the chord pads.

RELATED LINKS

[Chord Pad Settings – Remote Control](#) on page 848
[Changing the Pads Remote Range](#) on page 852

Recording Chords on MIDI or Instrument Tracks

You can record the chords that are triggered through the chord pads on MIDI or instrument tracks. This way, you can play back and edit your performance at any time.

PREREQUISITE

You have connected and set up a MIDI keyboard, you have opened and set up the chord pads, and you have added an instrument or a MIDI track for which a VST instrument is loaded to your project.

PROCEDURE

1. On the instrument track, click **Record Enable**.
2. On the **Transport** panel, activate **Record**.
3. On your MIDI keyboard, press the keys that trigger the chord pads.

NOTE

Use the keys that are not assigned to play and record other chords.

RESULT

The triggered chords are recorded on the track. The note events are automatically assigned to different MIDI channels according to their pitches. Note events that correspond to the soprano voice are assigned to MIDI channel 1, alto is assigned to MIDI channel 2, and so on.

AFTER COMPLETING THIS TASK

You can now open the **Key Editor** and fine-tune your recorded MIDI parts using the chord editing functions, for example. You can also use **MIDI > Dissolve Part** to dissolve the recorded chords by pitches/channels.

Recording Chords on the Chord Track

You can record the triggered chords on the chord track. This way, you can easily create chord events for a lead sheet, for example.

PREREQUISITE

You have connected and set up a MIDI keyboard, you have opened and set up the chord pads, and you have added an instrument or a MIDI track for which a VST instrument is loaded.

PROCEDURE

1. On the instrument track, enable **Monitor**.
2. Select **Project > Add Track > Chord** to add the chord track.
3. In the Inspector for the chord track, click **Record Enable**.
4. On the **Transport** panel, activate **Record**.
5. On your MIDI keyboard, press the keys that trigger the chord pads.

NOTE

Use the keys that are not assigned to play and record other chords.

RESULT

The chord events are recorded on the chord track.

NOTE

The recorded chord events may sound different from the chord pad playback. This is because the voicing settings for the chord track differ from the chord pad voicings.

RELATED LINKS


[Chord Functions](#) on page 819

[Voicings](#) on page 828

Chord Pad Settings – Remote Control

On the **Remote Control** tab in the chord pad **Settings**, you can change the remote key assignments.

- To the left of the chord pads, click **Show/Hide Settings** and activate the **Remote Control** tab.



- 1 **Show/Hide Settings**
Opens the settings for the chord pads.
- 2 **Pad Control**
Allows you to set up remote keys for the chord pads and for voicings, tensions, and transpose control. On the keyboard, these are highlighted in blue and in green.
- 3 **Player Control**

Allows you to set up remote keys for the section player. On the keyboard, these are highlighted in brown.

4 Pads Remote Range

The keys that are assigned as remote keys for the chord pads are highlighted in blue.

5 Voicings/Tensions/Transpose

The keys that are assigned as remote keys for voicings, tensions, and transpose control are highlighted in green.

6 Section Remote Range

The keys that are assigned as remote keys for the sections are highlighted in brown.

7 Subsection Remote Range

The keys that are assigned as remote keys for the subsections are highlighted in light green.

RELATED LINKS

[Pads Remote Range](#) on page 849

[Section Remote Range](#) on page 850

[Section Player](#) on page 853

[Using Different Players on Multiple Tracks](#) on page 857

Pads Remote Range

The pads remote range is the range of remote keys that trigger the chords that are assigned to the chord pads.

- Select **Remote Control > Pad Control** to open the settings for the pads remote range.
- Select **Remote Control** to open the settings for the pads remote range.



1 Pads Remote Range

Allows you to set the start and end note for the remote range.

By default, **Range Start** is set to C1 and **Range End** to B1. This is indicated by the corresponding keys on the keyboard in the chord pads being highlighted in blue. You can trigger the chords that are assigned to the chord pads by hitting the keys that correspond to this note range on your MIDI keyboard.

2 Voicings/Tension/Transpose

Allows you to assign remote keys for changing the voicings, tension, and transposition settings of the last played chord pad. You can also assign continuous controllers to change all chord pads simultaneously.

The remote keys for voicings, tensions, and transpose are highlighted in green.

3 MIDI Learn

Activates/Deactivates the MIDI learn function to assign MIDI input to the pads remote range, and to the parameters for changing voicings, tensions, and transpose.

4 Activate

Activates/Deactivates the remote key assignment for the parameters voicings, tensions, and transpose. If this option is deactivated, only the remote key assignment for the pads remote range is active.

5 Latch Chords

Activate this if you want the chord pad to play back until it is triggered again.


NOTE

- If you use MIDI controllers that are already assigned to other remote control features, for example, the Track Quick Controls or the VST Quick Controls, all previous assignments are lost.
- If you use MIDI controllers that are already assigned to other remote control features, for example, the VST Quick Controls, all previous assignments are lost.

Section Remote Range

The section remote range is the range of remote keys that trigger the chord notes that correspond to the sections.

- Select **Remote Control > Player Control** to open the settings for the section remote range.



1 Sections

Allows you to assign remote keys for up to 5 sections. You can use the section remote keys together with a pad remote key to trigger the chord notes that correspond to the sections. By default, **Section 1** is set to G2, **Section 2** is set to A2, **Section 3** is set to B2, and **Section 4** is set to C3. This is indicated by the corresponding keys on the keyboard in the chord pads being highlighted in brown.

2 Subsections

Allows you to assign remote keys for up to 5 subsections. You can use the subsection remote keys together with a pad remote key to trigger the chord notes that correspond to the section transposed by the offset that is specified by its subsection.

There are no default remote keys for subsections. If you set remote keys for subsections, the corresponding keys on the keyboard in the chord pads are highlighted in light green.

3 Select/Mute Player

Allows you to assign remote keys for player navigation and muting if you use different players on multiple tracks.

4 MIDI Learn

Activates/Deactivates the MIDI learn function to assign MIDI input to sections, subsections, and to the parameters for selecting and muting players.

RELATED LINKS

[Section Player](#) on page 853

Default Remote Assignment

Default Remote Assignment for Pad Control

By default, the MIDI events C1 to B1 trigger the chords that are assigned to the chord pads. All keys that are not assigned for remote control can be used for regular playback.

You can change the voicing, tension, or transposition of the triggered chord by enabling **Activate** in the lower part of the **Remote Control** tab and using the following default remote notes:

Action	Description	Remote Note
Voicings: Previous	Plays back the previous voicing of the last played chord.	C2
Voicings: Next	Plays back the next voicing of the last played chord.	C#2
Voicings for all chord pads	The wheel position determines the voicings for the next played chords of all chord pads.	CC 1 Modulation wheel
Tensions: Less	Plays back the last played chord with fewer tensions.	D2
Tensions: More	Plays back the last played chord with more tensions.	D#2
Tensions for all chord pads	Allows you to determine the tension level for the next played chord of all chord pads.	CC 16
Transpose: Down	Plays back the last played chord and transposes it downwards.	E2
Transpose: Up	Plays back the last played chord and transposes it upwards.	F2
Transpose all chord pads	The wheel position determines the transposition value for the next played chords of all chord pads. Moving the wheel all the way up or all the way down corresponds to +/-5 semitones.	Pitchbend wheel

Remote assignments are saved globally.

NOTE

If you use the remote keys for voicings, tensions, or transposition after releasing the remote key for the chord pad, the next played chord is affected.

Default Remote Assignment for Player Control

By default, the MIDI events G2 to B2 trigger the chord notes corresponding to the sections.

The remote keys for **Subsections**, and also for selecting or muting players in a multitrack project, are not assigned by default.

Remote assignments are saved globally.

Changing the Pads Remote Range

You can widen the pads remote range to access more chord pads. If you want to use a wider key range on your MIDI keyboard for regular playing, you can narrow the pads remote range.

PROCEDURE

1. Select **Show/Hide Settings > Remote Control** to open the remote control assignments.
2. Do one of the following:
 - Click **MIDI Learn** so that the button lights up, and on your MIDI keyboard, press the 2 keys that you want to assign as range start and range end.
 - Enter a new value in the **Range Start** and **Range End** fields.


RESULT

On the keyboard, the indication for pads remote range is changed.

Chord Pad Settings – Players

On the **Players** tab in the chord pad **Settings**, you can change the voicing that is used for the chord pads. You can select different players with specific voicing settings that are typical for that kind of player. By default, the **Piano Player** option is active. By selecting **Plain Chords**, **Pattern**, or **Sections**, you can determine how the notes of a chord are played.

- To the left of the chord pads, click **Show/Hide Settings** and activate the **Players** tab.



- 1 **Show/Hide Settings**
Opens the settings for the chord pads.
- 2 **Player Selection**
Selects the player, and uses its voicing for the chord pads.
- 3 **Plain Chords/Pattern/Sections**
 - Select **Plain Chords** to trigger all notes of a chord simultaneously.
 - Select **Pattern** to break up the chords into their individual notes.
 - Select **Sections** to control the playback of single notes or groups of notes of a chord.
- 4 **Manage Players**

Opens a menu where you can select the player that you want to add. From here, you can also rename or remove the current player.

5 Overlaps

When you play a chord without releasing the previous chord, this option allows you to select what happens with the notes of the first chord.

- Select **Hold First** to hold the notes of the first chord. No note-off message is sent. If the chords have common notes, these are not triggered again.
- Select **Legato** to release the notes of the first chord, except for the common notes. These are held and not triggered again.
- Select **Stop First** to release the notes of the first chord including the common notes.

6 Filter Notes

Allows you to select which keys are filtered.

- Select **Off** to filter nothing.
- Select **From MIDI Thru** to filter unassigned keys, and keys that are assigned as remote keys for voicings, tensions, and transpose.
- Select **From Chord Pads** to filter keys that are assigned as remote keys for chord pads, voicings, tensions, and transpose.
- Select **All** to filter everything.

RELATED LINKS

[Players and Voicings](#) on page 855

[Voicings](#) on page 828

[Chord Pad Settings – Players](#) on page 852

Section Player

The section player allows you to control the playback of single notes or groups of notes, so called sections, of a chord that is assigned to a chord pad.

Sections hold the chord notes, starting from bottom to top: the first section represents the lowest note or voicing of a chord, usually the bass. The second section represents the tenor, and so on.

You can play the sections and their corresponding chord notes by using the remote keys that are assigned to them together with the remote keys that are assigned to a chord pad. To view and edit the assignment, you can open the **Remote Control** tab.

The **Pad Control** tab shows the remote key assignment for the chord pads. The **Player Control** tab shows the remote key assignment for the sections.

RELATED LINKS


[Chord Pad Settings – Remote Control](#) on page 848

[Custom Settings for Section Player](#) on page 853

Custom Settings for Section Player

The custom settings for the section player allow you to determine how the sections are triggered, how they are distributed, or if they are played at all. Only sections with remote keys assigned are available.

- On the **Players** tab, activate the **Sections** tab and click **Custom**.



The following settings are available:

Play Modes	
<input checked="" type="radio"/>	Sections
<input type="radio"/>	Chord Pads
<input type="radio"/>	Combination
<input checked="" type="checkbox"/>	Latch Chord Pads
Chord Note Distribution	
Distribute additional notes starting at:	Last Section ▼
Force single notes for:	First Section ▼
Mute Sections	
<input type="checkbox"/>	1st
<input type="checkbox"/>	2nd
<input type="checkbox"/>	3rd
<input type="checkbox"/>	4th
<input type="checkbox"/>	5th
Subsection Assignments	
Subsection 1:	assigned to: No Section ▼ Offset: 0 ▾
Subsection 2:	assigned to: No Section ▼ Offset: 0 ▾
Subsection 3:	assigned to: No Section ▼ Offset: 0 ▾
Subsection 4:	assigned to: No Section ▼ Offset: 0 ▾
Subsection 5:	assigned to: No Section ▼ Offset: 0 ▾

Play Modes

- **Sections**
On your MIDI keyboard, first press a key that is assigned to a chord pad, then press the remote key for a specific section to hear the chord notes that correspond to the section.
- **Chord Pads**
On your MIDI keyboard, first press the remote key for a specific section, then press a key that is assigned to a chord pad to hear the chord notes that correspond to the section.
- **Combination**
Combines sections and chord pads so that it does not matter whether you first press the remote key for the chord pad or for the section.

For sections and combination modes you can activate **Latch Chord Pads**. This way, if you release the remote key for the chord pad, you will still hear the sections if you keep the section remote keys pressed.

Chord Note Distribution

Here, you can determine how chord notes are distributed among the sections if the chord that is assigned to the chord pad has more notes than sections.

Mute Sections

Activate this option to exclude a section from being played. This is useful if you want to exclude specific voicings from playback.

Subsection Assignments

These are available if you have set up remote keys for subsections on the **Remote Control** tab in the **Player Control** settings.

- Open the **assigned to** pop-up menu to assign a subsection to a section.
- Use the **Offset** controls to specify an offset from the section. This way, when you press the remote key for the subsection, you will hear the chord notes that correspond to the section, transposed by the specified offset.

NOTE

To set **Play Modes**, **Chord Note Distribution**, and **Mute Sections** to their default settings, close the **Custom Settings for Section Player** pane and click **Default**.

Playing Back Chord Sections

You can play back single chord notes or chord sections of a chord pad.

PREREQUISITE

You have added an instrument track with an instrument assigned to your project. You have record-enabled the instrument track. You have a MIDI keyboard connected and set up.

PROCEDURE

1. In the chord pads, activate **Show/Hide Settings**.
2. Open the **Players** tab, and activate **Sections**.

On the keyboard, the remote range for the sections is highlighted in orange.



3. On your MIDI keyboard, press any key that corresponds to the pads remote range. This normally triggers the chord pad, however, in sections mode, you do not hear anything until you press a section remote key.
 4. On your MIDI keyboard, press any key that corresponds to the section remote range.
-

RESULT

The chord section of the chord whose chord pad you triggered is played back. You can press any other key in the section remote range to play different sections of the same chord, or press them all at once. You can use the remote keys for voicing, tension, and transpose to add variety.

Players and Voicings

Different types of instruments and styles have different voicing libraries. These determine how the chords are played back, and which pitches are played. These voicings are referred to as players.

RELATED LINKS

[Voicings on page 828](#)

Adaptive Voicing

In Cubase, the adaptive voicing setting ensures that pitches in chord progressions do not change abruptly.

Adaptive voicing is activated and the voicings of the chord pads are determined automatically according to specific voice leading rules.



If you want to set the voicing of a specific chord pad manually, and do not want it changed automatically, you can use the voicing control to the right of a chord pad. When you assign your own voicing, adaptive voicing is deactivated for that chord pad, so that the pad does no longer follow the voice leading rules of the voicing reference. To activate adaptive voicing again, right-click the chord pad and activate **Adaptive Voicing**.

To lock the voicing for a chord pad, you can right-click the pad and activate **Lock**. This locks this pad for editing and remote control changes, and deactivates **Adaptive Voicing**. To unlock the chord pad again, right-click the pad and deactivate **Lock**.

Pattern Player


The pattern player allows you to break up the triggered chord to individual notes that are played back one after another (arpeggio).

Using the Pattern Player

The pattern player plays the notes that make up the chord one after another (arpeggio).

PROCEDURE

1. Select **Show/Hide Settings > Players > Pattern**.



2. Perform one of the following actions:
 - Click **Import MIDI Loop** to select a MIDI loop that you want to use as a pattern.
 - Drag a MIDI part from the event display to the **Drop MIDI Part** field.

NOTE

The loop or part must have between 3 and 5 voices. In the **MediaBay**, the number of voices is indicated in the **Voices** column of the result list.

The loop or part is taken as a reference and defines how the chord is played. The **Drop MIDI Part** field displays the name of the selected loop or part.

3. In the **Velocity from:** field, select a velocity source for the notes.
 - Activate **MIDI Keyboard** to determine the velocity values by pressing the keys on your MIDI keyboard harder or softer.
 - Activate **Pattern** to use the velocity values from the MIDI loop or the MIDI part that is selected as a pattern.

AFTER COMPLETING THIS TASK

If you have a pattern that you want to use in other projects, you can save it using the presets section in the pattern player.

RELATED LINKS

- [Assigning Voices to Notes](#) on page 834
- [Setting Up the Results List Columns](#) on page 557

Using Different Players on Multiple Tracks

You can set up different players with different sounds on different tracks. If you record-enable these tracks and play the chord pads, each track uses a dedicated player.

PROCEDURE

1. Select **Project > Add Track > Instrument**.
2. In the **Add Instrument Track** dialog, enter the number of tracks in the **Count** field, and select a VST instrument.
3. Click **Add Track**.
The instrument tracks are added to your project.
4. Select **Project > Chord Pads** to open the chord pads.
5. To the left of the chord pads, activate **Show/Hide Settings** and click **Players**.
6. Select the first instrument track, select a sound on the VST instrument, and in the chord pads, select a player.
For example, select a piano sound and assign a **Piano Player**.

NOTE

When setting up the player for a track, make sure that **Record Enable** or **Monitor** is only active for this particular track.

7. Select the second instrument track, select a sound on the VST instrument, and set up another player.
For example, select a guitar sound and assign a **Guitar Player**.
8. Select the next instrument track, and proceed as for the other 2 tracks.
For example, select a string sound and assign a **Basic Player**.
9. Select all instrument tracks, and click **Record Enable**.


RESULT

You can now play the chord pads and use the remote control parameters for tensions and transpose to change all chord symbols for each player simultaneously. However, if you change the **Voicing**, only the selected player is affected.

Chord Pad Settings – Pad Layout

The **Pad Layout** tab in the chord pad **Settings** allows you to change the layout that is used for the chord pads. By default, the keyboard layout is active, but you can change to a grid layout if you prefer that. After changing the pad layout you may need to adjust the remote setup.

- To the left of the chord pads, click **Show/Hide Settings** and activate the **Pad Layout** tab.



- 1 **Show/Hide Settings**

Opens the settings for the chord pads.

2 Keyboard

Activate this to show the chord pads in a keyboard layout. You can display 1 or 2 octaves, and you can select if the first chord pad starts with C, A or E.

3 Grid

Activate this to show the chord pads in a grid layout. You can display up to 4 rows and 16 columns.

4 Layout display

Shows how the active chord pad layout is displayed.

Chord Pads Presets

Chord pads presets are templates that can be applied to newly created or to existing chord pads.

Chord pads presets contain the chords that are assigned to the chord pads, as well as the player configurations including any pattern data that you have imported via the **MediaBay** or by using drag & drop. The chord pads presets allow you to quickly load chords, or reuse player settings. The chord pads presets menu is located to the left of the chord pads. Chord pads presets are organized in the **MediaBay**, and you can categorize them with attributes.

- To save/load a chord pads preset, select **Chord Pads Presets > Save/Load Chord Pads Preset**.

You can also load only the assigned chords from a chord pads preset, without loading the player configurations. This is useful if you want to use specific chords that you have saved as a preset, but do not want to alter your current player setting.

- To load only the chords of a chord pads preset, select **Chord Pads Presets > Load Chords from Preset**.

In the same way, you can also load only the player configurations of a chord pads preset. This is useful if you have saved very complex player settings and want to reuse them on other chord pads without changing the assigned chords.

- To load only the player settings of a chord pads preset, select **Chord Pads Presets > Load Players from Preset**.

Saving Chord Pads Presets

If you have set up the chord pads, you can save them as chord pads presets.

PROCEDURE

1. To the left of the chord pads, select **Chord Pads Preset > Save Chord Pads Preset**.
2. In the **New Preset** section, enter a name for the new preset.

NOTE

You can also define attributes for the preset.

3. Click **OK** to save the preset and exit the dialog.
-

Creating Events from Chord Pads

You can use the chords assigned to the chord pads to create chord events or MIDI parts in the **Project** window.

- To create a chord event, drag a chord pad and drop it on the chord track.

- To create a MIDI part with the length of one bar, drag a chord pad and drop it on a MIDI or instrument track.

RELATED LINKS

[Recording Chord Events with a MIDI Keyboard](#) on page 835

Logical Editor

The **Logical Editor** is a powerful tool for search and replace functions on MIDI data.

IMPORTANT

The **Logical Editor** is only available in Cubase Pro. However, the **Transformer** MIDI insert and the **Input Transformer** that share many of the functions with the **Logical Editor** are also available in Cubase Artist.

The principle of the Logical Editor is this:

- You set up filter conditions to find certain elements.
This can be elements of a certain type, with certain attributes or values or on certain positions, in any combination. You can combine any number of filter conditions and make composite conditions using **And/Or** operators.
- You select the basic function to be performed.
The options include **Transform**, for changing properties of the found elements, **Delete**, for removing the elements, **Insert**, for adding new elements based on the found positions of other elements, and more.
- You set up a list of actions, which specify exactly what is done.
This is not necessary for all functions.

By combining filter conditions, functions and the specific actions, you can perform very powerful processing.

To master the **Logical Editor**, you need some knowledge about how MIDI messages are structured. However, the **Logical Editor** also comes with a rich selection of presets, allowing you to access its processing powers without delving into its more complicated aspects.

IMPORTANT

Studying the included presets or using them as starting points to set up your own actions is an excellent way to learn the workings of the **Logical Editor**.


RELATED LINKS

[Presets](#) on page 874

Window overview

The **Logical Editor** window allows you to combine filter conditions, functions, and actions to perform very powerful MIDI processing.

- To open the **Logical Editor**, select **MIDI > Logical Editor**.



1 Filter Conditions

Allows you to specify the conditions such as type, attribute, value, position, that a specific element must meet to be found. You can combine any number of filter conditions using AND/OR operators.

2 Action List

Allows you to set up a list of actions that specifies exactly what is done. This is not necessary for all functions.

3 Function pop-up menu

Allows you to select a function.

4 Apply

Applies your settings.

NOTE

This button is not available in the Transformer.

Filter Conditions

The upper list is where you set up the filter conditions, determining which elements to find. The list can contain one or several conditions, each on a separate line.

To set up a filter condition, make the following settings:

Filter Target

Sets the property of the element. This setting affects the available options in the other columns.

Condition

Determines how the **Logical Editor** compares the property in the **Filter Target** column to the values in the **Parameter** columns. The available options depend on the **Filter Target** setting.

Parameter 1

Sets which value the element properties are compared to. This depends on the **Filter Target**.

Parameter 2

Only available if one of the **Range** options is set in the **Condition** column. Allows you to find all elements with values inside or outside the range between **Parameter 1** and **Parameter 2**.

Bar Range/Time Base

Only available if the **Filter Target** is set to **Position**. If one of the **Bar Range** options is selected in the **Condition** column, you use the **Bar Range/Time Base** column to specify zones within each bar. This allows you to find all elements on or around the first beat of every bar, for example. If any of the other **Condition** options is selected, you can use the **Bar Range/Time Base** column to specify a time base such as PPQ, seconds, etc.

NOTE

This is only available in the **Logical Editor**.

Left bracket

Together with the right bracket, this allows you to combine multiple filter conditions, that is multiple lines with the boolean operators And/Or.

Right bracket

Together with the left bracket, this allows you to combine several filter conditions.

bool

Allows you to insert the boolean operators And/Or, when creating conditions with multiple lines.

NOTE

If you make a mistake when combining multiple conditions with brackets, you are informed in the status line.

NOTE

If you have already defined filter conditions and/or applied a preset, but want to start again from scratch, you can initialize the settings by selecting the **Init** option from the **Presets** pop-up menu.

NOTE

You can also set up filter conditions by dragging MIDI events directly into the upper list.

If the list contains no entries, a MIDI event dragged into this section will form conditions including the state and type of the event. If it contains entries, the dragged event will initialize the matching parameters. For example, if a length condition is used, the length will be set according to the length of the event.

Depending on the **Filter Target** setting, the following options can be selected in the **Condition** column:

Equal

Has the exact same value as set up in the **Parameter 1** column.

Unequal

Has any value other than the one set up in the **Parameter 1** column.

Bigger

Has a value higher than the one set up in the **Parameter 1** column.

Bigger or Equal

Has a value that is the same as or higher than the one set up in the **Parameter 1** column.

Less

Has a value lower than the one set up in the **Parameter 1** column.

Less or Equal

Has a value that is the same as or lower than the one set up in the **Parameter 1** column.

Inside Range

Has a value that is between the values set up in the **Parameter 1** and **Parameter 2** columns. Note that **Parameter 1** should be the lower value and **Parameter 2** the higher.

Outside Range

Has a value that is not between the values set up in the **Parameter 1** and **Parameter 2** columns.

Inside Bar Range (Logical Editor only)

Is within the zone set up in the **Bar Range/Time Base** column, in each bar within the current selection. This is only used if the **Filter Target** is set to **Position**.

Outside Bar Range (Logical Editor only)

Is outside the zone set up in the **Bar Range/Time Base** column, in each bar within the current selection. This is only used if the **Filter Target** is set to **Position**.

Before Cursor (Logical Editor only)

Is before the song cursor position. This is only used if the **Filter Target** is set to **Position**.

Beyond Cursor (Logical Editor only)

Is after the song cursor position **Position** only.

Inside Track Loop (Logical Editor only)

Is inside the set track loop. This is only used if the **Filter Target** is set to **Position**.

Inside Cycle (Logical Editor only)

Is inside the set cycle. This is only used if the **Filter Target** is set to **Position**.

Exactly Matching Cycle (Logical Editor only)

Exactly matches the set cycle. This is only used if the **Filter Target** is set to **Position**.

Note is equal to

Is the note specified in the **Parameter 1** column, regardless of octave only. For example, lets you find all C notes, in all octaves. This is only used if the **Filter Target** is set to **Pitch**.

NOTE

The conditions for the **Property** filter target are different.

RELATED LINKS

[Combining Multiple Condition Lines](#) on page 885

[Searching for Properties](#) on page 867

[Searching for Elements at Specific Positions \(Logical Editor only\)](#) on page 864

Searching for Elements at Specific Positions (Logical Editor only)

You can search for elements starting at specific positions, either relative to the start of the project or within each bar.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Position**.
This allows you to find elements starting at specific positions, either relative to the start of the project or within each bar.
2. Open the **Condition** pop-up menu and select one of the following options:
 - To find all elements at a specific position, select a position in the **Parameter 1** column.
You can set a time base such as PPQ, seconds, samples, or frames in the **Bar Range/Time Base** column.
 - To find all elements inside or outside a range, select **Inside Bar Range** or **Outside Bar Range**.
You can set the bar range in the **Bar Range/Time Base** column by clicking and dragging in the bar display or by adjusting the start position of the range in the **Parameter 1** column and the end position in the **Parameter 2** column. You can change the time base use the **Bar Range/Time Base** column. The position for **Bar Range** is measured in ticks related to the start of the bar.

EXAMPLE

You can set up the **Logical Editor** to find all elements at 1.1.1.0 in the project.

Filter Target	Condition	Parameter 1
Position	Equal	1.01.01.000

You can set up the **Logical Editor** to find elements starting around the second beat in each bar.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Position	Inside Bar Range	391	491	

Searching for Notes of Specific Lengths (Logical Editor only)

You can search for notes of specific lengths.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Length**.
This allows you to find notes of a specific length only.
- NOTE**
- The **Length** parameter is interpreted via the time base setting in the **Bar Range/Time Base** column, that is, in PPQ, seconds, samples, or frames.
-
2. Open the **Parameter 1** pop-up menu and set the length that you want to search for.
 3. Open the **Condition** pop-up menu and select an option.
If you select **Inside Range** or **Outside Range**, use **Parameter 1** and **Parameter 2** to set the start and the end of the range.
 4. Click  below the list to add another condition line.
Parameter 1 is automatically set to **Note** as the **Length Filter Target** is only valid for notes.

RELATED LINKS

[Combining Multiple Condition Lines](#) on page 885

Value 1 and Value 2

MIDI events can be composed of value 1 and value 2.

Value 1 and value 2 have different meanings for different event types:

Event type	Value 1	Value 2
Notes	The Note Number/Pitch.	The velocity of the note.
Poly Pressure	The key that was pressed.	The amount of pressure for the key.
Controller	The type of Controller, displayed as a number.	The amount of Control Change.
Program Change	The Program Change number.	Not used.
Aftertouch	The amount of pressure.	Not used.
Pitchbend	The "fine-tune" of the bend. Not always used.	The coarse amount of bend.
VST 3 Event	Not used.	The value of the VST 3 Event parameter. The value range of the VST 3 event (0.0 to 1.0) is transformed into the MIDI value range (0-127), that is, the VST 3 event value 0.5 corresponds to 64. For some operations that require a higher resolution, you can make use of the "VST 3 Value Operation" parameter.

NOTE

System Exclusive events do not use value 1 and 2.

RELATED LINKS

[Action Target](#) on page 887

Searching for Note Pitches or Velocities

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Value 1** for pitches, or **Value 2** for velocities.
2. Optional for pitches: In the **Parameter 1** column, enter a pitch either as note name such as C3, D#4, etc. or as a MIDI note number from 0 to 127.

NOTE

To find all notes of a certain key, in all octaves, open the **Condition** pop-up menu and select **Note is equal to**.

3. Click  below the list to add another condition line.
Parameter 1 is automatically set to **Note**. Also, **Value 1** and **Value 2** will be displayed as **Pitch** and **Velocity** respectively.
-

RELATED LINKS

[Combining Multiple Condition Lines](#) on page 885

Searching for Controllers

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Value 1**.
 2. Click  below the list to add another condition line.
 3. Open the **Parameter 1** pop-up menu and select **Controller**.
Value 1 is automatically set to **MIDI Controller No.** and the **Parameter 1** column will show the names of the MIDI controllers.
-

RELATED LINKS

[Combining Multiple Condition Lines](#) on page 885

Searching for MIDI Channels

Searching for MIDI channels is useful if you have recorded MIDI from an instrument sending on several different channels. Or if you have imported a MIDI file of type 0 with a single track, containing MIDI events with different channel settings.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Channel**.
 2. In the **Parameter 1** field, enter a MIDI channel from 1 to 16.
 3. Open the **Condition** pop-up menu and select an option.
-

Searching for Element Types

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Type**.
 2. Open the **Parameter 1** pop-up menu and select a type such as note, poly pressure, controller, etc.
 3. Open the **Condition** pop-up menu and select an option.
-

Searching for Properties

You can search for properties that are not part of the MIDI standard but rather Cubase-specific settings.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Property**.
2. Open the **Parameter 1** pop-up menu and select the property that you want to search for.
3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Property is set** if you want to search for events that have the specified property.
 - Select **Property is not set** if you want to search for events that do not have the specified property.

EXAMPLE

You can set up the **Logical Editor** to find all muted events.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Property	Property is set	Event is muted		

You can set up the **Logical Editor** to find events that are selected and muted.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
(Property	Property is set	Event is selected		
	Property	Property is set	Event is muted		

Cubase Pro only: You can set up the **Logical Editor** to find all Note Expression data.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Type Is	Unequal	Note		
Property	Property is set	Event inside NoteExp		

Cubase Pro only: You can set up the **Logical Editor** to find all MIDI controller events that form part of note expression data.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Type Is	Equal	Controller		
Property	Property is set	Event inside NoteExp		

Cubase Pro only: You can set up the **Logical Editor** to find all VST 3 events that cannot be played back, because there is no Note Expression compatible VST instrument on the related track.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Type Is	Equal	VST3 Event	All Types	
Property	Property is set	Event is valid VST3		

Searching for Event Contexts

You can perform context-dependent searches. This is especially useful in the **Input Transformer**.

The **Filter Target Last Event** indicates the state of an event which has already passed the **Input Transformer** or the **Logical Editor**. The condition must be combined with **Parameter 1** and **Parameter 2**.

EXAMPLE

You can set up the **Logical Editor** to perform actions only when the sustain pedal is down.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Last Event	Equal	MIDI Status	176/Controller			And
	Last Event	Equal	Value 1	64/E3			And
	Last Event	Equal	Value 2	64/E3			

You can set up the **Input Transformer** or the **Transformer** to perform actions only when the note C1 is pressed.

Filter Target	Condition	Parameter 1	Parameter 2	bool
Type Is	Equal	Note		And
Last Event	Equal	Note is playing	36/C1	

In this example, the action is performed after playing the C1.

Filter Target	Condition	Parameter 1	Parameter 2	bool
Last Event	Equal	Value 1	36/C1	

Searching for Chords (Logical Editor only)

You can search for chords in a MIDI part or on the chord track.

PREREQUISITE

NOTE

A note belongs to a chord if at least 2 other notes play at the same time.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Context Variable**.
2. Open the **Parameter 1** pop-up menu and select the property that you want to search for.
3. Open the **Condition** pop-up menu and select an option.

Chords Filter

If the **Filter Target** is set to **Context Variable**, you can search for the following parameters:

Highest/Lowest/Average Pitch

Finds notes with the highest, lowest or average pitch in the selected MIDI part.

Highest/Lowest/Average Velocity

Finds notes with the highest, lowest or average velocity in the selected MIDI part.

Highest/Lowest/Average CC Value

Controllers with the highest, lowest or average value in the selected MIDI part.

The following settings for **Parameter 1** require a **Parameter 2**:

Number of Notes in Chord (Part)

If you set **Parameter 2** to the number of notes in the chord, this finds chords with the specified number of notes in the selected MIDI part.

Number of Voices (Part)

If you set **Parameter 2** to the number of voices of the chord, this finds chords with the specified number of voices in the selected MIDI part.

Position in Chord (Part)

If you set **Parameter 2** to the position in the chord, this finds chords with the specified chord interval in the selected MIDI part.

Note Number in Chord (lowest = 0)

If you set **Parameter 2** to the voicing number of chord, this finds chords with the specified voicing number in the selected MIDI part.

Position in Chord (Chord track)

If you set **Parameter 2** to the position in the chord, this finds the specified chord interval in the selected MIDI part. The Chord track is taken as reference.

Voice

If you set **Parameter 2** to the voice in the chord, this finds the specified voice in the selected MIDI part.

NOTE

The **Musical Context** presets give you an idea of the possibilities of this filter target.

Combining multiple condition lines

You can add condition lines and combine them by using boolean And and Or operators and brackets.

- To add a new condition, click **+** below the list.
The new line is added at the bottom of the list.
- To remove a condition, select it and click **-** below the list.

The Bool column

In the **bool** column to the right in the list, you can select a boolean operator: **And** or **Or**.

A boolean operator combines 2 condition lines and determines the result in the following way:

- **And** determines that both conditions must be fulfilled for an element to be found.
- **Or** determines that at least one of the conditions must be fulfilled for an element to be found.

IMPORTANT

When you add a new condition line, the boolean setting defaults to **And**.

EXAMPLE

You can set up the **Logical Editor** to find elements that are notes and start at the beginning of the third bar.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Type Is	Equal	Note)	And
	Position	Equal	3.01.01.000		PPQ)	

You can set up the **Logical Editor** to find all events that are notes (regardless of their position) and all events starting at the beginning of the third bar (regardless of their type).

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Type Is	Equal	Note)	Or
	Position	Equal	3.01.01.000		PPQ)	

Using brackets

The bracket columns let you enclose 2 or more condition lines, dividing the conditional expression into smaller units. This is only relevant when you have 3 or more condition lines and want to use the boolean **Or** operator.

You add brackets by clicking in the bracket columns and selecting an option. Up to triple brackets can be selected.

You can add brackets by clicking in the bracket columns and selecting an option. Up to triple brackets can be selected.

If you add several layers of brackets, these are evaluated from the inside out, starting with the innermost brackets.

Expressions within brackets are evaluated first.

EXAMPLE

You can set up the **Logical Editor** to find all MIDI notes with the pitch C3, as well as all events (regardless of their type) set to MIDI channel 1.


(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Type Is	Equal	Note				And
	Pitch	Equal	C3				Or
	Channel	Equal	1)	

You can set up the **Logical Editor** to find all notes that either had the pitch C3 or the MIDI channel 1 (but no non-note events).

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Type Is	Equal	Note				And
(Pitch	Equal	C3				Or
	Channel	Equal	1)	

Selecting a function

The pop-up menu at the bottom of the **Logical Editor** is where you select the function, that is, the basic type of editing to be performed.



Below, the available options are listed.

NOTE

Some options are not available in the **Transformer** effect.

Delete

Deletes all elements found by the **Logical Editor**. In the case of the **Transformer**, this function will remove or mute all found elements from the output stream. The actual elements on the track are not affected.

Transform

Changes one or several aspects of the found elements. You set up exactly what is changed in the action list.

Insert

Creates new elements and inserts these into the parts (**Logical Editor**) or the output stream (**Transformer**). The new elements will be based on the elements found by the filter conditions, but with any changes you have set up in the action list applied.

Another way of expressing this is that the **Insert** function copies the found elements, transforms them according to the action list and inserts the transformed copies among the existing elements.

Insert Exclusive

Transforms the found elements according to the action list. All elements that do not meet the filter conditions are deleted (**Logical Editor**) or removed from the output stream (**Transformer**).

Copy (Logical Editor only)

Copies all found elements, transforms them according to the action list and pastes them into a new part on a new MIDI track. The original events are not affected.

Extract (Logical Editor only)

Transforms all found events and moves them to a new part on a new MIDI track.

Select (Logical Editor only)

Selects all found events and highlights them for further work in the regular MIDI editors.

RELATED LINKS

[Specifying actions](#) on page 871

Specifying actions

You can specify actions, that is, changes that are made to the found elements, in the lower list of the **Logical Editor**. Actions are relevant for all function types except **Delete** and **Select**.

Action Target	Operation	Parameter 1	Parameter 2
Value 1	Set to fixed value		2

You can add action lines by clicking **+**, and remove them by selecting it and clicking **-**.

Action Target

The **Action Target** allows you to select the property that is changed in the events.

Position (Logical Editor only)

Moves the events.

Length (Logical Editor only)

Resizes note events.

Value 1

Adjusts value 1 in the events. What is displayed for value 1 depends on the event type. For notes, value 1 is the pitch.

Value 2

Adjusts value 2 in the events. What is displayed for value 2 depends on the event type. For notes, value 2 is the velocity value.

Channel

Allows you to change the MIDI channel setting.

Type

Allows you to change the event type, that is, transform aftertouch events to modulation events, or pitchbend events to VST 3 Tuning events.

Value 3

Adjusts value 3 in the events, which is used for handling of Note-off velocity when searching for properties.

NoteExp Operation (Logical Editor only)

Cubase Pro only: Allows you to specify a Note Expression operation in the Operation column.

VST 3 Value Operation (Logical Editor only)

Allows you to perform common operations within the VST 3 value range (0.0 to 1.0) instead of the standard MIDI value range (0-127), for finer adjustments.

NOTE

The **Position** and **Length** parameters are interpreted via the time base setting in the **Bar Range/Time Base** column, with the exception of the **Random** setting, which uses the time base of the affected events.

RELATED LINKS

[Searching for Properties](#) on page 867
[Value 1 and Value 2](#) on page 865

Operation

The Operation allows you to determine what to do with the **Action Target**.

The options on this pop-up menu are different depending on the selected **Action Target**.

Add

Adds the value specified in the **Parameter 1** column to the **Action Target**.

Subtract

Subtracts the value specified in the **Parameter 1** column from the **Action Target**.

Multiply by

Multiplies the **Action Target** with the value specified in the **Parameter 1** column.

Divide by

Divides the **Action Target** by the value specified in the **Parameter 1** column.

Cubase Pro only: VST 3 Value Operation – Invert (Logical Editor only)

Inverts note expression data containing the specified VST 3 event parameter.

Round by

Rounds the **Action Target** value using the value specified in the **Parameter 1** column.

Set Random Values between

Sets the **Action Target** value to a random value within the range specified with **Parameter 1** and **Parameter 2**.

Set to fixed value

Sets the **Action Target** to the value specified in the **Parameter 1** column.

Set Relative Random Values between

Adds a random value to the current **Action Target** value. The added random value will be within the range specified with **Parameter 1** and **Parameter 2**. Note that these can be set to negative values.

Add Length (Logical Editor only)

This is only available if you set **Action Target** to **Position**. Furthermore, it is only valid if the found events are notes. If you select **Add Length**, the length of each note event is added to the **Position** value.

Transpose to Scale

This is only available if you set **Action Target** to Value 1, and if the filter conditions are specifically set up to find notes (a **Type = Note** filter condition line has been

added). When **Transpose to Scale** is selected, you can specify a musical scale using the **Parameter 1** and **Parameter 2** columns. **Parameter 1** is the key (C, C#, D, etc.) while **Parameter 2** is the type of scale (major, melodic or harmonic minor, etc.).

Each note will be transposed to the closest note in the selected scale.

Use Value 2

This is only available if you set **Action Target** to **Value 1**. If this option is selected, the **Value 2** setting in each event will be copied to the **Value 1** setting.

Use Value 1

This is only available if you set **Action Target** to **Value 2**. If this option is selected, the **Value 1** setting in each event will be copied to the **Value 2** setting.

Mirror

This is only available if you set **Action Target** to **Value 1** or **Value 2**. When this option is selected, the values are mirrored around the value set in the **Parameter 1** column.

In the case of notes, this inverts the scale, with the key set in the **Parameter 1** column as center point.

Linear Change in Loop Range (Logical Editor only)

This affects events between the left and right locators only. It creates a linear ramp of values (replacing the original values) starting at the value in the **Parameter 1** column and ending at the **Parameter 2** value.

Relative Change in Loop Range (Logical Editor only)

This will create a ramp of values, affecting events in the loop range only, that is, between the locators. However, here the changes are relative, meaning that values will be added to the existing values.

In other words, you set up a value ramp starting at **Parameter 1** and ending at **Parameter 2** (note that the values can be negative). The resulting value ramp is then added to the existing values for the events within the loop range.

For example, if you apply this to note velocities with **Parameter 1** set to 0 and **Parameter 2** set to -100, you create a velocity fade-out, keeping the original velocity relations:

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Type Is	Equal	Note				
+ -							
Action Target	Operation	Parameter 1	Parameter 2				
Value 1	Relative Change in Loop Range	0	-100				

Cubase Pro only: NoteExp Operation – Remove Note Expression (Logical Editor only)

This option is only available for notes. It allows you to remove all note expression data from a note.

Cubase Pro only: NoteExp Operation – Create One-Shot (Logical Editor only)

This option is only available for notes. It allows you to add note expression data for notes in **One Shot** mode, meaning that you add a parameter as note expression data. After having added the one-shot parameter, you have to set it to the desired value in a second go.

Cubase Pro only: NoteExp Operation – Reverse (Logical Editor only)

Reverses the note expression data.

RELATED LINKS

[Value 1 and Value 2](#) on page 865

Applying the Defined Actions

Once you have set up filter conditions, selected a function and set the required actions or loaded a preset, you apply the actions defined with the **Logical Editor** by clicking the **Apply** button.

IMPORTANT

The MIDI insert effect **Transformer** does not feature an **Apply** button. Here, the current settings are automatically applied in realtime during playback or live playing.

Logical Editor operations can be undone just like any other editing.

Presets

The section in the upper left section of the window allows you to load, save and manage **Logical Editor** presets.

To load a preset, do one of the following:

- Open the **Select Preset** pop-up menu, and select an option.
- Select **MIDI > Logical Presets**, and select an option.
- Open the **List Editor** and in the filters bar, select a preset from the **Show** section.

NOTE

If you set up a key command for a preset you can conveniently apply the same operation to several selected events in one go.

RELATED LINKS

[Key Commands](#) on page 973

Storing your own settings as a preset

You can save settings that you want to use again as presets.

PROCEDURE

1. In the section in the upper left of the **Logical Editor**, click **Store Preset**.
 2. In the dialog that opens, specify a name for the preset and click OK.
-

RESULT

The preset is stored.

NOTE

To remove a preset, load it and click the **Remove Preset** button.

Organizing and sharing presets

The **Logical Editor** presets are stored within the application folder in the **Presets\Logical Edit Project** subfolder.

Preset files cannot be edited manually, but you can reorganize them. This also makes it easy to share presets with other Cubase users, by transferring the individual preset files.

NOTE

The list of presets is read each time the **Logical Editor** is opened.

Project Logical Editor (Cubase Pro only)

The **Project Logical Editor** is a powerful tool for search and replace functions in the **Project** window.

The **Project Logical Editor** allows you to specify filter conditions and combine them with actions. This way you can search for all open folder tracks in your project, for example, and close them.

The **Project Logical Editor** comes with a number of presets that show you the possibilities of this feature, and that you can use as a starting point for your own settings.

RELATED LINKS


[Presets](#) on page 890

[Window Overview](#) on page 876

Window Overview

The **Project Logical Editor** window allows you to combine filter conditions, functions, actions, and macros to perform very powerful processing.

- To open the **Project Logical Editor**, select **Edit > Project Logical Editor**.



1 Filter Conditions

Allows you to specify the conditions such as type, attribute, value, position, that a specific element must meet to be found. You can combine any number of filter conditions using AND/OR operators.

2 Action List

Allows you to set up a list of actions that specifies exactly what is done. This is not necessary for all functions.

3 Function pop-up menu

Allows you to select if the found elements are transformed, deleted, or selected.

4 Macro pop-up menu

Allows you to select a macro.

5 Apply

Applies your settings.

IMPORTANT

Not every combination of settings always makes sense. Experiment a bit before applying your edits to important projects.

NOTE


You can undo the operations by selecting **Edit > Undo**.

RELATED LINKS

[Presets](#) on page 890

Filter Conditions

By setting up filter conditions you can determine which filter target that is what elements you want to find.



To set up a filter condition, make the following settings:

Filter Target

Sets the property of the element. This setting affects the available options in the other columns.

Condition

Determines how the **Project Logical Editor** compares the property in the **Filter Target** column to the values in the **Parameter** columns. The available options depend on the **Filter Target** setting.

Parameter 1

Sets which value the element properties are compared to. This depends on the **Filter Target**.

Parameter 2

Only available if one of the **Range** options is set in the **Condition** column. Allows you to find all elements with values inside or outside the range between **Parameter 1** and **Parameter 2**.

Bar Range/Time Base

Only available if the **Filter Target** is set to **Position**. If one of the **Bar Range** options is selected in the **Condition** column, you use the **Bar Range/Time Base** column to specify zones within each bar. This allows you to find all elements on or around the first beat of every bar, for example. If any of the other **Condition** options is selected, you can use the **Bar Range/Time Base** column to specify a time base such as PPQ, seconds, etc.

Left bracket

Together with the right bracket, this allows you to combine multiple filter conditions, that is multiple lines with the boolean operators And/Or.

Right bracket

Together with the left bracket, this allows you to combine several filter conditions.

bool

Allows you to insert the boolean operators And/Or, when creating conditions with multiple lines.

NOTE

If you make a mistake when combining multiple conditions with brackets, you are informed in the status line.

NOTE

If you have already defined filter conditions and/or applied a preset, but want to start again from scratch, you can initialize the settings by selecting the **Init** option from the **Presets** pop-up menu.

RELATED LINKS

[Searching for Elements at Specific Positions](#) on page 881
[Combining Multiple Condition Lines](#) on page 885

Searching for Media Types

You can search for elements by their media type.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Media Type**.
 2. Open the **Parameter 1** pop-up menu and select the media type that you want to search for.
 3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Equal** if you want to search for the specified media type.
 - Select **Unequal** if you want to search for any other media type than the specified.
 - Select **All Types** if you want to search for all media types.
-

Media Type Filter

When the **Filter Target** is set to **Media Type**, the pop-up menu lists the available media types.

Audio

If no container type is specified, this finds audio events, audio parts and audio tracks.

MIDI

If no container type is specified, this finds MIDI parts and MIDI tracks.

Automation

If no container type is specified, this finds automation events and automation tracks.

Marker

If no container type is specified, this finds marker events and marker tracks.

Transpose

If no container type is specified, this finds transpose events and transpose tracks.

Arranger

If no container type is specified, this finds arranger events and arranger tracks.

Tempo

If no container type is specified, this finds tempo events and tempo tracks.

Signature

If no container type is specified, this finds signature events and signature tracks.

Chord

If no container type is specified, this finds chord events and chord tracks.

Scale Event

If no container type is specified, this finds scale events.

Video

If no container type is specified, this finds video events.

Group

If no container type is specified, this finds group tracks.

Effect

If no container type is specified, this finds FX channel tracks.

Device

If no container type is specified, this finds device tracks.

VCA

If no container type is specified, this finds VCA fader tracks.

For media types, the following options are available:

Equal

This finds the media type set up in the **Parameter 1** column.

All Types

This finds all media types.

Searching for Container Types

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Container Type**.
2. Open the **Parameter 1** pop-up menu and select the container type that you want to search for.
3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Equal** if you want to search for the specified container type.

- Select **Unequal** if you want to search for any other container type than the specified.
- Select **All Types** if you want to search for all container types.

EXAMPLE

You can set up the **Project Logical Editor** to find all folder tracks in the project.

Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base
Container Type is	Equal	FolderTrack		

Container Type Filter

When the **Filter Target** is set to **Container Type**, the pop-up menu lists the available container types.

Folder Track

This finds all folder tracks, included FX channel and group channel folders.

Track

This finds all track types.

Part

This finds audio, MIDI, and instrument parts. Folder parts will not be found.

Event

This finds automation points, markers, as well as audio, arranger, transpose, tempo and time signature events.

For container types, the following options are available:

Equal

This finds the container type set up in the **Parameter 1** column.

All Types

This finds all container types.

Combining Media Type and Container Type

The combination of the filter targets **Media Type** and **Container Type** represents a versatile tool for logical operations.

EXAMPLE

You can set up the **Project Logical Editor** to find all MIDI and instrument parts in the project.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Media Type is	Equal	MIDI)	And
	Container Type is	Equal	Part)	

You can set up the **Project Logical Editor** to find all automation tracks (not events) in the project whose name contains vol.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Media Type is	Equal	Automation)	And
	Container Type is	Equal	Track)	And
	Name	Contains	vol)	

You can set up the **Project Logical Editor** to find all MIDI and instrument parts (not tracks) in the project that are muted.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Media Type is	Equal	MIDI)	And
	Container Type is	Equal	Part)	And
	Property	Not set	Event is muted)	

You can set up the **Project Logical Editor** to find all MIDI and instrument parts (not tracks) or all audio events (not parts or tracks) in the project that are muted.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
((Media Type is	Equal	MIDI)	And
	Container Type is	Equal	Part)	Or
(Media Type is	Equal	Audio)	And
	Container Type is	Equal	Event)	And
	Property	Property is not set	Event is muted)	

Searching for Names

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Name**.
 2. Open the **Parameter 1** pop-up menu and enter a name, or a part of a name that you want to search for.
 3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Equal** if you want to search for the exact name.
 - Select **Contains** if you want to search for a name that contains the specified name.
 - Select **Contains not** if you want to search any other name than the specified.
-

EXAMPLE

You can set up the **Project Logical Editor** to find all tracks in the project whose name contains **voc**.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Container Type is	Equal	Track)	And
	Name	Contains	voc)	

Searching for Elements at Specific Positions

You can search for elements starting at specific positions, either relative to the start of the project or within each bar.

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Position**.
This allows you to find elements starting at specific positions, either relative to the start of the project or within each bar.
 2. Open the **Condition** pop-up menu and select one of the following options:
 - To find all elements at a specific position, select a position in the **Parameter 1** column.
You can set a time base such as PPQ, seconds, samples, or frames in the **Bar Range/Time Base** column.
 - To find all elements inside or outside a range, select **Inside Bar Range** or **Outside Bar Range**.
You can set the bar range in the **Bar Range/Time Base** column by clicking and dragging in the bar display or by adjusting the start position of the range in the **Parameter 1** column and the end position in the **Parameter 2** column. You can change the time base use the **Bar Range/Time Base** column. The position for **Bar Range** is measured in ticks related to the start of the bar.
-

EXAMPLE

You can set up the **Project Logical Editor** to find all elements at the PPQ position 5.1.1. in the project.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Position	Equal	5.01.01.000		PPQ)	

You can set up the **Project Logical Editor** to find elements starting around the second beat in each bar.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
(Position	Inside Bar Range	419	541	)	

Position Filter

For positions, the following options are available:

Equal

Has the exact same value as set up in the **Parameter 1** column.

Unequal

Has any value other than the one set up in the **Parameter 1** column.

Bigger

Has a value higher than the one set up in the **Parameter 1** column.

Bigger or Equal

Has a value that is the same as or higher than the one set up in the **Parameter 1** column.

Less

Has a value lower than the one set up in the **Parameter 1** column.

Less or Equal

Has a value that is the same as or lower than the one set up in the **Parameter 1** column.

Inside Range

Has a value that is between the values set up in the **Parameter 1** and **Parameter 2** columns. Note that **Parameter 1** should be the lower value and **Parameter 2** the higher.

Outside Range

Has a value that is not between the values set up in the **Parameter 1** and **Parameter 2** columns.

Inside Bar Range

Is within the zone set up in the **Bar Range/Time Base** column, in each bar within the current selection.

Outside Bar Range

Is outside the zone set up in the **Bar Range/Time Base** column, in each bar within the current selection.

Before Cursor

Is before the cursor position.

Beyond Cursor

Is after the cursor position.

Inside Track Loop

Is inside the set track loop.

Inside Cycle

Is inside the set cycle.

Exactly Matching Cycle

Exactly matches the set cycle.

Searching for Elements of Specific Lengths

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Length**.
This allows you to find elements of a specific length only.

NOTE

The **Length** parameter is interpreted via the time base setting in the **Bar Range/Time Base column**, that is, in PPQ, seconds, samples, or frames.

2. Open the **Parameter 1** pop-up menu and set the length that you want to search for.
3. Open the **Condition** pop-up menu and select an option.
If you select **Inside Range** or **Outside Range**, use **Parameter 1** and **Parameter 2** to set the start and the end of the range.

EXAMPLE

You can set up the **Project Logical Editor** to find all audio parts and events in the project with a length value below 200 samples.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Container Type is	Equal	Part				Or
	Container Type is	Equal	Event				And
(Media Type is	Equal	Audio				And
	Length	Less	0200		Samples)	

RELATED LINKS

[Lengths Filter](#) on page 883

Lengths Filter

For lengths, the following options are available:

Equal

Has the exact same value as set up in the **Parameter 1** column.

Unequal

Has any value other than the one set up in the **Parameter 1** column.

Bigger

Has a value higher than the one set up in the **Parameter 1** column.

Bigger or Equal

Has a value that is the same as or higher than the one set up in the **Parameter 1** column.

Less

Has a value lower than the one set up in the **Parameter 1** column.

Less or Equal

Has a value that is the same as or lower than the one set up in the **Parameter 1** column.

Inside Range

Has a value that is between the values set up in the **Parameter 1** and **Parameter 2** columns. Note that **Parameter 1** should be the lower value and **Parameter 2** the higher.

Outside Range

Has a value that is not between the values set up in the **Parameter 1** and **Parameter 2** columns.

Searching for Color Names

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Color Name**.
 2. Open the **Parameter 1** pop-up menu and enter the color name for which you want to search.
You can also select the color from the pop-up menu.
 3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Equal** if you want to search for the exact color name.
 - Select **Contains** if you want to search for a color name that contains the specified color name.
 - Select **Contains not** if you want to search any other color name than the specified name.
-

Searching for Properties

PROCEDURE

1. Open the **Filter Target** pop-up menu and select **Property**.
 2. Open the **Parameter 1** pop-up menu and select the property that you want to search for.
 3. Open the **Condition** pop-up menu and select one of the following options:
 - Select **Property is set** if you want to search for events that have the specified property.
 - Select **Property is not set** if you want to search for events that do not have the specified property.
-

EXAMPLE

You can set up the **Project Logical Editor** to find all muted MIDI and instrument parts.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Media Type is	Equal	MIDI				And
	Container Type is	Equal	Part				And
	Property	Property is set	Event is muted				

You can set up the **Project Logical Editor** to find all elements that are empty.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Media Type is	Equal	Audio				And
	Container Type is	Equal	Part				And
	Property	Property is set	Event is selected				And
	Property	Property is set	Event is empty				

You can set up the **Project Logical Editor** to find all selected audio parts that are selected but not muted.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Property	Property is set	Event is selected				And
	Property	Property is not set	Event is muted				

Properties Filter

For properties, the following options are available:

Property is set

This finds all events that have the property that is set in the **Parameter 1** column.

Property is not set

This finds all events that do not have the property that is set in the **Parameter 1** column.

When the **Filter Target** is set to **Property**, the pop-up menu lists the available properties.

Event is muted

This finds all muted events.

Event is selected

This finds all selected events.

Event is empty

This finds all empty events.

Event inside NoteExp

This finds all events that form part of Note Expression automation data. These can be VST 3 or MIDI controller events.

Event is valid VST 3

This finds all VST3 events in a note that are valid. This means that the corresponding track is routed to an instrument that supports them.

Is Hidden

This finds all hidden tracks.

Has TrackVersion

This finds all tracks that have TrackVersions.

Follows Chord Track

This finds all tracks that follow the chord track.

Is Disabled

This finds all disabled tracks.

Combining Multiple Condition Lines

You can add condition lines and combine them by using boolean And and Or operators and brackets.

- To add a new condition, click **+** below the list.
The new line is added at the bottom of the list.
- To remove a condition, select it and click **-** below the list.

The Bool Column

In the **bool** column to the right in the list, you can select a boolean operator: And or Or.

A boolean operator combines 2 condition lines and determines the result in the following way:

- And determines that both conditions must be fulfilled for an element to be found.
- Or determines that at least one of the conditions must be fulfilled for an element to be found.

IMPORTANT

When you add a new condition line, the boolean setting defaults to And.

EXAMPLE

You can set up the **Project Logical Editor** to find MIDI tracks.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Media Type is	Equal	MIDI				And
	Container Type is	Equal	Track				

You can set up the **Project Logical Editor** to find all parts or events that match exactly the cycle.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Container Type is	Equal	Part				Or
	Container Type is	Equal	FolderTrack				And
	Position	Exactly Matching Cycle			PPQ		

Using Brackets

The bracket columns let you enclose 2 or more condition lines, dividing the conditional expression into smaller units. This is only relevant when you have 3 or more condition lines and want to use the boolean Or operator.

You can add brackets by clicking in the bracket columns and selecting an option. Up to triple brackets can be selected.

If you add several layers of brackets, these are evaluated from the inside out, starting with the innermost brackets.

Expressions within brackets are evaluated first.

EXAMPLE

You can set up the **Project Logical Editor** to find all audio parts and events whose name contains perc as well as other MIDI parts and events whose name contains drums.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Media Type is	Equal	Audio				And
	Name	Contains	perc				Or
	Name	Contains	drums				

You can set up the **Project Logical Editor** to find all audio parts or events whose name contains perc or drums.

(Filter Target	Condition	Parameter 1	Parameter 2	Bar Range/Time Base)	bool
	Media Type is	Equal	Audio				And
(Name	Contains	perc				Or
	Name	Contains	drums)	

Specifying Actions

You can specify actions, that is, changes that are made to the found elements, in the lower list of the **Project Logical Editor**. Actions are only relevant for the function type **Transform**.

Action Target	Operation	Parameter 1	Parameter 2
Track Operation	Record	Toggle	

You can perform the following action types:

- Track-based actions such as **Track Operation, Name**
- Event-based actions such as **Position, Length, Name**.

- Actions that only take effect on automation data such as **Trim**.

You can add action lines by clicking , and remove them by selecting it and clicking .

Action Target

The **Action Target** allows you to select the property that is changed.

Position

Adjusting the **Position** value moves the elements.

This parameter is interpreted via the time base setting in the **Bar Range/Time Base** column, with the exception of the **Random** setting, which uses the time base of the affected events:

Add

Adds the value specified in the **Parameter 1** column to the **Position**.

Subtract

Subtracts the value specified in the **Parameter 1** column from the **Position**.

Multiply by

Multiplies the **Position** value with the value specified in the **Parameter 1** column.

Divide by

Divides the **Position** value by the value specified in the **Parameter 1** column.

Round by

This rounds the **Position** value using the value specified in the **Parameter 1** column. In other words, the **Position** value is changed to the closest value that can be divided by the **Parameter 1** value.

Set relative Random Values between

This will add a random value to the current **Position** value. The added random value will be within the range specified with **Parameter 1** and **Parameter 2**. Note that these can be set to negative values.

Set to fixed value

This sets the position to the value specified in the **Parameter 1** column.

Length

Adjusting the **Length** value allows you to resize the elements.

This parameter is interpreted via the time base setting in the **Bar Range/Time Base** column, with the exception of the **Random** setting, which uses the time base of the affected events:

Add

Adds the value specified in the **Parameter 1** column to the **Length**.

Subtract

Subtracts the value specified in the **Parameter 1** column from the **Length**.

Multiply by

Multiplies the **Length** value with the value specified in the **Parameter 1** column.

Divide by

Divides the **Length** value by the value specified in the **Parameter 1** column.

Round by

This rounds the **Length** value using the value specified in the **Parameter 1** column. In other words, the **Length** value is changed to the closest value that can be divided by the **Parameter 1** value.

Set to fixed value

This sets the **Length** to the value specified in the **Parameter 1** column.

Set Random Values between

This will add a random value to the current length. The added random value will be within the range specified with **Parameter 1** and **Parameter 2**.

Track Operation

Adjusting the **Track Operation** value allows you to change the track status.

NOTE

Track operations may also affect automation tracks. This may lead to unexpected results, especially if you use the **Toggle** action.

Folder

Opens, closes, or toggles folders.

Record

Enables, disables, or toggles the record enable status.

Monitor

Enables, disables, or toggles the monitor status.

Solo

Enables, disables, or toggles the solo status.

Mute

Enables, disables, or toggles the mute status.

Read

Enables, disables, or toggles the read enable status.

Write

Enables, disables, or toggles the write enable status.

EQ Bypass

Enables, disables, or toggles the EQ bypass status.

Inserts Bypass

Enables, disables, or toggles the inserts bypass status.

Sends Bypass

Enables, disables, or toggles the sends bypass status.

Lanes Active

Enables, disables, or toggles the lanes active status.

Hide Track

Enables, disables, or toggles the track visibility status.

Time Domain

Sets the track time domain to **Musical**, **Linear**, or toggles the status.

Name

Adjusting the **Name** value allows you to rename the found elements.

Replace

Replaces names with the text specified in the **Parameter 1** column.

Append

Names will be appended with the string specified in the **Parameter 1** column.

Prepend

The name will be prepended with the string specified in the **Parameter 1** column.

Generate Name

The name will be replaced by the text specified in the **Parameter 1** column, followed by the number set with **Parameter 2**. The number will be increased by 1 for every found element.

Replace Search String

You can specify a search string under **Parameter 1** that is replaced by the text specified in the **Parameter 2** column.

Trim

Adjusting the **Trim** value allows you to trim the found elements. This is used for automation only.

Multiply by

Multiplies the **Trim** value with the value specified in the **Parameter 1** column.

Divide by

Divides the Trim value by the value specified in the **Parameter 1** column.


Set Color

Adjusting the **Set Color** value allows you to set the color for an element.

For this **Action Target**, you can select the operation **Set to fixed value**. To set a specific color, click the **Parameter 1** column and select the item in the pop-up menu.

Selecting a Function

The left pop-up menu at the bottom of the **Project Logical Editor** is where you select the function – the basic type of editing to be performed.



The available options are:

Delete

Deletes all elements found by the **Project Logical Editor**.

NOTE

When you delete automation tracks and undo this operation by selecting **Undo** from the **Edit** menu, the automation tracks will be restored, but the tracks will be closed.

Transform

Changes one or several aspects of the found elements. You set up exactly what is changed in the action list.

Select

This will simply select all found elements, highlighting them for further work in the **Project** window.

Applying Macros

In the **Macro** pop-up menu you can select a macro that will be executed automatically after completing the actions defined.

To use this, you set up the macro that you need in the **Key Commands** dialog and then select it in the **Project Logical Editor** from the **Macro** pop-up menu.

EXAMPLE

Use the filter conditions to select all tracks that contain automation data for the volume automation parameter. In the **Function** pop-up menu select **Delete**, and in the **Macro** pop-up menu select **Select all on Track**. This removes the automation events from these tracks.

RELATED LINKS

[Key Commands](#) on page 973

Applying the Defined Actions

Once you have set up filter conditions, selected a function and set the required actions or loaded a preset, you apply the actions defined with the **Project Logical Editor** by clicking the **Apply** button.

Project Logical Editor operations can be undone just like any other editing.

Presets

The section in the upper left section of the window allows you to load, save and manage **Project Logical Editor** presets.

To load a preset, do one of the following:

- Open the **Select Preset** pop-up menu, and select an option.
- Select **Edit > Process Project Logical Editor**, and select an option.

NOTE

If you set up a key command for a preset you can conveniently apply the same operation to several selected events in one go.

RELATED LINKS

[Key Commands](#) on page 973

Storing Your Own Settings as Presets

You can save settings that you want to use again as presets.

PROCEDURE

1. In the section in the upper left of the **Project Logical Editor**, click **Store Preset**.
2. In the dialog that opens, specify a name for the preset and click OK.

RESULT

The preset is stored.

NOTE

To remove a preset, load it and click the **Remove Preset** button.

Organizing and Sharing Presets

The **Project Logical Editor** presets are stored within the application folder in the **Presets \Logical Edit Project** subfolder.

Preset files cannot be edited manually, but you can reorganize them. This also makes it easy to share presets with other Cubase users, by transferring the individual preset files.

NOTE

The list of presets is read each time the **Project Logical Editor** is opened.

Setting up Key Commands for Your Presets

If you have stored **Project Logical Editor** presets, you can set up key commands for them.

PROCEDURE

1. Select **File > Key Commands**.
2. In the **Commands** column navigate to the category **Process Project Logical Editor** and click the plus sign to display the items in the folder.
3. In the list, select the item to which you want to assign a key command, click in the **Type in Key** field and enter a new key command.
4. Click the **Assign** button above the field.
The new key command is shown in the **Keys List**.
5. Click **OK**.

RELATED LINKS

[Key Commands](#) on page 973

Editing Tempo and Time Signature

Project Tempo Modes

For every project you can set a tempo mode, depending on whether your music has a fixed tempo or if it changes throughout the project.

On the **Transport** panel, you can set the following tempo modes:

- **Fixed Tempo Mode**

If you want to work with one fixed tempo that does not change throughout the project, deactivate **Activate Tempo Track** on the **Transport** panel. You can change the tempo value to set a fixed rehearsal tempo.



- **Tempo Track Mode**

If the tempo of your music contains tempo changes, activate **Activate Tempo Track** on the **Transport** panel. You can change the tempo value to change the tempo at the cursor. If your project does not contain any tempo changes, the tempo is changed at the project start.



RELATED LINKS

[Setting up Projects for Tempo Changes](#) on page 896

Track Time Base

The time base of a track determines if a track can follow the tempo changes of a project that is set to tempo track mode.

In the **Inspector** for MIDI tracks, instrument tracks, and audio related tracks, you can activate/deactivate **Toggle Time Base** to switch the track time base.

The following time base modes are available:

- **Musical**

Use this mode for material with a musical, that is, tempo-related time base. All tracks that are set to musical time base follow any tempo changes that you add on the tempo track.

NOTE

For audio events on audio tracks that are set to musical time base, the tempo changes on the tempo track affect only the start position and not the actual audio.

- **Linear**
Use this mode for material with a linear, time-related time base.

RELATED LINKS

[Instrument Track Inspector](#) on page 105


[MIDI Track Inspector](#) on page 112

[Audio Track Inspector](#) on page 98

Tempo Track Editor

The **Tempo Track Editor** provides an overview of the project tempo settings. It allows you to add and edit tempo events.

- To open the **Tempo Track Editor**, select **Project > Tempo Track**, or press **Ctrl/Cmd-T**.



The **Tempo Track Editor** is divided into several sections:

- 1 **Tempo scale**
Shows the tempo scale in BPM.
- 2 **Toolbar**
Contains tools for selecting, adding, and changing tempo and time signature events.
- 3 **Info line**
Shows information about the selected tempo or time signature event.
- 4 **Ruler**
Shows the timeline and the display format of the project.
- 5 **Time signature display**
Shows the time signature events in the project.
- 6 **Tempo curve display**
If your project is set to a fixed tempo, only one tempo event and a fixed tempo is shown.
If your project is set to tempo track mode, the curve display shows the tempo curve with the tempo events in the project.

Toolbar

The toolbar contains tools for selecting, adding, and changing tempo and time signature events.

The following tools are available:

Activate Tempo Track



Switches the project tempo between fixed tempo mode and tempo track mode.

Show/Hide Info



Opens/Closes the info line.

Tools



Contains tools to select, erase, zoom, and draw.

Auto-Scroll




Allows the tempo event display to scroll during playback, keeping the project cursor visible in the editor.

Snap




Allows you to restrict horizontal movement and positioning of tempo events to certain positions. Time signature events always snap to the beginning of bars.

Type of New Tempo Points



Allows you to select the type of new tempo points. Select **Ramp** if you want new tempo points to change gradually from the previous curve point to the new one. Select **Jump** if you want new tempo points to change instantly. Select **Automatic** if new tempo points should have the same type as the previous curve point.

Current Tempo



In fixed tempo mode, this allows you to change the current tempo.

Tempo Recording Slider



Allows you to record tempo changes.

Open Process Tempo Dialog



Opens the **Process Tempo** dialog.

Open Process Bars Dialog



Opens the **Process Bars** dialog.

Tempo Track

You can use the tempo track to create tempo changes within a project.

- To add a tempo track to your project, select **Project > Add Track > Tempo**.
- You can use the tools on the **Project** window toolbar to add and edit tempo events.
- You can use the tempo event editor to edit selected tempo events.
- To select a tempo event, click it with the **Object Selection** tool.

- To select multiple events, drag a selection rectangle with the **Object Selection** tool or **Shift**-click the events.
- To select all tempo events on the tempo track, right-click the tempo track and select **Select All Events** from the context menu.

RELATED LINKS

[Tempo Track Inspector](#) on page 144


[Tempo Track Controls](#) on page 145

Tempo Event Editor

The tempo event editor allows you to edit selected events on the tempo track.

- To open the tempo event editor, activate the **Object Selection** tool and drag a selection rectangle on the tempo track.

The tempo event editor features the following smart controls for specific editing modes:



1 Tilt Left

If you click in the upper left corner of the editor, you can tilt the left part of the curve. This allows you to tilt the event values at the start of the curve upwards or downwards.

2 Compress Left

If you **Alt**-click in the upper left corner of the editor, you can compress or expand the left part of the curve. This allows you to compress or expand the event values at the start of the curve.

3 Scale Vertically

If you click in the middle of the upper border of the editor, you can scale the curve vertically. This allows you to raise or lower the event values of the curve in percent.

4 Move Vertically

If you click on the upper border of the editor, you can move the entire curve vertically. This allows you to raise or lower the values of the event values of the curve.

5 Compress Right

If you **Alt**-click in the upper right corner of the editor, you can compress or expand the right part of the curve. This allows you to compress or expand the event values at the end of the curve.

6 Tilt Right

If you click in the upper right corner of the editor, you can tilt the right part of the curve. This allows you to tilt the event values at the end of the curve upwards or downwards.

7 Scale Around Relative Center

If you **Alt**-click in the middle right border of the editor, you can scale the curve relative to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

8 Scale Around Absolute Center

If you click in the middle right corner of the editor, you can scale the curve absolute to its center. This allows you to raise or lower the event values horizontally around the center of the editor.

9 Stretch

If you click on the lower border of the editor, you can stretch the curve horizontally. This allows you to move the event values of the curve to the left or to the right.

Setting up Tempo Changes for Projects

If the tempo track is activated, you can set up tempo changes for your project.

IMPORTANT

If your project is set to tempo track mode and you set up tempo changes, only tracks that are set to musical time base follow the tempo changes.

NOTE

If you work in tempo track mode, make sure that the display format in the **Project** window ruler is set to **Bars+Beats**. Otherwise, you may get confusing results.

If you activate **Activate Tempo Track** in the **Transport** panel, the tempo track curve is displayed in the tempo curve display.

If you know the tempo of your music, you can adjust the tempo value as follows:

- By adding tempo events in the **Tempo Track Editor**.
- By recording tempo changes with the **Tempo Recording slider** on the toolbar of the **Tempo Track Editor**.
- By adding tempo events on the tempo track.
- By importing tempo tracks (Cubase Pro only).

Cubase Pro only: If you do not know the tempo of your music, Cubase offers tools to calculate and set it:

- **Tempo Detection Panel**
- **Time Warp** tool
- **Process Bars** dialog
- **Process Tempo** dialog

RELATED LINKS

[Setting up Projects for Tempo Changes](#) on page 896

Setting up Projects for Tempo Changes

When you create a new project, the project tempo is automatically set to fixed tempo mode. If your music contains tempo changes, you must set your project to tempo track mode.

PROCEDURE

- To set your project to tempo track mode, do one of the following:
 - On the **Transport** panel, activate **Activate Tempo Track**.
 - Select **Project > Tempo Track** and activate **Activate Tempo Track**.
 - Select **Project > Add Track > Tempo** and activate **Activate Tempo Track**.
-

RESULT

The project tempo is now set up to follow the tempo track.

All tracks that are set to musical (tempo-related) time base follow any tempo changes that you add on the tempo track.

RELATED LINKS

[Track Time Base](#) on page 892

[Tempo Track Controls](#) on page 145

[Tempo Track Editor](#) on page 893

Setting up a Tempo Track by Adding Tempo Changes

PROCEDURE

1. Do one of the following:
 - Select **Project > Tempo Track** to open the **Tempo Track Editor**.
 - Select **Project > Add Track > Tempo** to add a tempo track to your project.
2. Open the **Type of New Tempo Points** pop-up menu and select an option.
3. Do one of the following:
 - On the toolbar, select the **Object Selection** tool and click the tempo curve.
 - On the toolbar, select the **Draw** tool, and click and drag in the tempo curve display.

NOTE

If **Snap** is activated, this determines at which time positions you can insert tempo curve points.

RESULT

The tempo event is added to the tempo curve.

Setting up a Tempo Track by Recording Tempo Changes (Cubase Pro only)

You can set up a complete tempo track by recording tempo changes. This is useful if you want to create natural sounding ritardandos, for example.

PROCEDURE

1. Open the project for which you want to set up a tempo track and start playback.
 2. Select **Project > Tempo Track**.
 3. On the **Tempo Track Editor** toolbar, use the Tempo Recording Slider to add tempo changes on the fly.
By moving the slider to the right, you can raise the project tempo, by moving it to the left, you can lower it.
-

RESULT

The tempo changes are recorded and added to the tempo curve in the **Tempo Track Editor**.

RELATED LINKS

[Toolbar](#) on page 893

Setting up a Tempo Track from Tapping (Cubase Pro only)

You can create a complete tempo track based on tapping the tempo of freely recorded audio or MIDI material.

PREREQUISITE

You have opened a project with a freely recorded audio or MIDI file. You have added an instrument track and loaded an instrument. You have connected and set up a MIDI keyboard.

PROCEDURE

1. In the instrument track **Inspector**, deactivate **Toggle Time Base** to set the track time base to linear.
2. On the instrument track, activate **Record Enable**.
3. On the **Transport** panel, activate **Record**.
4. On the MIDI keyboard, tap the tempo by hitting a key to the beat of your music.
5. Stop recording and play back the recorded MIDI notes together with the original recording to check if the timing is correct.
6. Do one of the following:
 - Select the MIDI part in the **Project** window.
 - Open the MIDI part in the **Key Editor** and select the notes that you want to use for the calculation.
7. Select **MIDI > Functions > Merge Tempo From Tapping**.
8. Open the **Tapping** pop-up menu to specify what type of note you tapped during the recording.
9. Optional: To start the calculation of the tempo curve at the beginning of a bar, activate **Begin at Bar Start**.
10. Click **OK**.

RESULT

The project tempo is set to the tapped tempo.

AFTER COMPLETING THIS TASK

Open the **Tempo Track Editor** to see and edit the new tempo curve.

RELATED LINKS

[Setting Up All MIDI Inputs](#) on page 19

Setting up a Tempo Track from Tempo Detection (Cubase Pro only)

You can set up a complete tempo track using the result of a tempo detection for an audio event or a MIDI part.

PROCEDURE

1. In the **Project** window, select the audio event or the MIDI part that you want to analyze.
2. Select **Project > Tempo Detection**.
3. In the **Tempo Detection Panel**, click **Analyze**.

RESULT

- A tempo track is added to the project. On the tempo track, tempo events are created based on the analysis for the selected audio event or MIDI part.

- A signature track is added to the project. On the signature track, a signature event with the value 1/4 is added.
- On the **Project** window toolbar, the **Time Warp** tool is selected.

AFTER COMPLETING THIS TASK

Depending on the rhythmic quality of the material, the analysis may instantly lead to a perfect result. You can verify the quality of the analysis by activating the metronome click in the **Transport** panel, and playing back the project. To correct the result manually, use the functions in the **Tempo Detection Panel**.

RELATED LINKS

[Tempo Detection Panel](#) on page 903

[Correcting the Analysis Manually](#) on page 899

Correcting the Analysis Manually

If your music contains sections that are played in a different tempo or with special rhythmic characteristics, for example, you must adjust the tempo events manually.

PREREQUISITE

You have analyzed your material and the **Tempo Detection Panel** is still open. The metronome click is activated.

PROCEDURE

1. Play back the track with the analyzed material from the beginning and listen to the click.
2. Optional: If you work with an audio event, zoom in on the waveform so that you can compare the transients with the tempo events on the tempo track.
3. Optional: If the first tempo event that is not placed correctly is located at the beginning of the material, click the left arrow button in the **Tempo Detection Panel** to change the direction of the reanalysis.
4. Select the **Time Warp** tool and move the first tempo event that is not placed correctly to the correct position.

RESULT

The material is reanalyzed and the tempo recalculated.

AFTER COMPLETING THIS TASK

Continue listening to the material and correcting tempo events until the end. Close the **Tempo Detection Panel**.

NOTE

If your material includes multiple sections with different tempo, you can also cut the material at each major tempo change and perform a tempo detection for every single resulting section. Remember that each section must have a length of at least 7 seconds.

Editing Tempo Events

In the **Tempo Track Editor**, you can edit selected tempo events.

Use the following methods:

- With the **Object Selection** tool, click and drag horizontally and/or vertically.
- On the **Info Line**, adjust the tempo value in the **Value** field.

NOTE

When editing tempo events on tempo curves, make sure that the display format in the **Project** window ruler is set to **Bars+Beats**. Otherwise, you may get confusing results.

Use the following methods to remove tempo events:

- With the **Erase** tool, click the tempo event.
- Select the tempo event and press **Backspace**.

NOTE

You cannot remove the first tempo event.

Use the following method to change the tempo curve type:

- On the **Info Line**, adjust the tempo curve type in the **Type** field.

Adjusting the Tempo of a Range (Cubase Pro only)

You can adjust the tempo of a range to match a specific length or end time.

PROCEDURE

1. Set the left and right locator to specify the start and the end of the range you want to adjust.
 2. Select **Project > Tempo Track**.
 3. Click **Open Process Tempo Dialog**.
 4. Open the **Time Display Format** pop-up menu and select a time display format for the new range.
 5. In the **New Range** section, enter a new end time or a new length for the range.
 6. Click **Process**.
-

RESULT

The range is adjusted to match the new end time or the new length. The tempo track is adjusted to show the new tempo of the range.

Setting up a Fixed Project Tempo

If your music does not contain tempo changes, and the tempo track is deactivated, you can set up a fixed tempo for your project.

When the tempo track is deactivated, the tempo track curve is grayed out. The fixed tempo is displayed as a horizontal line in the tempo curve display.

If you know the tempo of your music, you can adjust the tempo value in the following areas:

- **Tempo** field on the **Transport** panel
- **Current Tempo** field on the **Tempo Track Editor** toolbar
- **Current Tempo** field on the tempo track

If you do not know the tempo of your music, use one of the following tools to calculate and set it:

- Beat Calculator
- Merge Tempo From Tapping (Cubase Pro only)
- Set Project Tempo from Loop

RELATED LINKS

[Setting the Project Tempo from a Recording](#) on page 901

[Setting the Project Tempo by Tapping](#) on page 901

[Setting the Project Tempo from an Audio Loop](#) on page 902

Setting the Project Tempo from a Recording

You can calculate the tempo of freely recorded audio or MIDI material with the **Beat Calculator** and set it as the project tempo.

PREREQUISITE

The tempo mode is set to **Fixed**.

PROCEDURE

1. On the **Project** window toolbar, select the **Range Selection** tool.
 2. In the event display, make a selection that covers an exact number of beats of the recording.
 3. Select **Project > Beat Calculator**.
 4. In the **Beats** value field, enter the number of beats that the selection encompasses. The calculated tempo is shown in the **BPM** field.
 5. In the **Insert Tempo into Tempo Track** section, click **At Tempo Track Start**.
-

RESULT

The project tempo is set to the tempo calculated from your recording.

RELATED LINKS

[Beat Calculator](#) on page 902

Setting the Project Tempo by Tapping

You can set the tempo of freely recorded audio or MIDI material by tapping.


PREREQUISITE

The tempo mode is set to **Fixed**.

PROCEDURE

1. Activate playback.
2. Select **Project > Beat Calculator**.
3. Click **Tap Tempo**.

The **Tap Tempo** window opens.



4. Use **Space** to tap the tempo of the recording that is played back. In the **BPM** field, the calculated tempo is updated each time you tap.
5. Click **OK** to close the window. The tapped tempo is shown in the **BPM** field of the **Beat Calculator**.

6. Click one of the buttons in the **Insert Tempo into Tempo Track** section to insert the calculated tempo into the tempo track.
-

RESULT

The project tempo is set to the tapped tempo.

RELATED LINKS

[Setting up a Fixed Project Tempo](#) on page 900

Setting the Project Tempo from an Audio Loop

You can set the project tempo from the tempo of an audio loop.

PREREQUISITE

Your project contains an audio loop that is not in **Musical Mode**.

PROCEDURE


1. In the **Project** window ruler, set the left locator to the beginning of the audio loop.
 2. Set the right locator to the end of the last bar.
This does not need to match the end of the audio loop, but its number of bars.
 3. Select the audio loop.
 4. Select **Audio > Advanced > Set Tempo from Event**.
You are asked if you want to set the global project tempo.
 5. Perform one of the following actions:
 - Click **Yes** to adjust the project tempo globally.
 - Click **No** to adjust the project tempo only in the section of the audio event.
-

RESULT

The project tempo is set to the tempo calculated for the audio loop.

Beat Calculator

The **Beat Calculator** is a tool for calculating the tempo of freely recorded audio or MIDI material. It also allows you to set the tempo by tapping.



- To open the **Beat Calculator** for an audio or MIDI recording, select **Project > Beat Calculator**.
- 1 **Beats**
Allows you to enter the number of beats for the selected section of your recording.
 - 2 **BPM**
Shows the tempo calculated for the selection.

3 Tap Tempo

Opens a window where you can specify a tempo by tapping.

4 Insert Tempo into Tempo Track at Tempo Track Start

If your project is in tempo track mode, the calculated tempo is set as the first tempo curve point. If your project is in fixed tempo mode, the calculated tempo is set for the entire project.

5 Insert Tempo into Tempo Track at Selection Start

If your project is in tempo track mode, the calculated tempo is set as a new tempo event at the start of the selection.

6 Refresh

Allows you to recalculate the tempo. This is useful if you adjust the selection, for example.

Tempo Detection (Cubase Pro only)

You can detect the tempo of any rhythmic musical content, even if it has not been recorded to a metronome click or if it contains tempo drift.

Detecting the tempo of musical material is useful for the following cases:

- If you want your audio or MIDI tracks to follow the tempo of freely recorded material.
- If you want to adjust freely recorded material to the project tempo.


To perform a tempo detection, the following requirements must be met:

- The audio event or MIDI part must be at least 7 seconds long.
- The material must have discernible beats or rhythms.

Tempo Detection Panel

The **Tempo Detection Panel** allows you to analyze the tempo of audio events or MIDI parts.

- To open the **Tempo Detection Panel** for an audio event or a MIDI part, select the event or the part and select **Project > Tempo Detection**.



1 Name

Shows the name of the selected event or part.

2 Analyze

Starts the tempo detection.

3 Multiply by 2

Allows you to double the detected tempo. This is useful if your material is twice as fast as the detected tempo.

4 Divide by 2

Allows you to halve the detected tempo. This is useful if your material is half as fast as the detected tempo.

5 Multiply by 4/3

Allows you to adjust the detected tempo with a factor of 4/3. This is useful if your material contains dotted notes or triplets and the algorithm detects 3 beats where 4 are expected.

6 Multiply by 3/4

Allows you to adjust the detected tempo with a factor of 3/4. Combined with **Multiply by 2**, this is useful if the actual signature is 2/4 and the algorithm detects 6/8 beats or vice versa.

7 Offbeat Correction

Allows you to shift the detected tempo events by half a beat. This is useful for material where the offbeat is so dominant that the algorithm mistakes it for an upbeat.

8 Smooth Tempo

Allows you to retrigger the tempo analysis and removes irregular spikes or tempo changes for material that has a steady tempo. This is useful if irregular tempo changes were detected, even though you know that the material has a more or less steady tempo.

9 Direction of reanalysis

When you correct the detected tempo curve by reanalyzing it manually, these buttons allow you to change the direction in which the material is analyzed. To reanalyze the beginning of the tempo curve, activate the left arrow button.

10 Reset

Resets the analysis data.

Exporting a Tempo Track (Cubase Pro only)

You can export a tempo track as an XML file to use it in other projects.

PROCEDURE

1. Select **File > Export > Tempo Track**.
2. In the file dialog that opens, specify a name and a location for the file.
3. Click **Save**.

RESULT

The tempo track information is saved together with signature events with the file extension **.smt**.

Importing a Tempo Track (Cubase Pro only)

You can import a tempo track from another project.

PROCEDURE


1. Select **File > Import > Tempo Track**.
2. In the file dialog that opens, navigate to the file you want to import.
3. Click **Open**.

RESULT

The tempo track is imported to your project together with signature events. All tempo track data in the project is replaced.

Process Tempo (Cubase Pro only)

The **Process Tempo** dialog allows you to set a range to a specific length or to adjust its end time by automatic adjustment of the tempo track.




- To open the **Process Tempo** dialog, activate **Activate Tempo Track**, select **Project > Tempo Track** to open the **Tempo Track Editor**, and click **Open Process Tempo Dialog**.

The following options are available:

- 1 Range Start Time in PPQ**
Shows the start time of the locator range in bars and beats.
- 2 Range End Time in PPQ**
Shows the end time of the locator range in bars and beats.
- 3 Range Length in Selected Time Format**
Shows the length of the locator range in bars and beats.
- 4 Range End Time in Selected Time Format**
Shows the end time of the locator range in the selected time format.
- 5 Range Start Time in Selected Time Format**
Shows the start time of the locator range in the selected time format.
- 6 Time Display Format**
Allows you to select the time format that is displayed in the value fields of the new range.
- 7 New Range Start Time in Selected Time Format**
Shows the start time of the new range in the selected time format.
- 8 New Range End Time in Selected Time Format**
Shows the end time of the new range in the selected time format.
- 9 New Range Length in Selected Time Format**
Shows the length of the new range in the selected time format.
- 10 Tempo Scaling**
Shows the scaling value.

Process Bars (Cubase Pro only)

The **Process Bars** dialog allows you to insert, delete, replace, or reinterpret the signature events for a specified bar range by automatic adjustment of the signature and tempo events.



- To open the **Process Bars** dialog, select **Project > Tempo Track** to open the **Tempo Track Editor**, and click **Open Process Bars Dialog**.

The following options are available:

1 Bar Range

Shows the specified bar range.

2 Start

Allows you to set a start position for the bar range.

3 Length

Allows you to set a length for the bar range.

4 Action

Allows you to select one of the following actions:

- **Insert Bars** inserts an empty **Bar Range** with the set time **Signature** at the **Start** position.
- **Delete Bars** deletes the set **Bar Range** at the **Start** position.
- **Reinterpret Bars** reinterprets the set **Bar Range** with the set time **Signature** at the **Start** position. However, the playback of the notes stays the same.
- **Replace Bars** replaces the set **Bar Range** at the **Start** position.

5 Signature

Allows you to specify the time signature that is used for the **Insert**, **Reinterpret**, and **Replace** actions.

6 Process

Applies the specified action.

Time Warp (Cubase Pro only)


The **Time Warp** tool allows you to adjust musical positions of events or parts to time positions.

- You can adjust positions in musical time-based material to positions in time.
- You can match material with a musical time base to material with a linear time base.


NOTE

The **Time Warp** tool can create tempo values up to 300 BPM.

If you activate **Time Warp** on the toolbar, the ruler shows tempo events as flags with tempo values.



If you click the **Time Warp** on the **Project** window toolbar and click again, a pop-up menu opens where you can select one of the following modes:



- **Warp Grid**
If you use the **Time Warp** tool in this mode, the absolute time positions for all tracks that are set to musical time base are kept.
- **Warp Grid (musical events follow)**
If you use the **Time Warp** tool in this mode, all tracks that are set to musical time base follow the changes.

When you click with the **Time Warp** tool, it snaps to the tempo grid in the window. If you want the **Time Warp** tool to snap to a marker or the start or end of an event instead, activate **Snap** and set the **Snap Type** to **Events**.

Adjusting Musical Positions to Time Positions

You can adjust musical positions to positions in time with the **Time Warp** tool.

PREREQUISITE

Tempo track mode is activated. **Snap** is activated and you have selected an appropriate **Snap Type**.

PROCEDURE

1. On the **Project** window toolbar, click **Time Warp**.
The ruler is automatically set to **Bars+Beats** format.
2. In the event display, locate the musical position that you want to adjust and drag the time position to match it.



This can be the event start, a certain hit within the event, etc.

3. Release the mouse button.

RESULT

The musical position is adjusted to the time position, and the tempo value of the last tempo event before the click position is changed. If later tempo events exist, a new tempo event is created at the click position.


RELATED LINKS

[Project Tempo Modes](#) on page 892

[Time Warp \(Cubase Pro only\)](#) on page 906

Set Definition From Tempo

The **Set Definition from Tempo** dialog allows you to set up freely recorded audio material to follow a specific tempo.



- To open the **Set Definition from Tempo** dialog for an audio recording, select **Audio > Advanced > Set Definition from Tempo**.

Save Definition in Project Only

Allows you to save the tempo information in the project file only.

Write Definition to Audio Files

Allows you to write the tempo information to the selected audio files. This is useful if you want to use them in other projects together with the tempo information.

Set all Tracks to Musical Time Base

Allows you to set all tracks to musical time base. If this is deactivated, only the tracks with the selected events are set to musical time base.

Adjusting the Audio Tempo to the Project Tempo

You can adjust the tempo of freely recorded audio material to the project tempo.

PROCEDURE

1. Select the audio events that you want to adjust to the project tempo.
2. Select **Audio > Advanced > Set Definition from Tempo**.
3. Optional: Adjust the settings.
4. Click **OK**.

RESULT

The tempo information is copied to the audio and the tracks are set to musical time base. This is achieved by applying warping to the events. **Musical Mode** is activated for the audio events. The audio tracks now follow any tempo changes in the project.

Time Signature Events

You can set up one or more time signatures for a project.

You can set up the first time signature event of your project on the **Transport** panel. You can add further time signature events in the **Tempo Track Editor**.

Time signature events can have click patterns assigned. These allow you to create different grooves and feels for the metronome click. You can create a triplet click pattern for a 4/4 time signature, for example.

RELATED LINKS

[Toolbar](#) on page 40

[Transport](#) on page 49

[Signature Track](#) on page 143

[Adding Time Signature Events on the Signature Track](#) on page 909

[Setting Up a Click Pattern for a Time Signature Event](#) on page 909

Adding Time Signature Events in the Tempo Track Editor

PROCEDURE

1. Select **Project > Tempo Track** to open the **Tempo Track Editor**.
2. Select **Draw** on the toolbar, and in the ruler, click at the time position where you want to insert the time signature event.
3. Edit the numerator and the denominator to change the value of the time signature event.

NOTE

You can also select the time signature event and edit the time signature value on the info line.

RESULT

The time signature event is added at the specified time position. The timeline and the event displays for the **Project** window and the editors reflect the changes.

Adding Time Signature Events on the Signature Track

You can add multiple time signature events for a project. This is useful if you want to change the time signature at a specific bar, for example.

PROCEDURE

1. Select **Project > Add Track > Signature**.
 2. Select **Draw** on the **Project** window toolbar and on the signature track, click at the time position where you want to insert the time signature event.
 3. Edit the numerator and the denominator to change the value of the time signature event.
-

RESULT

The time signature event is added at the specified time position. The timeline and the event displays for the **Project** window and the editors reflect the changes.

RELATED LINKS

[Signature Track](#) on page 143

Setting Up a Click Pattern for a Time Signature Event

For each signature event in your project, you can set up a metronome click pattern.

PROCEDURE

1. Double-click the plus sign or the pattern to the right of the time signature value to open the **Click Pattern Editor**.
2. Do one of the following:
 - Open the **Pattern** pop-up menu and select one of the presets.
 - Use the **Clicks** setting to define the number of clicks that you want to hear, and click in the event display to set up a new click pattern.

3. When you are done, click outside the **Click Pattern Editor** to close it.
 4. Repeat this for each signature event for which you want to set up a click pattern.
-

RESULT

If you play back the project and activate the metronome click, the different project parts use the defined click patterns. The **Click Pattern Editor** in the **Transport** shows the pattern at the project cursor position.

RELATED LINKS

[Click Pattern Editor](#) on page 225


Project Browser (Cubase Pro only)

The **Project Browser** provides a list-based representation of the project. It allows you to view and edit all events on all tracks.

- To open the **Project Browser**, select **Project > Browser**.

NOTE

The **Project Browser** can be open while you are working in other windows. Any changes in the **Project** window or an editor are immediately reflected in the **Project Browser** and vice versa.



- 1 Project Structure**
Allows you to select specific track types for viewing and editing in the event display.
- 2 Toolbar**
Contains tools and settings for editing.
- 3 Info Line**
Shows information about the selected item.
- 4 Event Display**
Allows you to view and edit the selected item.

Toolbar

The toolbar contains tools and settings for editing in the **Project Browser**.




- 1 Open/Close All**
Opens/Closes all folders in the **Project Structure** list.
- 2 Time Format pop-up menu**
Allows you to change the time display format in the **Project Browser**.
- 3 Track/Part/Event type pop-up menu**
Shows what is added when you click **Add**.
- 4 Add button**
Adds the track, part, or event type that is shown in the pop-up menu to the left.
- 5 Filter pop-up menu**
Allows you to filter the event display by event type.
- 6 Sync Selection**
Links the selection in the **Project Browser** to the selection in the **Project** window. This allows you to locate events in the two windows.

Project Structure

The **Project Structure** allows you to select specific track types for viewing and editing in the event display. Depending on what track type you select, different items can be available in the **Project Structure**.

Track Data



If you select **Track Data**, the **Project Structure** shows audio events and/or audio parts, which in turn can contain audio events, or MIDI parts, which in turn can contain MIDI events.

Track Data is available for audio and MIDI tracks.

Automation

Selecting **Automation** in the **Project Structure** shows the automation events of the track, if available.

Each **Automation** item in the **Project Structure** has subentries for each automated parameter.

Event Display

The **Project Browser** event display allows you to view and edit the selected item.

Name	File	Start	End	Snap	Length	Offset	Volume	Fade In	Fade Out	Mute	Image
01 - Flying Home	01 - Flying Home	1. 1. 1. 0	97. 2. 3. 56	1. 1. 1.	0. 6. 1. 2. 56	0. 0. 0. 0	0. 0. 0. 0	0. 0. 0. 0	0. 0. 0. 0	0	-

NOTE

Not all columns are available for all events. You can rearrange the order of the columns by clicking a header and dragging left or right.

Name

Double-click the name to change it. You cannot change the name for the left and right locator.

Audio events: Double-click the waveform image to open the event in the **Sample Editor**.

Audio parts: Double-click the waveform image to open the event in the **Audio Editor**.

MIDI parts: Double-click the part image to open the event in the **Key Editor**.

File

Audio events: The name of the audio file referenced by the audio clip of the event.

Type

MIDI events: The type of the MIDI event.

Tempo track: The type of the tempo curve.

Start

The start position of the event.

End

The end position of the event.

Position

The position of an event.

Tempo

The tempo value of a tempo event.

Signature

The time signature value of a signature event.

Snap

Audio events: The position of the event snap point. Adjust this value to move the audio event.

Length

The length of the event.

Offset

The event start position in the clip.

NOTE

If the event already plays the whole clip, this value cannot be adjusted.

Volume

The volume of the event.

Fade In/Fade Out

The length of the fade-in and fade-out areas respectively.

NOTE

If you add a fade, a linear fade is created. If you adjust the length of an existing fade, the previous fade shape is maintained.

Mute

Mutes or unmutes the event.

Image

Audio events: Displays a waveform image of the event.

Editing Note Expression Data

In the **Project Browser**, you can view and edit the MIDI controller events or VST 3 events of a MIDI note with note expression data.

PROCEDURE

1. In the **Project Structure**, select the **Note Expression** subitem of the MIDI note that you want to view or edit.
In the event display, all MIDI controllers or VST 3 events within the note expression data are listed.
2. In the event display, edit the parameter values.

RESULT

The event changes accordingly.

EXAMPLE

If you entered a different **Start** value, the event is moved.

RELATED LINKS

[Note Expression](#) on page 800

Deleting events

PROCEDURE

1. Select an event or a part in the event display.
2. Do one of the following:
 - Select **Edit > Delete**.
 - Press **Delete** or **Backspace**.

RESULT

The selected event is deleted.

IMPORTANT

You cannot delete the first tempo event or the first time signature event of the project.

Rendering Audio and MIDI

You can render existing material to new audio material.

You can render the following:

- Audio tracks
- Instrument tracks
- Audio events or parts on audio tracks
- MIDI parts on instrument tracks
- Range selections on audio or instrument tracks
- Range selections on multiple audio or instrument tracks


IMPORTANT

The rendering function does not support side-chain routing.

Render Tracks

The **Render Tracks** dialog allows you to customize the track render settings.

To open the **Render Tracks** dialog, select one or more audio tracks, instrument tracks, or MIDI tracks, and select **Edit > Render in Place > Render Settings**.



The following settings are available:

As Separate Events

One or more tracks are created. These contain separate events or parts that are saved as separate audio files.

As Block Events

One or more tracks are created. These contain adjacent events/parts that are combined to blocks. Every block is saved as a separate audio file.

As One Event

One or more tracks are created. These contain the events/parts that are combined to one event/part. Every combination is saved as a separate audio file.

Dry

If this option is activated, all effects and panner settings are copied to new audio tracks. The resulting audio tracks keep the formats of their source tracks. A mono track results in a mono track, for example.

Channel Settings

If this option is activated, all effects are rendered into the resulting audio files. This includes insert effects, channel strip settings, group channel settings, and FX send channel settings. Panner settings are transferred to the new audio tracks. The resulting audio tracks keep the formats of their source tracks. A mono track results in a mono track, for example.

Complete Signal Path

If this option is activated, the complete signal path is rendered into the new audio files, including all channel settings, group channel settings, FX send channel settings, and panner settings. The new audio track is created without effects. Stereo balance panner settings are activated. The resulting audio file format is determined by the output channel of the source track. A mono track that is routed to a stereo bus results in a stereo audio file.

Complete Signal Path + Master FX

If this option is activated, the complete signal path and the master bus settings are rendered into the resulting audio files. This includes all channel settings, group channel settings, FX send channel settings, and panner settings. The resulting audio file format is determined by the output channel of the source track. A mono track that is routed to a stereo bus results in a stereo audio file.

Mix Down to One Track

By default, rendering multiple tracks or selections from multiple tracks at once results in multiple new audio tracks. To create one resulting audio track from all your source material, activate **Mix Down to One Track**.

Mix Down to One Track is only available if several tracks are selected and **Dry (Transfer Channel Settings)** is deactivated.

Tail Size

Allows you to set a tail size in seconds or bars and beats for the rendered files. This adds time at the end of the rendered file to allow reverb and delay tails to fully fade out.

Bit Depth

Allows you to set the bit depth for the resulting material to 16 bit, 24 bit, 32 bit, 32 bit float, or 64 bit float.

Name

Allows you to enter a custom name for the rendered files. To do this, unlock this option by clicking the lock icon.

Path

Allows you to select a custom folder to which the resulting .wav files are rendered.

Keep Source Tracks Unchanged

If this option is selected, the source tracks remain unchanged.

Mute Source Tracks

If this option is selected, the source tracks are automatically muted.

Disable Source Tracks

If this option is selected, the source tracks are disabled and are therefore no longer processed. This option releases CPU and RAM resources and is therefore similar to the **Freeze** function. To reenables the tracks, right-click the disabled track to open the context menu and select **Enable Track**.

Remove Source Tracks

If this option is selected, the source tracks are removed from the track list.

Hide Source Tracks

If this option is activated, the source tracks are hidden after rendering. To show the source tracks again, select the **Visibility** tab in the **Project** window and select the track that you want to show.

RELATED LINKS

[Setting Pan](#) on page 337

Rendering Tracks

You can render selected tracks either via the **Render Tracks** dialog or by directly using the **Render (with Current Settings)** command.

PROCEDURE

1. Select one or more audio, MIDI, or instrument tracks.
2. Select **Edit > Render in Place > Render Settings**.
3. Specify the render options.
4. Click **Render**.

RESULT


All selected source material is processed according to your render settings. Your render options are saved and used for all further render operations.

NOTE

You can also start the rendering operation directly by selecting **Edit > Render in Place > Render (with Current Settings)**.

Render Selection

You can render selections of audio events and/or MIDI parts with default settings or with customized settings. The **Render Selection** dialog allows you to customize the selection render settings.



The following settings are available:

As Separate Events

One or more tracks are created. These contain separate events or parts that are saved as separate audio files.

As Block Events

One or more tracks are created. These contain adjacent events/parts that are combined to blocks. Every block is saved as a separate audio file.

As One Event

One or more tracks are created. These contain the events/parts that are combined to one event/part. Every combination is saved as a separate audio file.

Dry

If this option is activated, all effects and panner settings are copied to new audio tracks. The resulting audio tracks keep the formats of their source tracks. A mono track results in a mono track, for example.

Channel Settings

If this option is activated, all effects are rendered into the resulting audio files. This includes insert effects, channel strip settings, group channel settings, and FX send channel settings. Panner settings are transferred to the new audio tracks. The resulting audio tracks keep the formats of their source tracks. A mono track results in a mono track, for example.

Complete Signal Path

If this option is activated, the complete signal path is rendered into the new audio files, including all channel settings, group channel settings, FX send channel settings, and panner settings. The new audio track is created without effects. Stereo balance panner settings are activated. The resulting audio file format is determined by the output channel of the source track. A mono track that is routed to a stereo bus results in a stereo audio file.

Complete Signal Path + Master FX

If this option is activated, the complete signal path and the master bus settings are rendered into the resulting audio files. This includes all channel settings, group channel settings, FX send channel settings, and panner settings. The resulting audio

file format is determined by the output channel of the source track. A mono track that is routed to a stereo bus results in a stereo audio file.

Mix Down to One Track

By default, rendering multiple tracks or selections from multiple tracks at once results in multiple new audio tracks. To create one resulting audio track from all your source material, activate **Mix Down to One Track**.

Mix Down to One Track is only available if several tracks are selected and **Dry (Transfer Channel Settings)** is deactivated.

Tail Size

Allows you to set a tail size in seconds or bars and beats for the rendered files. This adds time at the end of the rendered file to allow reverb and delay tails to fully fade out.

Bit Depth

Allows you to set the bit depth for the resulting material to 16 bit, 24 bit, 32 bit, 32 bit float, or 64 bit float.

Name

Allows you to enter a custom name for the rendered files. To do this, unlock this option by clicking the lock icon.

Path

Allows you to select a custom folder to which the resulting .wav files are rendered.

Keep Source Events Unchanged

If this option is selected, the source tracks remain unchanged.

Mute Source Events

If this option is selected, the source tracks are automatically muted.

Rendering Selections

You can render selections or range selections of audio events and/or MIDI parts via the **Render Selection** dialog.

PROCEDURE

1. Select one or more audio events and/or MIDI parts or make a range selection.
2. Select **Edit > Render in Place > Render Settings**.
3. In the **Render Selection** dialog, specify the render options.
4. Click **Render**.

RESULT

All selected source material is processed according to your render settings. Your render options are saved and used for all further render operations.


NOTE

You can also start the rendering operation directly by selecting **Edit > Render in Place > Render (with Current Settings)**.

Export Audio Mixdown

The **Export Audio Mixdown** function allows you to mix down and export all audio that is contained between the left and right locators of a project. Cubase Pro only: You can also export audio that is contained in different ranges defined by cycle markers.

To open the **Export Audio Mixdown** dialog, select **File > Export > Audio Mixdown**.



The **Export Audio Mixdown** dialog is divided into several sections:

1 Channel Selection

Allows you to select the channels that are mixed down from a list of all output and audio-related channels that are available in the project.

2 Cycle Marker Selection

Cubase Pro only: Allows you to export sections of your project that are defined by cycle marker ranges of the active marker track.

3 File Location

Allows you to set up the naming scheme and to select a path for the exported file.

4 File Format

Allows you to select a file format and make additional settings for the file to be created. This includes codec settings, metadata, sample rate, bit depth, etc. The available options depend on the selected file format.

5 Audio Engine Output

Allows you to specify a sample rate, a bit depth, and the number of audio channels for the audio output.

6 Import Into Project

Allows you to automatically import the resulting audio file back into your project.

7 Post Process

Allows you to specify what happens after the export process.

RELATED LINKS

[Channel Selection](#) on page 922

[Cycle Marker Selection \(Cubase Pro only\)](#) on page 923

[File Location](#) on page 923

[File Format](#) on page 926

[Audio Engine Output](#) on page 932

[Import Into Project](#) on page 933

[Post Process](#) on page 934

Mixing Down to Audio Files

PROCEDURE

1. Set up the left and right locators to encompass the section that you want to mix down.
2. Set up your tracks so that they play back the way you want.
This includes muting unwanted tracks or parts, making manual **MixConsole** settings, and/or activating the **R** (Read) automation buttons for **MixConsole** channels.

IMPORTANT

The setting of the **Output Routing** in the corresponding track **Inspector** determines the channel width of the **Export Audio Mixdown** export. This means, if no main output bus is selected, the exported audio file only contains silence.

3. Select **File > Export > Audio Mixdown**.
4. In the **Export Audio Mixdown** dialog, make your settings.
5. Click **Export**.

RESULT

The audio file is exported.

IMPORTANT

- If you set the export range in such a way that the effects that are applied to a preceding event, for example reverb, reach into the next, these will be heard in the mixdown even though the event itself is not included. To avoid this, mute the first event.

Available Channels for Export

The **Channel Selection** section of the **Export Audio Mixdown** dialog contains a list of channels that you can export as an audio mixdown.

The channels are organized in a hierarchical structure. Channels of the same type are grouped. This allows you to easily identify and select the channels for export.

NOTE

MIDI tracks are not available for export. To include MIDI in a mixdown, you must record MIDI to audio tracks.

You can mix down the following channel types:


- **Output channels**
All output channels that you configured in the **Audio Connections** dialog are listed in the **Channel Selection** section. By activating an output channel in the list, you instruct Cubase to mix down all tracks that are routed to this output channel.
- **Audio channels**
All audio channels that are available in your project are listed in the **Channel Selection** section. By activating an audio channel in the list, you instruct Cubase to mix it down to a file, including insert effects, EQ, etc.
- **Any audio-related MixConsole channels**
All VST instrument channels, instrument tracks, effect return channels (FX channel tracks), group channels, and ReWire channels of your project are listed in the **Channel Selection** section. By activating an audio-related channel in the list, you instruct Cubase to mix it down, including insert effects, EQ, etc.

RELATED LINKS

[Audio Connections](#) on page 21

Channel Selection

The **Channel Selection** section allows you to select the channels that are mixed down.



- 1 **Channel Batch Export** (Cubase Pro only)

Activate this option if you want to mix down several channels simultaneously. An individual file is created for each channel. If you activate a channel type in the list, all channels of this type are selected.

2 Channels available for export


In the list, activate the channels that you want to include in the mixdown. Only the sound of the activated channels is included in the mixdown. **MixConsole** settings, record enable, and insert effects are taken into account.

3 Filter

Allows you to enter the channel name to filter the channels. This is useful if your project contains a large number of channels.

Cycle Marker Selection (Cubase Pro only)

You can export different sections of a project at the same time.



To enable this, you must define several cycle marker ranges. In the **Cycle Marker Selection** section of the **Export Audio Mixdown** dialog, you can activate the cycle markers to include their ranges in the mixdown.

1 Export Cycle Marker(s)

Activate this option to select the available cycle markers in the list. This option is only available if you set up at least 1 cycle marker.

2 Cycle markers available for export

Activate the cycle markers that define the ranges that you want to include in your mixdown. On export, one audio file is created for each range.

NOTE


Only the cycle markers of the active marker track can be selected.

RELATED LINKS

[Markers](#) on page 307

File Location

The **File Location** section allows you to specify a name and path for the mixdown file.



1 Name

Specifies the name of the mixdown file.

2 Naming Options

Opens a pop-up menu with naming options:

- **Set to Project Name** inserts the project name into the **Name** field.
- **Auto Update Name** adds a number to the file name and increments the number every time you export a file.

3 Path

Opens a dialog that allows you to browse for a file location.

4 Path Options

Opens a pop-up menu with the following options:

- **Choose** opens a dialog that allows you to browse for a file location.
- **Use Project Audio Folder** sets the path to the **Audio** folder of your project.
- **Recent Paths** allows you to select recently selected file locations.
- **Clear Recent Paths** allows you to delete all recently selected file locations.

5 Naming Scheme

Opens a dialog where you can specify a naming scheme for the mixdown file name.

6 Resolve File Name Conflicts

Specifies how file name conflicts with existing files are resolved.

RELATED LINKS

[Naming Scheme Dialog](#) on page 924


[Resolve File Name Conflicts](#) on page 925

Naming Scheme Dialog

The **Naming Scheme** dialog allows you to define naming schemes for the audio material that you want to export.

The naming attributes that are available in this dialog depend on the channel that you selected for export.

- To open the **Naming Scheme** dialog, click **Naming Scheme** in the **Export Audio Mixdown** dialog.



1 Scheme

Allows you to select, create, save, and delete naming schemes.

2 Attributes

Shows the available naming scheme attributes.

- 3 Result**
Allows you to drag and drop attributes to this field and rearrange them by dragging.
- 4 Settings**
Allows you to make separator and counter settings.
- 5 Preview**
Displays a preview of your current naming scheme.

RELATED LINKS

[Channel Selection](#) on page 922

Defining Naming Schemes

You can define a naming scheme by combining attributes that determine the structure of the file names for the exported audio files.

Depending on the settings in the **Channel Selection** section and the **Cycle Marker Selection** section (Cubase Pro only), different naming attributes are available.

PROCEDURE

1. Drag and drop up to 5 attributes into the **Result** section.
You can also double-click an attribute to add it to the **Result** section.
2. In the **Settings** section, double-click the **Separator** text field and type in a separator.
The **Preview** section displays the file name scheme according to your settings.
3. Click the up or down arrows to set the **Counter**.
The counter will start counting from this value. You can also double-click the **Counter** text field and enter a value.
4. Click the **Digits** field and select the number of digits from the pop-up menu.
The **Digits** setting determines how many digits the counters will contain.
5. Optional: Double-click the text field in the **Scheme** section and enter a preset name. Press enter to save your settings as a preset.

NOTE

The preset is only available for the channels that are selected in the **Channel Selection** section of the **Export Audio Mixdown** dialog.

Resolve File Name Conflicts

Exporting audio can cause name conflicts with existing files that have the same name. You can define how file name conflicts are resolved.

In the **Export Audio Mixdown** dialog, select one of the following options from the **Resolve File Name Conflicts** pop-up menu:

Always Ask

Always asks if an existing file should be overwritten or if a new unique file name should be created by adding an incremental number.

Create Unique File Name

Creates a unique file name by adding an incremental number.

Always Overwrite

Always overwrites the existing file.

File Format


The **File Format** section allows you to select a format and make additional settings for the mixdown file.

The following file formats are available:

- **Wave File**
This is the most common file format on the PC platform. Wave files have the extension **.wav**.
- **AIFC File**
This is an audio file format standard defined by Apple Inc. AIFC files are used on most computer platforms. They support compression ratios as high as 6:1 and contain tags in the header. AIFC files have the extension **.aifc**.
- **AIFF Files**
This is an audio file format standard defined by Apple Inc. AIFF files are used on most computer platforms. The files can contain embedded text strings. AIFF files have the extension **.aif**.
- **MPEG**
This is a family of standards used for encoding audio-visual information such as movies, video, and music in a digital compressed format. Cubase can read MPEG Layer 2 and MPEG Layer 3. MP3 files are highly compressed files that still provide good audio quality. The files have the extension **.mp3**.
- **Windows Media Audio File** (Windows only)
This is an audio file format defined by Microsoft Inc. WMA files can be decreased in size with no loss of audio quality. WMA Pro features the possibility of mixing down to 5.1 surround sound. The files have the extension **.wma**.
- **FLAC File**
This is an open source format that reduces the size of audio files by 50 to 60 % compared to regular Wave files. The files have the extension **.flac**.
- **Ogg Vorbis File**
This is an open source, patent-free audio encoding and streaming technology. The Ogg Vorbis encoder uses variable bit rate encoding. It offers compressed audio files of small size, but with comparatively high audio quality. The files have the extension **.ogg**.
- **Wave 64 File**
This is a proprietary format developed by Sonic Foundry Inc. Wave 64 files offer the same quality as Wave files, but they can be considerably larger than standard Wave files. They are especially suited for long recordings with file sizes over 2 GB. The files have the extension **.w64**.

Wave Files

Wave files have the extension **.wav** and are the most common file format on the PC platform.



If you select the **Wave File** format for the exported file, you can make the following settings:

1 Insert Broadcast Wave Chunk

Activates the embedding of additional file information in Broadcast Wave format.

NOTE

By activating this option, you create a Broadcast Wave file. Some applications may not be able to handle these files. If you get problems using the file in another application, deactivate **Insert Broadcast Wave Chunk** and export the file again.

2 Edit

Opens the **Broadcast Wave Chunk** dialog where you can enter information.

3 Don't Use Wave Extensible Format

Deactivates the Wave Extensible format that contains additional metadata, such as the speaker configuration.

4 Don't Use RF64-compliant File Format

Deactivates the RF64-compliant format that allows file sizes to exceed 4 GB.

5 Insert iXML Chunk

Includes additional project-related metadata, such as project name, author, and project frame rate.

6 Insert Tempo Definition


This option is only available if **Insert iXML Chunk** is activated. It allows you to include tempo information from the tempo track or from the **Definition** section of the **Sample Editor** in the iXML chunk of the exported files.

RELATED LINKS

[Attribute Inspector](#) on page 570

AIFC Files

AIFC files support compression ratios as high as 6:1 and contain tags in the header. AIFC files have the extension .aifc and are used on most computer platforms.



1 Insert Broadcast Wave Chunk

Activates the embedding of additional file information in Broadcast Wave format.

NOTE

By activating this option, you create a Broadcast Wave file. Some applications may not be able to handle these files. If you get problems using the file in another application, deactivate **Insert Broadcast Wave Chunk** and export the file again.

2 Edit

Opens the **Broadcast Wave Chunk** dialog where you can enter embedded information.

3 Insert iXML Chunk


Includes additional project-related metadata, such as project name, author, and project frame rate.

4 Insert Tempo Definition

This option is only available if **Insert iXML Chunk** is activated. It allows you to include tempo information from the tempo track or from the **Definition** section of the **Sample Editor** in the iXML chunk of the exported files.

AIFF Files

AIFF stands for Audio Interchange File Format, a standard defined by Apple Inc. AIFF files have the extension `.aif` and are used on most computer platforms.



1 Insert Broadcast Wave Chunk

Activates the embedding of additional file information.

NOTE

By activating this option, you create a Broadcast Wave file. Some applications may not be able to handle these files. If you get problems using the file in another application, deactivate **Insert Broadcast Wave Chunk** and export the file again.

2 Edit

Opens the **Broadcast Wave Chunk** dialog where you can enter embedded information.

3 Insert iXML Chunk


Includes additional project-related metadata, such as project name, author, and project frame rate.

4 Insert Tempo Definition

This option is only available if **Insert iXML Chunk** is activated. It allows you to include tempo information from the tempo track or from the **Definition** section of the **Sample Editor** in the iXML chunk of the exported files.

MP3 (MPEG-1 Layer 3) files

MP3 files are highly compressed files that still provide good audio quality. They have the extension `.mp3`.



1 Bit Rate

Sets the bit rate for the MP3 file. The higher the bit rate, the better the audio quality and the larger the file. For stereo audio, 128 kBit/s is considered to be providing good audio quality results.

2 Sample Rate

Sets the Sample Rate for the MP3 file.

3 High Quality Mode

Sets the encoder to a different resampling mode. This may give better results depending on your settings. However, it does not allow you to select the **Sample Rate**.

4 Insert ID3 Tag


Includes ID3 Tag information in the exported file.

5 Edit ID3 Tag

Opens the **ID3 Tag** dialog that allows you to enter information about the file. This information is embedded in the file and can be displayed by most MP3 playback applications.

Windows Media Audio Files (Windows only)

The Windows Media Audio format by Microsoft Inc. uses advanced audio codecs and lossless compression. WMA files can be decreased in size with no loss of audio quality. Furthermore, WMA features the possibility of mixing down to 5.1 surround sound. The files have the extension `.wma`.




- **Codec Settings**

Opens the **Windows Media Audio File Settings** dialog.

Windows Media Audio File Settings - General

The **General** tab in the **Windows Media Audio File Settings** dialog allows you to specify sample rate, bit rate, and channels for the encoded file.



1 Sample Rate

Allows you to set the sample rate to 44.100, 48.000, or 96.000 kHz. Set this to match the sample rate of the source material or use the closest available value that is higher than the actual value.

2 Bit Depth

Allows you to set the bit depth to 16 bit or 24 bit. Set this parameter to match the bit depth of the source material or use the closest available value that is higher than the actual value.

NOTE

Always keep in mind the intended use of the file. For publication on the Internet, you might not want too high bit rates, for example.

3 Channels

This setting depends on the chosen output. You cannot change it manually.

4 Mode


- Select **Constant Bit Rate** if you want to limit the file size. To calculate the size of a file that is encoded with a constant bit rate, multiply the bit rate by the duration of the file.
- Select **Variable Bit Rate** if you want the bit rate to fluctuate depending on the character and intricacy of the material being encoded. The more complex passages in the source material, the higher the bit rate – and the larger the final file.
- Select **Lossless** to encode the file with lossless compression.

5 Bit Rate/Quality

- Allows you to set the bit rate settings depending on the selected mode and/or output channels. The higher the bit rate or quality you select, the larger the final file.

Windows Media Audio File Settings - Advanced

The **Advanced** tab in the **Windows Media Audio File Settings** dialog allows you to specify the dynamic range control, that is, the difference in dB between the average loudness and the peak audio level (the loudest sounds) of the audio for the encoded file.



1 Dynamic Range Control

The dynamic range is automatically calculated during the encoding process. If you activate this option, you can specify the dynamic range manually.

If **Dynamic Range Control** is activated and the Quiet Mode of the Windows Media Player is set to Medium Difference, the peak level is limited to the peak value that you specified. If **Dynamic Range Control** is deactivated, the peak level is limited to 12 dB above the average level during playback.

If **Dynamic Range Control** is activated and the Quiet Mode of the Windows Media Player is set to Little Difference, the peak level is limited to the average value between the peak and average values that you specified. If **Dynamic Range Control** is deactivated, the peak level is limited to 6 dB above the average level during playback.

2 Peak


Allows you to set a peak value between 0 and -90 dB.

3 Average

Allows you to set a peak value between 0 and -90 dB. However, this affects the overall volume level and can have a negative effect on the audio quality.

Windows Media Audio File Settings - Media


The **Media** tab in the **Windows Media Audio File Settings** dialog allows you to enter information about the file.



Use the **Title**, **Author**, **Copyright**, and **Description** fields to enter a file description of its content that is embedded in the file header. This can be displayed by some Windows Media Audio playback applications.

FLAC Files

Free Lossless Audio Codec files are audio files that are typically 50 to 60 % smaller than regular Wave files.




1 Compression Level

Sets the compression level for the FLAC file. Since FLAC is a lossless format, the level has more influence on the encoding speed than on the file size.

Ogg Vorbis Files

Ogg Vorbis is an open source, patent-free audio encoding and streaming technology, offering compressed audio files of small size, but with comparatively high audio quality. Ogg Vorbis files have the extension `.ogg`.




1 Quality

Sets the quality for the variable bit rate encoding. This setting determines between which limits the bit rate will vary. The higher the value, the higher the sound quality but also the larger the files.

Wave 64 Files

Wave 64 is a proprietary format developed by Sonic Foundry Inc. Wave 64 files have the extension `.w64`.



NOTE

In terms of audio quality, Wave 64 files are identical to standard Wave files, but in the file headers, Wave 64 files use 64-bit values for addressing where Wave files use 32-bit values. The consequence of this is that Wave 64 files can be considerably larger than standard Wave files. Wave 64 is therefore a good file format choice for long recordings, for example, if the file sizes exceed 2 GB.

1 Insert Broadcast Wave Chunk

Embeds additional file information in Broadcast Wave Format.

NOTE

Activating this option creates a Broadcast Wave file. Some applications may not be able to handle Broadcast Wave files. If you get problems using the file in another application, deactivate **Insert Broadcast Wave Chunk** and export the file again.

2 **Edit**

Opens the **Broadcast Wave Chunk** dialog where you can enter embedded information.

3 **Insert iXML Chunk**


Includes additional project-related metadata, such as project name, author, and project frame rate.

4 **Insert Tempo Definition**

This option is only available if **Insert iXML Chunk** is activated. It allows you to include tempo information from the tempo track or from the **Definition** section of the **Sample Editor** in the iXML chunk of the exported files.

Audio Engine Output

The **Audio Engine Output** section contains all the settings related to the output of the Cubase audio engine.



1 **Sample Rate**

NOTE

This parameter is only available for uncompressed audio file formats and FLAC files.

Allows you to select the frequency range of the exported audio. If you set the value lower than the project sample rate, the audio quality degrades and the high-frequency content is reduced. If you set the value higher than the project sample rate, the file size increases without increasing the audio quality. For CD burning select 44.100 kHz, because this is the sample rate used on audio CDs.

2 **Bit Depth**

NOTE

This parameter is only available for uncompressed audio file formats and FLAC files.

Allows you to select 8 bit, 16 bit, 24 bit, 32 bit, 32 bit float, and 64 bit float. If you plan to re-import the mixdown file into Cubase, select **32 bit float** or **64 bit float**, depending on the **Processing Precision** setting in the **Studio Setup** dialog. 32-bit float files are twice the size of 16-bit files. For CD burning, use the 16-bit option, as CD audio is always 16 bit. In this case, we recommend dithering. Activating the **UV22HR** dithering plug-in reduces the effects of quantization noise and artifacts when converting the audio to 16 bit. 8-bit format results in limited audio quality and should only be used if required.

3 **Real-Time Export**

Allows you to export the mixdown file in real time. This takes at least the same time as regular playback. Some VST plug-ins, external instruments, and effects require real-time

export in order to have enough time to update correctly during the mixdown. Consult the plug-in manufacturers for further information.

Cubase Pro only: During the real-time export of a single channel, the **Audition Volume** fader is displayed in the progress dialog. It allows you to adjust the **Control Room** volume.

NOTE

If the CPU and disk speed of your computer do not allow to export all channels simultaneously in real time, the program stops the process, reduces the number of channels, and starts again. Afterwards, the next batch of files is exported. This is repeated as often as needed to export all selected channels.

4 Mono Downmix

In Cubase Artist, this option allows you to downmix the 2 channels of a stereo bus to a single mono file. In Cubase Pro, this option allows you to downmix all the subchannels of a stereo or surround channel or bus to a single mono file.

For stereo, the panning law as defined in the **Project Setup** dialog is applied to avoid clipping. For surround (Cubase Pro only), the channels are summed and divided through the number of channels used (in case of a 5.1. channel = $(L+R+C+LFE+Ls+Rs)/6$).

5 Split Channels

Allows you to export the 2 channels of a stereo bus or all subchannels of a multi channel bus (Cubase Pro only) as separate mono files.

6 L/R Channels

Allows you to export only the left and right subchannels of a multi channel bus into a stereo file (Cubase Pro only).

RELATED LINKS


[VST Audio System](#) on page 13

[Dither Effects](#) on page 407

[Control Room \(Cubase Pro only\)](#) on page 372

Import Into Project

This section offers several options for importing the resulting mixdown files back into the existing or into a new project.



NOTE

When you play back the reimported file in the same project, mute the original tracks so that you only hear the mixdown.

1 Pool

Imports the resulting audio file automatically back into the **Pool** as a clip. Deactivating this option also deactivates the **Audio Track** option.

2 Audio Track

Creates an audio event that plays the clip on a new audio track, starting at the left locator. Activating this option also activates the **Pool** option.

3 Pool Folder

Allows you to specify a **Pool** folder for the clip.

4 **Create New Project**

NOTE

This option is only available for uncompressed file formats for which the **Use Project Audio Folder** option in the **File Location** section is deactivated.

Activate this option to create a new project that contains an audio track for each of the exported channels, as well as the signature and tempo track of the original project.

The tracks will have the corresponding mixdown file as audio event. The track names will be identical with the export channel names. Note that the new project will be the active project.

Activating this option disables the **Pool** and **Audio Track** options.

NOTE

If you activate any of the options in this section, the **Import Options** dialog opens for each exported channel when the export is complete.


RELATED LINKS

[Importing Media](#) on page 539

[File Location](#) on page 923

Post Process

In this section, you can select a process that you want to run after mixing down your audio file.



1 **Deactivate External MIDI Inputs**

Activate this option if MIDI inputs that are performed on external devices should be ignored during the export process.

2 **Close Window after Export**

Closes the dialog automatically after export.

3 **Update Display**

Activate this option if you want the meters to be updated during the export process. This allows you to check for clipping, for example.

4 **Post Process**

If WaveLab 7.0.1 or higher is installed on your computer, you can select **Open in WaveLab** to open your mixdown file in this application after export.

Select **Upload to SoundCloud** to launch SoundCloud, connect to your user account, and upload your mixdown.

Synchronization

Background

What is synchronization?

Synchronization is the process of getting 2 or more devices to play back together at the same speed and position. These devices can range from audio and video tape machines to digital audio workstations, MIDI sequencers, synchronization controllers, and digital video devices.

Synchronization basics

There are 3 basic components of audio/visual synchronization: position, speed, and phase. If these parameters are known for a particular device (the master), then a second device (the slave) can have its speed and position “resolved” to the first in order to have the 2 devices play in perfect sync with one another.

Position

The position of a device is represented by either samples (audio word clock), video frames (timecode), or musical bars and beats (MIDI clock).

Speed

The speed of a device is measured either by the frame rate of the timecode, the sample rate (audio word clock) or by the tempo of the MIDI clock (bars and beats).

Phase

Phase is the alignment of the position and speed components to each other. In other words, each pulse of the speed component should be aligned with each measurement of the position for the most accuracy. Each frame of timecode should be perfectly lined up with the correct sample of audio. Put simply, phase is the very precise position of a synchronized device relative to the master (sample accuracy).

Machine control

When 2 or more devices are synchronized, the question remains: how do we control the entire system? We need to be able to locate to any position, play, record, and even jog and scrub the entire system using one set of controls.

Machine control is an integral part of any synchronization setup. In many cases, the device simply called “the master” will control the whole system. However, the term “master” can also refer to the device that is generating the position and speed references. Care must be taken to differentiate between the 2.

Master and slave

Calling one device the “master” and another the “slave” can lead to a great deal of confusion. The timecode relationship and the machine control relationship must be differentiated in this regard.

In this document, the following terms are used:

- The “timecode master” is the device generating position information or timecode.
- The “timecode slave” is any device receiving the timecode and synchronizing or “locking” to it.
- The “machine control master” is the device that issues transport commands to the system.
- The “machine control slave” is the device receiving those commands and responding to them.

For example, Cubase could be the machine control master, sending transport commands to an external device which in turn sends timecode and audio clock information back to Cubase. In that case, Cubase would also be the timecode slave at the same time. So calling Cubase simply the master is misleading.

NOTE

In most scenarios, the machine control slave is also the timecode master. Once it receives a play command, that device starts generating timecode for all the timecode slaves to synchronize to.

Timecode (positional references)

The position of any device is most often described using timecode. Timecode represents time using hours, minutes, seconds, and frames to provide a location for each device. Each frame represents a visual film or video frame.

Timecode can be communicated in several ways:

- LTC (Longitudinal Timecode) is an analog signal that can be recorded on tape. It should be used for positional information primarily. It can also be used for speed and phase information as a last resort if no other clock source is available.
- VITC (Vertical Interval Timecode) is contained within a composite video signal. It is recorded onto video tape and is physically tied to each video frame.
- MTC (MIDI Timecode) is identical to LTC except that it is a digital signal transmitted via MIDI.

Timecode standards

Timecode has several standards. The subject of the various timecode formats can be very confusing due to the use and misuse of the shorthand names for specific timecode standards and frame rates. The timecode format can be divided into 2 variables: frame count and frame rate.

Frame count (frames per second)

The frame count of timecode defines the standard with which it is labeled. There are 4 timecode standards:

24 fps Film (F)

This frame count is the traditional count for film. It is also used for HD video formats and commonly referred to as 24 p. However, with HD video, the actual frame rate or speed of the video sync reference is slower, 23.976 frames per second, so timecode does not reflect the actual realtime on the clock for 24 p HD video.

25 fps PAL (P)

This is the broadcast video standard frame count for European (and other PAL countries) television broadcast.

30 fps non-drop SMPTE (N)

This is the frame count of NTSC broadcast video. However, the actual frame rate or speed of the video format runs at 29.97 fps. This timecode clock does not run in realtime. It is slightly slower by 0.1 %.

30 fps drop-frame SMPTE (D)

The 30 fps drop-frame count is an adaptation that allows a timecode display running at 29.97 fps to actually show the clock-on-the-wall-time of the timeline by dropping or skipping specific frame numbers in order to catch the clock up to realtime.

Confused? Just remember to keep the timecode standard (or frame count) and frame rate (or speed) separate.

Frame rate (speed)

Regardless of the frame counting system, the actual speed at which frames of video go by in real time is the true frame rate.

Cubase supports the following frame rates:

23.98 fps (Cubase Pro only)

This frame rate is used for film that is being transferred to NTSC video and must be slowed down for a 2-3 pull-down telecine transfer. It is also used for the type of HD video referred to as 24 p.

24 fps

This is the true speed of standard film cameras.

24.98 fps (Cubase Pro only)

This frame rate is commonly used to facilitate transfers between PAL and NTSC video and film sources. It is mostly used to compensate for some error.

25 fps

This is the frame rate of PAL video.

29.97 fps/29.97 dfps

This is the frame rate of NTSC video. The count can be either non-drop or drop-frame.

30 fps/30 dfps

This frame rate is not a video standard anymore but has been commonly used in music recording. Many years ago, it was the black and white NTSC broadcast standard. It is equal to NTSC video being pulled up to film speed after a 2-3 telecine transfer. The count can be either non-drop or drop-frame.

50 fps (Cubase Pro only)

This rate is also referred to as 50 p.

59.94 fps (Cubase Pro only)

This video frame rate is supported by high definition cameras and is compatible with NTSC.

60 fps (Cubase Pro only)

This video frame rate is supported by many high definition cameras. However, the NTSC compatible 59.94 fps frame rate is much more common.

IMPORTANT

Video formats with a variable frame rate (VFR) are not supported.

Frame count vs. frame rate

Part of the confusion in timecode stems from the use of frames per second in both the timecode standard and the actual frame rate. When used to describe a timecode standard, frames per second defines how many frames of timecode are counted before one second on the counter increments. When describing frame rates, frames per second define how many frames are played back during the span of one second of realtime. In other words: Regardless of how many frames of video there are per second of timecode (frame count), those frames can be moving at different rates depending on the speed (frame rate) of the video format. For example, NTSC timecode (SMPTE) has a frame count of 30 fps. However, NTSC video runs at a rate of 29.97 fps. So the NTSC timecode standard known as SMPTE is a 30 fps standard that runs at 29.97 fps realtime.

Clock sources (speed references)

Once the position is established, the next essential factor for synchronization is the playback speed. Once 2 devices start playing from the same position, they must run at exactly the same speed in order to remain in sync. Therefore, a single speed reference must be used and all devices in the system must follow that reference. With digital audio, the speed is determined by the audio clock rate. With video, the speed is determined by the video sync signal.

Audio clock

Audio clock signals run at the speed of the sample rate used by a digital audio device and are transmitted in several ways:

Word clock

Word clock is a dedicated signal running at the current sample rate that is fed over BNC coaxial cables between devices. It is the most reliable form of audio clock and is relatively easy to connect and use.

AES/SPDIF Digital Audio

An audio clock source is embedded within AES and SPDIF digital audio signals. This clock source can be used as a speed reference. Preferably, the signal itself does not contain any actual audio (digital black), but any digital audio source can be used if necessary.

ADAT Lightpipe

ADAT Lightpipe, the 8-channel digital audio protocol developed by Alesis, also contains audio clock and can be used as a speed reference. It is transmitted via optical cables between devices.

NOTE

Do not confuse the audio clock embedded in the Lightpipe protocol with ADAT Sync, which has timecode and machine control running over a proprietary DIN plug connection.

MIDI clock

MIDI clock is a signal that uses position and timing data based on musical bars and beats to determine location and speed (tempo). It can perform the same function as a positional reference and a speed reference for other MIDI devices. Cubase supports sending MIDI clock to external devices but cannot slave to incoming MIDI clock.

IMPORTANT

MIDI clock cannot be used to synchronize digital audio. It is only used for MIDI devices to play in musical sync with one another. Cubase does not support being a MIDI clock slave.

The Project Synchronization Setup dialog

Cubase's Project Synchronization Setup dialog provides a central place to configure a complex synchronized system. In addition to settings for timecode sources and machine control settings, project setup parameters are available along with basic transport controls for testing the system.

- To open the **Project Synchronization Setup** dialog, select **Transport > Project Synchronization Setup**.


The dialog is organized into sections separating related groups of settings. The arrows shown between the various sections of the dialog indicate how settings in one section influence settings in another section. In the following, the available sections are described in detail.

The Cubase Section

At the center of the Project Synchronization Setup dialog is the Cubase section. It is provided to help you visualize the role that Cubase takes in your setup. It shows which external signals enter or leave the application.

Timecode Source

The Timecode Source setting determines whether Cubase is acting as timecode master or slave.



When set to "Internal Timecode", Cubase is the timecode master, generating all position references for any other device in the system. The other options are for external timecode sources. Selecting any of these, makes Cubase a timecode slave if "Use External Synchronization" is activated on the Transport menu.

Internal Timecode

Cubase generates timecode based on the project timeline and project setup settings. The timecode will follow the format specified in the Project Setup section.

MIDI Timecode

Cubase acts as a timecode slave to any incoming MIDI timecode (MTC) on the ports selected in the MIDI Timecode section, to the right of the Timecode Source section.



Selecting "All MIDI Inputs" allows Cubase to sync to MTC from any MIDI connection. You can also select a single MIDI port for receiving MTC.

ASIO Audio Device

This option is only available with audio cards that support ASIO Positioning Protocol. These audio cards have an integrated LTC reader or ADAT sync port and can perform a phase alignment of timecode and audio clock.

VST System Link


VST System Link can provide all aspects of sample-accurate synchronization between other System Link workstations.

RELATED LINKS

[Working with VST System Link](#) on page 945

Timecode Preferences

When MIDI Timecode is selected, additional options become available in the Cubase section, providing several options for working with external timecode.



Lock Frames

This setting determines how many full frames of timecode it takes for Cubase to try and establish sync or “lock”. If you have an external tape transport with a very short start-up time, try lowering this number to make lock-up even faster. This option can only be set to multiples of 2.

Drop Out Frames

This setting determines the amount of missed timecode frames it takes for Cubase to stop. Using LTC recorded on an analog tape machine can result in some amount of drop outs. Increasing this number allows Cubase to “free-wheel” over missed frames without stopping. Lowering this number causes Cubase to stop sooner once the tape machine has stopped.

Inhibit Restart ms

Some synchronizers still transmit MTC for a short period after an external tape machine has been stopped. These extra frames of timecode sometimes cause Cubase to restart suddenly. The “Inhibit Restart ms” setting allows you to control the amount of time in milliseconds that Cubase will wait to restart (ignoring incoming MTC) once it has stopped.

Auto-Detect Frame-Rate Changes


Cubase can notify the user when the frame rate of timecode changes at any point. This is helpful in diagnosing problems with timecode and external devices. This notification will interrupt playback or recording. Deactivating this option will avoid any interruption in playback or recording.

IMPORTANT

If there is a discrepancy between the project frame rate in Cubase and incoming timecode, Cubase might still be able to lock to the incoming timecode. If the user is unaware of these differences, problems can arise later in postproduction.

Machine Control Output Destination

If **Use External Synchronization** in the **Transport** menu is activated, all transport commands (including movements of the cursor in the **Project** window) are translated into machine control commands and routed according to the settings that are made in the **Machine Control Output Destination** section.



MC Master Active

If this option is activated, transport commands are routed or sent to any device while sync is enabled. Additional routing options become available. Deactivating this option does not affect the operation of the individual MMC Device panels. They can still function regardless of the machine control destination.

MMC Input and Output

The MMC Input and MMC Output settings determine which MIDI port in your system will send and receive MMC commands. Set both the input and output to MIDI ports that are connected to the desired MIDI device.

MMC Device ID

The MMC device ID should be set to the same number as the receiving device. You can also set the device ID to "All" if more than one machine is receiving MMC commands or if the device ID is not known.

NOTE

Some devices can only listen to their specific IDs. Therefore, using the All option will not work with such devices.

Number of Audio Tracks (Cubase Pro only)

The number of audio tracks should be set to match the amount of available audio tracks in the destination device. This setting determines how many record-enable buttons are shown in the MMC Master panel.

MMC Master panel




The MMC Master panel can be opened from the Studio menu. In order to use the MMC Master panel, proceed as follows:

- In the **Preferences** dialog, select **MIDI > MIDI Filter**, and make sure SysEx is activated in the Thru section.
This is necessary since MMC uses 2-way communication (the tape recorder "replies" to the MMC messages it receives from Cubase). By filtering out SysEx Thru, you ensure that these MMC System Exclusive replies are not echoed back to the tape recorder.
- On the MMC Master panel, activate the Online button to use the transport buttons on the panel to control the transport of the device.
It is not necessary to have this activated in order to synchronize with the MMC device. It only affects operation of the MMC Master panel.
- You can use the buttons to the left on the MMC Master panel to arm tape tracks for recording.
- The "A1, A2, TC, VD" items refer to additional tracks usually found on video tape recorders.
Refer to the manual of your VTR device to see if these tracks are supported.

Machine Control Input (Cubase Pro only)

Cubase can respond to machine control commands from external MIDI devices.

Cubase can follow incoming transport commands (locate, play, record) and respond to record-enabling commands for audio tracks. This allows Cubase to easily integrate into larger studio systems with centralized machine control and synchronization such as theatrical mixing stages.



MMC Slave Active

If this option is activated, several settings become available in the Machine Control Input section:

Option	Description
MMC Input	Set this to the MIDI input that is connected to the master machine control device.
MMC Output	Set this to the MIDI output that is connected to the master machine control device.
MMC Device ID	This determines the MIDI ID number that is used to identify the machine in Cubase.

IMPORTANT


The MMC protocol involves polling devices (requesting information) for their status which requires 2-way communication. While some functions may work with only one way communication, it is best to connect both MIDI ports (input and output) of MMC devices.

MIDI Timecode Destinations

Cubase can send MTC to any MIDI port. Use this section to specify the MIDI ports to which MTC is routed. Devices that can lock to MTC will chase Cubase's timecode position.

NOTE

Some MIDI interfaces send MTC over all ports by default. If this is the case, only select one port of the interface for MTC.




MIDI Timecode Follows Project Time

Activate this option to ensure that the MTC output follows Cubase's time position at all times including looping, locating, or jumping while playing. If not, MTC will continue on without changing locations at a loop or jump point until playback stops.

MIDI Clock Destinations

Some MIDI devices like drum machines can match their tempo and location to incoming MIDI clock. Select any MIDI ports that you want to output MIDI clock.



MIDI Clock Follows Project Position

Activate this option to ensure that the MIDI clock device follows Cubase when looping, locating, or jumping while playing.

NOTE

Some older MIDI devices might not respond well to these positioning messages and could take some time synchronizing to the new location.

Always Send Start Message

MIDI clock transport commands include Start, Stop, and Continue. However, some MIDI devices do not recognize the Continue command. By activating the “Always Send Start Message” option, you can avoid this problem with specific MIDI devices.

Send MIDI Clock in Stop Mode

Activate this option if you are working with a device that needs MIDI clock to run continuously in order to operate arpeggiators and loop generators.

Synchronized operation

Once you have connected all the devices that will be synchronized, it is important to understand how Cubase operates in Sync mode.

- To enable Sync mode, activate **Use External Synchronization** on the **Transport** menu.

Sync mode

If you activate “Use External Synchronization” on the Transport menu, the following happens:

- Cubase Pro only: Transport commands are routed to the machine control destination output as specified in the Project Synchronization Setup dialog. Locate, Play, Stop, and Record commands will now be sent to an external device.
- Cubase awaits incoming timecode from the chosen timecode source defined in the Project Synchronization Setup dialog in order to play. Cubase will detect incoming timecode, locate to its current position, and start playback in sync with the incoming timecode.

Cubase Pro only: In a typical scenario, an external tape machine, such as a VTR, has its timecode output connected to Cubase. Cubase is sending machine control commands to the deck. When Sync is activated and you click Play on the Transport panel, a play command is sent to the VTR. The VTR in turn starts playback, sending timecode back to Cubase. Cubase then synchronizes to that incoming timecode.

Example Scenarios (Cubase Pro only)

To better understand how synchronization options can be utilized, an example scenario is provided.

Personal music studio

In a personal music studio, the user might have the need of synchronizing with an external recording device such as a portable hard disk recorder used for live remote recordings.

In this example, MIDI will be used for timecode and machine control while the audio clock will be handled by Lightpipe digital audio connections.

- If “Use External Synchronization” is activated on the Transport menu, Cubase sends MMC commands to the hard disk recorder.
Cubase can remotely start playback of the recorder.
- The hard disk recorder is using audio clock from Cubase’s audio interface as the speed reference.
It is also possible for Cubase to use the audio clock from the recorder. The audio clock is carried over the Lightpipe digital audio connection that also carries audio signals.
- The hard disk recorder sends back MTC to Cubase.
When the recorder begins playing, MTC is sent back to Cubase which will sync to that timecode.

Sync settings for personal music studio

To synchronize the devices in this example scenario, proceed as follows:

PROCEDURE

1. Make the connections as shown in the diagram above.
In this simple example, any device that uses MTC can be substituted.
2. Open the Project Synchronization Setup dialog and select “MIDI Timecode” as the timecode source.
When recording from the hard disk recorder into Cubase, Cubase will be the machine control master and the timecode slave, locking to incoming MTC.
3. In the “Machine Control Output Destination” section, select the “MIDI Machine Control” option.
Cubase will now send MMC commands to the hard disk recorder to locate and start playback.
4. In the “Machine Control Output Settings” section, assign the MIDI input and output ports that are connected to the hard disk recorder.
Since MMC uses 2-way communication, both MIDI ports should be connected. Be sure the MIDI filter does not echo SysEx data.
5. On the Transport menu, activate “Use External Synchronization”.
This routes transport commands to the hard disk recorder via MIDI and sets Cubase as the timecode slave.
6. On the hard disk recorder, enable MMC and MTC.
Follow the instructions on how to set up the unit to receive MMC commands and transmit MTC.
7. In Cubase, click the Play button.

The hard disk recorder should start playback and send MTC to Cubase. Once Cubase syncs to MTC, the status on the Transport panel should read "Lock" and show the current frame rate of incoming MTC.

Working with VST System Link

VST System Link is a network system for digital audio that allows you to have several computers working together in one large system. Unlike conventional networks it does not require Ethernet cards, hubs, or CAT-5 cables; instead it uses the kind of digital audio hardware and cables you probably already possess in your studio.

VST System Link has been designed to be simple to set up and operate, yet give enormous flexibility and performance gains in use. It is capable of linking computers in a "ring" network (the System Link signal is passed from one machine to the next, and eventually returns to the first machine). VST System Link can send its networking signal over any type of digital audio cable, including S/PDIF, ADAT, TDIF, or AES, as long as each computer in the system is equipped with a suitable ASIO compatible audio interface.

Linking up 2 or more computers gives you vast possibilities:

- Dedicate one computer to running VST instruments while recording audio tracks on another.
- If you need lots of audio tracks, you may simply add tracks on another computer.
- You could have one computer serve as a "virtual effect rack", running CPU-intensive send effect plug-ins only.
- Since you can use VST System Link to connect different VST System Link applications on different platforms, you can take advantage of effect plug-ins and VST instruments that are specific to certain programs or platforms.

Requirements

The following equipment is required for VST System Link operation:

- 2 or more computers.
These can be of the same type or use different operating systems – it does not matter. For example, you can link an Intel-based PC to an Apple Macintosh without problems.
- Each computer must have audio hardware with specific ASIO drivers.
- The audio hardware must have digital inputs and outputs.
To be able to connect the computers, the digital connections must be compatible, that is, the same digital formats and connection types must be available.
- At least one digital audio cable must be available for each computer in the network.
- A VST System Link host application must be installed on each computer.
Any VST System Link application can connect to another.

Additionally, use of a KVM switchbox is recommended.

Using a KVM switchbox

Whether you want to set up a multi-computer network or a small network in a limited space, it is a good idea to invest in a KVM (Keyboard, Video, Mouse) switchbox. With one of these you can use the same keyboard, monitor, and mouse to control each computer in the system, and you can switch between computers very rapidly. If you decide not to go this route, the network will function just the same, but you may end up doing a lot of jumping from one machine to the other while setting up!

Making connections

Below, we assume that you are connecting 2 computers. Should you have more than 2 computers, it is still best to start with 2 and add the others one by one once the system is working – this makes troubleshooting easier if you run into problems. For 2 computers, you will need 2 digital audio cables, one in each direction:

PROCEDURE

1. Use the first digital audio cable to connect the digital output of computer 1 to the digital input of computer 2.
2. Use the other cable to connect the digital output of computer 2 to the digital input of computer 1.

If a card has more than one set of inputs and outputs, choose whichever one that suits you – for simplicity usually the first set is best.

Synchronization

Before you proceed, you need to make sure that the clock signals on your ASIO cards are synchronized correctly. This is essential when cabling any kind of digital audio system, not just **VST System Link**.

IMPORTANT

All digital audio cables by definition always carry a clock signal as well as audio signals, so you do not have to use a special word clock input and output for this (although you may find that you get a slightly more stable audio system if you do, especially when using multiple computers).

The clock mode or sync mode is set up in the ASIO control panel of the audio hardware.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select **VST Audio System**.
 3. In the **ASIO Driver** pop-up menu, select your audio hardware driver.
 4. In the **Devices** list, select the your audio interface.
 5. Click the **Control Panel** button.
 6. Open the ASIO control panel on the other computer as well.
If you are using another **VST System Link** host application on that computer, check its documentation for details on how to open the ASIO control panel.
 7. Now you need to make sure that one audio card is set to be the clock master and all other cards are set to be clock slaves, that is, they listen for the clock signal coming from the clock master.
The naming and procedure for this differs depending on the audio hardware – consult its documentation if required. If you are using Steinberg Nuendo ASIO hardware, all cards default to the **AutoSync** setting. In this case you must set one of the cards (and only one) to **Master** in the **Clock Mode** section of the control panel.
-

RESULT

Typically, the ASIO control panel for an audio card contains some indication of whether or not the card receives a proper sync signal, including the sample rate of that signal.

This is a good indication that you have connected the cards and set up clock sync properly. Check your audio hardware's documentation for details.

IMPORTANT

It is very important that only one card is the clock master, otherwise the network cannot function correctly. Once you have set this up, all the other cards in the network will take their clock signal from this card automatically.

The only exception to this procedure is if you are using an external clock – from a digital mixing desk or a special word clock synchronizer, for example. In that case you must leave all your ASIO cards in clock slave or **AutoSync** mode and make sure that each of them is listening for the signal coming from the synchronizer. This signal is usually passed through your ADAT cables or word clock connectors in a daisy chain fashion.

VST System Link and latency

The general definition of latency is the amount of time it takes any system to respond to whatever messages are sent to it. For example, if your system's latency is high and you play VST instruments in realtime, you will get a noticeable delay between when you press a key and when you hear the sound of the VST instrument. Nowadays, most ASIO-compatible audio cards are capable of operating with very low latencies. Also, all VST applications are designed to compensate for latency during playback, making the playback timing tight.

However, the latency time of a VST System Link network is the total latency of all the ASIO cards in the system added together. Therefore it is extra important to minimize the latency times for each computer in the network.

IMPORTANT

The latency does not affect the synchronization – it is always perfectly in time. But it can affect the time it takes to send and receive MIDI and audio signals, or make the system seem sluggish.

To adjust the latency of a system, you adjust the size of the buffers in the ASIO control panel – the lower the buffer size, the lower the latency. It is best to keep to fairly low latencies (buffer sizes) if your system can handle it – about 12 ms or less is usually a good idea.

Setting up your software

Now it is time to set up your programs. The procedures below describe how to set things up in Cubase. If you are using another program on the other computer, please refer to its documentation.

Setting the sample rate

The projects in both programs must be set to use the same sample rate. Select "Project Setup..." from the Project menu and make sure that the sample rate is the same in both systems.

Streaming digital audio between applications

PROCEDURE

1. Create input and output busses in both applications and route these to the digital inputs and outputs.
The number and configuration of the busses depend on your audio hardware and on your needs. If you have a system with 8 digital i/o channels (such as an ADAT connection), you could create several stereo or mono busses, a surround bus together with a stereo bus, or any combination you need. The important thing is that you should have the same configuration in both applications – if you have 4 stereo output busses on computer 1, you want 4 stereo input busses on computer 2, etc.
2. Set things up so that computer 1 plays back some audio.

For example, you could import an audio file and play it back in Cycle mode.

3. In the Inspector or MixConsole, make sure that the channel containing the audio material is routed to one of the digital output busses.
4. On computer 2, open the MixConsole and locate the corresponding digital input bus. The audio being played back should now “appear” in the program running on computer 2. You should see the input bus level meters moving.
5. Reverse this procedure so that computer 2 plays back and computer 1 “listens”.

RESULT

Now you have verified that the digital connection works as it should.

NOTE

From this point on in this chapter, we refer to the busses connected to the digital inputs and outputs as “VST System Link busses”.

Settings for the audio hardware

When you exchange VST System Link data between computers, it is important that the digital information is not changed in any way between the programs. Therefore, you should open the control panel (or additional application) for your audio hardware and make sure that the following conditions are met:

- If there are additional “format settings” for the digital ports that you use for VST System Link data, make sure that these are turned off.
For example, if you are using an S/PDIF connection for VST System Link, make sure that “Professional format”, Emphasis, and Dithering are turned off.
- If your audio hardware has a mixer application allowing you to adjust the levels of digital inputs and outputs, make sure that this mixer is disabled or that the levels for the VST System Link channels are set to ± 0 dB.
- Similarly, make sure no other forms of DSP (pan, effects, etc.) are applied to the VST System Link signal.

Notes for Hammerfall DSP users

If you are using RME Audio Hammerfall DSP audio hardware, the Totalmix function allows for extremely complex signal routing and mixing in the audio hardware. This can in some situations lead to “signal loops” in which case the VST System Link will not work. If you want to make absolutely sure this will not cause any problems, select the default or “plain” preset for the Totalmix function.

Activating VST System Link

Before you proceed, you need to make sure that **VST System Link** is set as the timecode source in the **Project Synchronization Setup** dialog and that the desired sync options are activated.


After setting up the inputs and outputs, you now need to define which input/output will carry the actual **VST System Link** information.

The **VST System Link** networking signal is carried on only one bit of one channel. This means that if you have an ADAT-based system which normally carries 8 channels of 24-bit audio, once you activate **VST System Link** you will have 7 channels of 24-bit audio and one channel of 23-bit audio (the least significant bit of this last channel will be used for networking). In practice this makes no discernible difference to the audio quality, since you will still have around 138 dB headroom on this channel.

To set things up, open the **VST System Link** panel:

PROCEDURE

1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select **VST System Link**.
The **VST System Link** settings are shown to the right of the **Devices** list.



3. Use the **ASIO Input** and **ASIO Output** pop-up menus to define which channel is the networking channel.
4. Activate the **Active** checkbox at the top left of the panel.
5. Repeat the steps above for every computer in the network.

RESULT

As the computers are made active, you should see the Sending and Receiving indicators flashing on each active computer, and the name of each computer should appear in the list at the bottom of the pane. Each computer is assigned a random number – do not worry about this, it is just so the network knows internally which one is which.

- You can double-click on the name in bold (which is the name of the computer you are working on) and set it to whatever other name.

This name will appear in the **VST System Link** window of every computer on the network.

NOTE

If you do not see the name of each computer appearing once you have made it active, you need to check your settings. Go through the procedure above again and make sure that all ASIO cards are listening to the digital clock signals correctly, and that each computer has the correct inputs and outputs assigned to the **VST System Link** network.

RELATED LINKS

[Timecode Preferences](#) on page 940

Putting the network online

After each computer's name you will see whether it is online or not. When a computer is online, it will receive transport and timecode signals, and its sequencer application can be started and stopped by remote control. If it is off-line, it can only be started from its own keyboard – it is effectively an independent machine, although it is still on the network.

NOTE

Note that any computer can control any and all of the others – VST System Link is a peer-to-peer network and there is no absolute “master” computer.

To put all computers online, proceed as follows:

PROCEDURE

1. For all computers, activate the Online checkbox on the VST System Link page.
 2. Start playback on one computer to check that the system is working – all computers should start almost instantly and play perfectly in time, with sample-accurate precision.
 - The Offset Samples setting allows you to adjust whether one machine will play slightly ahead or behind the rest.
This is normally not needed, but occasionally with some hardware you may find that the lock is a few samples out. For now, leave it set to 0 – it will most likely be what you want.
 - The Transfer Bits setting allows you to specify whether you want to transfer 24 or 16 bits. This allows you to use older audio cards which do not support transfer of 24 bits.
-

RESULT

VST System Link sends and understands all transport commands (such as play, stop, fast forward, rewind, etc.). This allows you to control the entire network from one computer. If you jump to a locator point on one machine, all other machines will also instantly jump to that locator point.

IMPORTANT

Make sure that all computers have their tempos set to the same value, otherwise your synchronization will be seriously skewed.

Scrubbing via VST System Link

You can scrub on one computer and have the video and audio on another computer scrub along. However, the playback on the linked systems may not be perfectly in sync while scrubbing and there are some further restrictions you should bear in mind when scrubbing via VST System Link:

- Use a remote controller for scrubbing.
- Always use the system where you started scrubbing to control the scrubbing.
Changing the scrub speed on a remote system will only change the speed on the local system.
- You can start playback on all systems.
This stops scrubbing and enters playback on all systems in sync.

Using MIDI

As well as supplying transport and sync control, VST System Link also supplies up to 16 MIDI ports, with 16 channels each.

PROCEDURE

1. Use the MIDI Inputs and MIDI Outputs value fields to specify the number of MIDI ports you need.
The default value is 0 MIDI In and 0 MIDI Out ports.
2. In the Project window, create a MIDI track and open the Inspector (top section).
3. If you now open the Input or Output Routing pop-up menu, you will find the specified System Link ports added to the list of MIDI inputs or outputs.



This allows you to route MIDI tracks to VST instruments running on another computer.

RELATED LINKS

[Application examples](#) on page 953

The “Use Selected ASIO Ports for Data only” setting

If you are sending huge amounts of MIDI data at once, there is a small possibility that you might run out of bandwidth on your **VST System Link** network. This will manifest itself by notes “choking” or timing becoming erratic.

If this happens, you can devote more bandwidth to MIDI by activating **Use Selected ASIO Ports for Data only** on the **VST System Link** page of the **Studio Setup** dialog. When this is activated, the **VST System Link** information will be sent on the entire channel instead of just one bit, more than enough for all the MIDI you could ever hope to use. The downside is that you can no longer use this ASIO channel for audio transfer (do not connect it to a speaker!), thus leaving you with only 7 audio channels in our ADAT cable example. Depending on how you work, this might be a reasonable compromise.

Hearing the network audio

If you are using an external mixing desk, hearing your audio really is not an issue – just plug the outputs of each computer into the desired channels on the external mixing desk, start playback on one of the computers, and you are good to go.

However, many people prefer to mix internally inside the computer and just use a desk for monitoring (or maybe not use any external mixer at all). In this case you will need to select one computer to be your “main mix computer” and send the audio from your other computers into this.

In the following example, we assume you are using 2 computers, with computer 1 as your main mix computer and computer 2 running 2 additional stereo audio tracks, an FX channel track with a reverb plug-in and a VST instrument plug-in with stereo outputs.

PROCEDURE

1. Set things up so that you can listen to the audio playback from computer 1.
In other words, you need an unused set of outputs, such as an analog stereo output, connected to your monitoring equipment.
2. On computer 2, route each of the 2 audio tracks to a separate output bus.
These should be busses connected to the digital outputs – let’s call them Bus 1 and 2.
3. Route the FX channel track to another VST System Link bus (Bus 3).
4. Route the VST instrument channel to yet another bus (Bus 4).
5. Go back to computer 1 and check the corresponding 4 VST System Link input busses.
If you start playback on computer 2, the audio should “appear” on the input busses on computer 1. However, to mix these audio sources you need actual mixer channels.
6. Add 4 new stereo audio tracks on computer 1 and route these to the output bus you use for listening, such as the analog stereo outputs.
7. For each of the audio tracks, select one of the 4 input busses.
Now, each computer 2 bus is routed to a separate audio channel on computer 1.
8. Activate monitoring for the 4 tracks.

RESULT

If you now start playback, the audio from computer 2 will be sent “live” to the new tracks on computer 1, allowing you to hear them together with any tracks you play back on computer 1.

Adding more tracks

What if you have more audio tracks than you have VST System Link busses (physical outputs)? Then you just use the computer 2 mixer as a submixer: Route several audio channels to the same output bus and adjust the output bus level if needed.

NOTE

If your audio cards have multiple sets of input and output connections, you can link up multiple ADAT cables and send audio via any of the busses on any of the cables.

Internal mixing and latency

One problem with mixing inside the computer is the latency issue we mentioned earlier. The VST engine always compensates for record latencies, but if you are monitoring through computer 1 you will hear a processing delay while you listen to signals coming from your other computers (not on your recording!). If your audio card in computer 1 supports ASIO Direct Monitoring you should definitely turn this on. You can find the setting on the VST Audio System device panel for

your hardware. Most modern ASIO cards support this function. If yours does not, you may want to change the Offset Samples value on the VST System Link page to compensate for any latency issues.

RELATED LINKS

[ASIO Direct Monitoring](#) on page 240

Setting up a larger network

Setting up a larger network is not much more difficult than a 2-computer network. The main thing to remember is that VST System Link is a daisy chain system. In other words, the output of computer 1 goes to the input of computer 2, the output of computer 2 goes to the input of computer 3, and so on around the chain. The output of the last computer in the chain must always go back into the input of computer 1, to complete the ring.

Once you have done this, the transmission of all the transport, sync, and MIDI information to the whole network is handled pretty much automatically. However, where you may run into confusion in a large network is in the transmission of audio signals back to a central mix computer.

If you have lots of hardware inputs and outputs on your ASIO cards, you do not have to send audio via the chain at all, but can transmit it directly to the master mix computer via one or more of its other hardware inputs. For example, if you have a Nuendo Digiset interface or 9652 card on computer 1, you could use ADAT cable 1 for networking, ADAT cable 2 as a direct audio input from computer 2, and ADAT cable 3 as a direct audio input from computer 3.

You can also transmit audio via the ring system if you do not have enough hardware I/Os for direct audio transmission. For example, in a 4-computer scenario you could send audio from computer 2 into a channel in the mixer in computer 3, from there to a channel in the mixer in computer 4, and from there back to the master mixer in computer 1. This can certainly be tricky to set up, so for complex networks it is generally recommended to use ASIO cards with at least 3 separate digital I/Os.

Application examples

Using one computer for VST instruments

In this example, one computer will be used as main record and playback machine, and another computer as a virtual synth rack.

PROCEDURE

1. Record a MIDI track into computer 1.
2. Once you have finished recording, route the MIDI output of that track to VST System Link MIDI port 1.
3. On computer 2, open up the VST Instruments window and assign an instrument to the first slot in the rack.
4. Route the VST instrument channel to the desired output bus.
If you are using computer 1 as your main mixing computer, this would be one of the VST System Link output busses, connected to computer 1.
5. Create a new MIDI track in the Project window of computer 2 and assign the MIDI output of the track to the VST instrument you created.
6. Assign the MIDI input of the track to be VST System Link port 1.
Now, the MIDI track on computer 1 is routed to the MIDI track on computer 2, which in turn is routed to the VST instrument.
7. Now activate monitoring for the MIDI track on computer 2, so that it will listen and respond to any MIDI commands coming in.

In Cubase, click the Monitor button in the track list or Inspector.

8. Start playback on computer 1.
It will now send the MIDI information on the track to the VST instrument loaded on computer 2.
-

RESULT

Even with a slow computer you should be able to stack a whole bunch of extra VST instruments this way, expanding your sound palette considerably. Do not forget that VST System Link MIDI is also sample-accurate, and thus has much tighter timing than any hardware MIDI interface ever invented!

Creating a virtual effect rack

The effect sends for an audio channel in Cubase can either be routed to an FX channel track or to any activated group or output bus. This allows you to use a separate computer as a “virtual effect rack”.

PROCEDURE

1. On computer 2 (the machine you will use as effect rack), add a new stereo audio track.
You cannot use an FX channel track in this case, since the track must have an audio input.
 2. Add the desired effect as an insert effect for the track.
Let's say you add a high-quality reverb plug-in.
 3. In the Inspector, select one of the VST System Link busses as input for the audio track.
You want to use a separate VST System Link bus, which will only be used for this purpose.
 4. Route the channel to the desired output bus.
If you are using computer 1 as your main mixing computer, this would be one of the VST System Link output busses, connected to computer 1.
 5. Activate monitoring for the track.
 6. Go back to computer 1 and select a track to which you want to add some reverb.
 7. Bring up the effect sends for the track in the Inspector or the MixConsole.
 8. Open the Send Routing pop-up menu for one of the sends and select the VST System Link bus assigned to the reverb in step 3.
 9. Use the Send slider to adjust the amount of effect as usual.
-

RESULT

The signal will be sent to the track on computer 2 and processed through its insert effect, without using any processor power on computer 1.

You can repeat the steps above to add more effects to the “virtual effect rack”. The number of effects available this way is only limited by the number of ports used in the VST System Link connection (and of course by the performance of computer 2, but given that it will not have to handle any recording or playback, you should be able to use quite a lot of effects).

Getting extra audio tracks

All computers on a VST System Link network are locked with sample-accuracy. Therefore, if you find that the hard drive on one computer is not fast enough to run as many audio tracks as you need, you can record new tracks on one of the other computers instead. This would create a “virtual RAID system”, with several disks all operating together. All tracks will remain locked together just as tightly as if they were all running on the same machine. This means that you effectively have an unlimited track count! Need another 100 tracks? Just add another computer.

Dedicated Video Playback

Playback of high-resolution video can be taxing on a system's CPU. By dedicating one computer for video playback via System Link, you can free up resources on your main CPU for audio and MIDI processing. Since all transport commands will respond on the VST System Link computers, scrubbing video is possible even when it is coming from another computer.

Video

Cubase supports the integration of video files in your project.

You can play back video files in various formats and via different output devices from within Cubase, extract the audio material from a video file, and edit your music to the video.

Video File Compatibility

When working on a project involving a video file, you must make sure that the video file type works on your system.

NOTE

If you are not able to play back a specific video file, use an external application to convert the file into a compatible format.

To find out what video files are supported, refer to the Help Center on the Steinberg web site.

RELATED LINKS

[Codecs](#) on page 956

Video Container Formats

Video and other multimedia files come in a container format.

This container holds various streams of information including video and audio, but also metadata such as synchronization information required to play back audio and video together. Data regarding creation dates, authors, chapter markings, and more can also be held within the container format.

The following container formats are supported by Cubase:

MOV

This is a QuickTime movie.

MPEG-4

This format can contain various metadata for streaming, editing, local playback, and interchange of content. Its file extension is `.mp4`.

AVI

This is a multimedia container format introduced by Microsoft.

Codecs

Codecs are methods of data compression used to make video and audio files smaller and more manageable for computers.

For further details, refer to the Help Center on the Steinberg web site.

Frame Rates

Cubase supports different video and film frame rates.

Frame rate (speed)

Regardless of the frame counting system, the actual speed at which frames of video go by in real time is the true frame rate.

Cubase supports the following frame rates:

23.98 fps (Cubase Pro only)

This frame rate is used for film that is being transferred to NTSC video and must be slowed down for a 2-3 pull-down telecine transfer. It is also used for the type of HD video referred to as 24 p.

24 fps

This is the true speed of standard film cameras.

24.98 fps (Cubase Pro only)

This frame rate is commonly used to facilitate transfers between PAL and NTSC video and film sources. It is mostly used to compensate for some error.

25 fps

This is the frame rate of PAL video.

29.97 fps/29.97 dfps

This is the frame rate of NTSC video. The count can be either non-drop or drop-frame.

30 fps/30 dfps

This frame rate is not a video standard anymore but has been commonly used in music recording. Many years ago, it was the black and white NTSC broadcast standard. It is equal to NTSC video being pulled up to film speed after a 2-3 telecine transfer. The count can be either non-drop or drop-frame.

50 fps (Cubase Pro only)

This rate is also referred to as 50 p.

59.94 fps (Cubase Pro only)

This video frame rate is supported by high definition cameras and is compatible with NTSC.

60 fps (Cubase Pro only)

This video frame rate is supported by many high definition cameras. However, the NTSC compatible 59.94 fps frame rate is much more common.

IMPORTANT

Video formats with a variable frame rate (VFR) are not supported.

Video Output Devices

Cubase supports several video output devices.

Viewing video files onscreen in the **Video Player** window may work just fine for many applications, but often it is necessary to display video in a large format for viewing small details and so others involved in the session can also see the video. Cubase provides the ability to use several types of video output devices to accomplish this.

Dedicated Video Cards

You can use a dedicated video card. Video is sent directly to the output of this video device.

The following video cards are supported:

- Blackmagic Design video output devices

IMPORTANT

- You must install the appropriate driver for the video device and set the video card output to the video file resolution used in your project.
 - Video output via FireWire is not supported.
-

RELATED LINKS

[Video Player Setup](#) on page 960

Preparations for Creating Video Projects

Before you can start working with video in Cubase, some basic preparations must be made.

In Cubase, you may work with multiple video files of different formats on the same video track.

NOTE

For proper synchronization of audio and video events, make sure that the project frame rate matches the frame rate of the video file.

RELATED LINKS

[Project Setup Dialog](#) on page 87

Importing Video Files

If you have a compatible video file, you can import it into your project.

PROCEDURE

1. Select **File > Import > Video File**.
 2. In the **Import Video** dialog, select the video file that you want to import.
 3. Optional: Activate **Extract Audio from Video** to import any embedded audio streams.
 4. Click **Open**.
-

RESULT

Cubase creates a video track with a video event. If **Extract Audio from Video** was activated, an audio track with an audio event is positioned below the video track. The corresponding audio clip is saved in the **Pool Record** folder.

NOTE

You can also import video files by dragging them from the **MediaBay**, the File Explorer/macOS Finder and dropping them in your project. If you want Cubase to automatically extract the audio, activate **Extract Audio on Import Video File** in the **Preferences** dialog (**Video** page).

RELATED LINKS

[Pool](#) on page 527

[Extract Audio from Video](#) on page 962

Adopting the Frame Rate

To ensure that the time display of Cubase corresponds to the actual frames in the video, you must set the project frame rate to the frame rate of the imported video file.

PREREQUISITE

The frame rate of the imported video file differs from the project frame rate.



PROCEDURE

1. Select **Project > Project Setup**.
2. In the **Project Setup** dialog, click **Get from Video**.
3. Click **OK**.

RESULT

- If Cubase supports the frame rate of the video, the project frame rate is adopted to it. If needed, the project start time is automatically adjusted to reflect the change in frame rate. For example, if the project frame rate is switched from 30 fps to 29.97 fps, the project start time is adopted so that all the events in the project remain at the same positions in relation to real time.

NOTE

If you want the project start time to remain the same, you must manually change it back. In this case, you must snap the video event to the timeline to ensure proper positioning and synchronization within the project.

Thumbnail Cache Files

For every imported video, file Cubase automatically creates a thumbnail cache file.

RELATED LINKS

[Manually Generating Thumbnail Cache Files](#) on page 959

Manually Generating Thumbnail Cache Files

You can manually generate thumbnail cache files. This is necessary if a thumbnail cache file could not be generated during import because the folder is write-protected, or because you have edited the file with an external video editing application.

PROCEDURE

- Do one of the following:
 - In the **Pool**, right-click the video file and select **Generate Thumbnail Cache**.
 - In the **Project** window, right-click the video event, and select **Media > Generate Thumbnail Cache**.

NOTE

Refreshing an already existing thumbnail cache file can be done only from within the **Pool**.

RESULT

The thumbnail cache file is generated in the background so that you can continue working with Cubase.

Preparations for Video Playback

You can play back imported video files from within Cubase by using the transport controls.

For this to work, you must activate and set up a video output device.


IMPORTANT

Your graphics card must support OpenGL 2.0 or higher.

Video Player Setup

The **Video Player** setup page in the **Studio Setup** dialog allows you to set up your video player, and to check if your video equipment allows for video playback from within Cubase.

- To open the **Video Player** page, select **Studio > Studio Setup** and activate **Video Player** in the **Devices** list.



The following options are displayed:

- 1 Device**
Lists the video output devices that are available on your system.
- 2 Format**
Allows you to select an output format.

NOTE

The **Onscreen Window** device only supports a fixed format.

- 3 Offset**
If the video image does not match the audio, you can enter an offset value in milliseconds to specify how much earlier the video should be delivered. This compensates for the display delay. The offset is only used during playback. It is saved globally for each output device and is independent of the project.
- 4 Active**
Allows you to activate the device that you want to use for playing back video.

Activating a Video Output Device

PROCEDURE

- 1.** Select **Studio > Studio Setup**.
- 2.** In the **Devices** list, activate **Video Player**.
The available video output devices are listed in the **Device** column.

3. In the **Active** column, activate the checkbox for the device that you want to use for playing back video.

NOTE

If you have no external device connected, you can use the **Onscreen Window** device that allows you to play back the video file on your computer monitor.

RELATED LINKS

[Video Output Devices](#) on page 957

Video Player Window

The **Video Player** window provides different size options for video playback on your computer screen. However, the larger the size of the window and the higher the resolution of your video, the more processor load is needed.

- To open the **Video Player** window, select **Studio > Video Player**.



Fullscreen Mode

Sets the window to full screen mode. To exit full screen mode, open the context menu and select **Exit Fullscreen Mode** or press **Esc**.

Quarter Size

Reduces the window to a quarter of the actual size.

Half Size

Reduces the window to half the actual size.

Actual Size

Sets the window to the size of the video.

Double Size

Enlarges the window to twice the actual size.

Aspect Ratio

You can also drag the borders of the **Video Player** window to resize it. However, this might lead to a distorted image. To prevent this, you can set an option from the **Aspect Ratio** pop-up menu.

- If you select **None**, the aspect ratio of the video is not kept when you resize the window. The image is enlarged/reduced to occupy the whole Video Player window.
- **Internal** allows you to resize the window freely while keeping the aspect ratio of the video. Borders might be displayed around the video image to fill the window.
- **External** allows you to resize the window within some limits so that the video image always fills the full window and its aspect ratio is kept.

- **NOTE**

In full screen mode, the aspect ratio of the video is always kept.

Scrubbing Video

You can scrub video events, that is, play them back forwards or backwards.

PROCEDURE

1. Select **Studio > Video Player**.
 2. Do one of the following:
 - Click in the **Video Player** window and move the mouse to the left or to the right.
 - Use a jog wheel on a remote controller.
-

Editing Video

Video events are created automatically when you import a video file.

You can view and edit video events in the **Project** window. A video event triggers the playback of the corresponding video clip.

You can copy and trim video events. You can also lock video events in the **Project** window.

You cannot draw, glue, and mute video events, or apply fades or crossfades.

RELATED LINKS

[Pool](#) on page 527

Extract Audio from Video

You can extract the audio stream of a video file on import. Cubase supports video files with audio in mono or stereo, and multi-channel configurations with up to 48 channels.

To extract audio from a video file, do one of the following:

- Select **File > Import > Video File** and activate **Extract Audio from Video** in the dialog.
- Select **Media > Extract Audio from Video File**, and select the video file in the file dialog.
- Select **File > Import > Audio from Video File**.

This creates an audio clip in the **Pool**, but does not add any events to the **Project** window.

A dialog is displayed allowing you to select different import options.

The extracted audio stream is added to the project on a new audio track and can be edited like all other audio material.

RELATED LINKS

[Import Options for Audio Files](#) on page 254

[Importing Video Files](#) on page 958

Exchanging Files with Other Applications

OMF Files (Cubase Pro only)

Open Media Framework Interchange (OMFI) is a platform-independent file format that allows you to transfer digital media between different applications.

Cubase can import and export OMF files.

Importing OMF Files

PROCEDURE

1. Select **File > Import > OMF**.
2. In the file dialog, select the OMF file and click **Open**.
3. Optional: If a project is open, choose if you want to create a new project. If you select **No**, the OMF file is imported into the current project.
4. In the **Import Options** dialog, choose the tracks that you want to import and make your settings.
5. Click **OK**.
6. Optional: If the OMF file contains video event information, choose whether you want to create markers at the start position of the video events.


NOTE

You can use these markers as position references if you want to manually import the video files.

RESULT

The audio events of the imported OMF file are added.

OMF Import Options



Import

Allows you to select a track for import.

Type

Shows the media type of the track.

Track Name

Shows the track name.

Select All Tracks

Selects all tracks for import.

Import All Media Files

Imports media files that are not referenced by events.

Import Clip Gain as Automation

Imports volume automation and envelopes of the volume automation track of each track.

Import at Timecode Position

Inserts the elements contained in the file at their original timecode positions.

This ensures that the elements are placed at their correct time positions even if Cubase uses a different frame rate than the file.

Import at Absolute Time

Inserts the elements contained in the file starting at the timecode position saved in the file and keeping the relative distances between the elements.

Exporting OMF Files

PROCEDURE

1. Select **File > Export > OMF**.
2. In the **Export Options** dialog, select the tracks that you want to include in the exported file and make your settings.
3. Click **OK**.


4. In the file dialog, specify a name and location.
 5. Click **Save**.
-

RESULT

The OMF file is exported. It contains or references all audio files that are played in the project, including fade and edit files.

Unused audio files that are referenced in the **Pool**, or any MIDI data are not contained in the file. Video files are not included.

OMF Export Options



Export

Allows you to select a track for export.

Track Name

Shows the track name.

Select All

Selects all tracks in the project for export.

From Left to Right Locator

Allows you to export the range between the locators only.

Media Destination Path

Allows you to specify a location for the exported files. You can also click **Browse**.

NOTE

You can create references to media destinations that do not exist on the system you are working with. This allows you to prepare files for use in projects on another system or in a network environment, for example.

Copy Media

Allows you to create copies of all the media files. By default, the copied audio files are placed in a subdirectory in the export destination folder. To specify a different location for the copied files, use the **Media Destination Path** field.

Consolidate Events

Allows you to copy only the portions of audio files that are used in the project.

The **Handle Length** value allows you to define a length in milliseconds to include audio outside each event boundary for later fine-tuning. Handles allow you to adjust fades or edit points when the project is imported in another application.

OMF 1.0 File

Allows you to select an OMF version. Select this depending on which version is supported by the application in which you plan to import the file.

OMF 2.0 File

Allows you to select an OMF version. Select this depending on which version is supported by the application in which you plan to import the file.

Export Media File References

Exports only media file references. This keeps the exported file small. However, the referenced audio files must be available for the receiving application.

Export All to One File

Exports all data to one self-contained file. This could result in a large file size.

Export Clip-Based Volume (OMF 2.0 only)

Includes the volume settings that you set up with the volume handles for the events.

Use Fade Curves (OMF 2.0 only)

Includes the fades that you set up with the fade handles for the events.

Export Clip Names (OMF 2.0 only)

Includes the clip names for the events.

Export Sample Size

Allows you to set a sample size for the exported files.

Quantize Events to Frames

Moves the event positions in the exported file to exact frames. This is sometimes necessary when exporting projects to video workstations that limit the accuracy of edits to the frame.

ReWire

Introduction

ReWire is a special protocol for streaming audio between two computer applications.

Developed by Propellerhead Software and Steinberg, ReWire provides the following possibilities and features:

- Realtime streaming of up to 256 (Cubase Artist: 128) separate audio channels, at full bandwidth, from the synthesizer application into the mixer application.
In this case, the mixer application is of course Cubase. An example of a synthesizer application is Propellerhead Software's Reason.
- Automatic, sample accurate synchronization between the audio in the two programs.
- The possibility to have the two programs share one audio card and take advantage of multiple outputs on that card.
- Linked transport controls that allow you to play, rewind, etc., either from Cubase or from the synthesizer application (provided it has some kind of transport functionality).
- Automatic audio mixing functions of separate channels as required.
In the case of Reason, for example, this allows you to have separate channels for the different devices.
- Additionally, ReWire offers the possibility to route MIDI tracks in Cubase to the other application, for full MIDI control.
For each ReWire compatible device, a number of extra MIDI outputs will be made available in Cubase. In the case of Reason, this allows you to route different MIDI tracks in Cubase to different devices in Reason, with Cubase serving as the main MIDI sequencer.
- The overall load on your system is much reduced, compared to when using the programs together in the conventional way.

Enabling ReWire Applications

To use the available ReWire applications on your computer in your project, you must enable them in the **ReWire Setup** dialog.

IMPORTANT

- Enabling ReWire applications may have an impact on performance and stability of Cubase, even if the ReWire connection is not used. We therefore recommend to enable only ReWire applications that you want to use in your project.
 - Disabling a ReWire application, removes the corresponding ReWire channels from your project. All associated automation or parameter settings are lost.
-

PROCEDURE

1. Select **Studio > ReWire > ReWire Setup**.
 2. Activate the ReWire applications that you want to use.
 3. Click **Apply**.
-

RESULT

The enabled ReWire applications become available in the **ReWire** submenu.

AFTER COMPLETING THIS TASK

You can activate ReWire channels in the ReWire panel of the application.

RELATED LINKS

[Activating ReWire channels](#) on page 970

Launching and quitting

When using ReWire, the order in which you launch and quit the two programs is very important.

Launching for normal use with ReWire

PROCEDURE

1. First launch Cubase.
 2. Enable one or several ReWire channels in the ReWire Device dialog for the other application.
 3. Launch the other application.
It may take slightly longer for the application to start when you are using ReWire.
-

RELATED LINKS

[Activating ReWire channels](#) on page 970

Quitting a ReWire session

When you are finished, you also need to quit the applications in a special order.

PROCEDURE

1. First quit the synthesizer application.
 2. Then quit Cubase.
-

Launching both programs without using ReWire

We cannot think of any scenario, in which you would need to run Cubase and the synthesizer application simultaneously on the same computer, without using ReWire, but you can.

PROCEDURE

1. First launch the synthesizer application.
2. Then launch Cubase.

NOTE

Please note that the two programs now compete for system resources such as audio cards, just as when running with other, non-ReWire audio applications.

Activating ReWire channels

ReWire supports streaming of up to 256 (Cubase Artist: 128) separate audio channels. The exact number of available ReWire channels depends on the synthesizer application. The ReWire device panels in Cubase allow you to activate the channels you that want to use.

PREREQUISITE

You have enabled the ReWire application that you want to use in the **ReWire Setup** dialog.

PROCEDURE

1. Select **Studio > ReWire**, and select the ReWire application that you want to use. The corresponding **ReWire** panel appears. This consists of a number of rows, one for each available ReWire channel.
 2. Click the power buttons to the left to activate/deactivate channels. The buttons light up to indicate activated channels.
 3. Optional: Double-click the labels in the right column, and type in another name. These labels are used in your project to identify the ReWire channels.
-

RESULT

The activated ReWire channels are added to the project.

NOTE

- The more ReWire channels you activate, the more processing power is required.
 - For information about exactly what signal is carried on each channel, refer to the documentation of the synthesizer application.
-

IMPORTANT

Deactivating ReWire channels in the **ReWire** panel, removes the channels from your project. All associated automation or parameter settings are lost.

RELATED LINKS

[Enabling ReWire Applications](#) on page 968

Using the transport and tempo controls

IMPORTANT

This is only relevant if the synthesizer application has some sort of built-in sequencer or similar.

Basic transport controls

When you run ReWire, the transports in the two programs are completely linked. It does not matter in which program you play, stop, fast forward or rewind. However, recording (if applicable) is still completely separate in the two applications.

Loop settings

If there is a loop or cycle facility in the synthesizer application, that loop will be completely linked to the cycle in Cubase. This means that you can move the start and end point for the loop or turn the loop on or off in either program, and this will be reflected in the other.

Tempo settings

As far as tempo goes, Cubase is always the master. This means that both programs will run in the tempo set in Cubase.

However, if you are not using the tempo track in Cubase, you can adjust the tempo in either program, and this will immediately be reflected in the other.

IMPORTANT

If you are using the tempo track in Cubase and the Tempo button is activated on the Transport panel, you should not adjust the tempo in the synthesizer application, since a tempo request from ReWire will automatically deactivate the tempo track in Cubase.

How the ReWire channels are handled

When you activate ReWire channels in the ReWire device panels, they will become available as channels in the MixConsole.

The ReWire channels have the following properties:

- ReWire channels may be any combination of mono and stereo, depending on the synthesizer application.
- ReWire channels have the same functionality as regular audio channels. This means you can set volume and pan, add EQ, insert effects and sends, and route the channel outputs to groups or busses. However, ReWire channels have no monitor buttons.
- All channel settings can be automated using the Read/Write buttons. When you write automation, channel automation tracks will automatically appear in the Project window. This allows you to view and edit the automation graphically, just as with VST instrument channels, etc.
- You can mix down the audio from ReWire channels to a file on your hard disk with the Export Audio Mixdown function. You can export the output bus to which you have routed the ReWire channels. Cubase Pro only: You can also export individual ReWire channels directly – “rendering” each ReWire channel to a separate audio file.


RELATED LINKS

[Mixing Down to Audio Files](#) on page 921

Routing MIDI via ReWire

When using Cubase with a ReWire-compatible application, additional MIDI outputs will automatically appear on the MIDI Output pop-up menus for MIDI tracks. This allows you to play

the synthesizer application via MIDI from Cubase, using it as one or several separate MIDI sound sources.



The MIDI outputs for a Reason song. Here, each output goes directly to a device in the Reason rack.

- The number and configuration of MIDI outputs depends on the synthesizer application.

Considerations and limitations

Sample rates

Synthesizer applications may be limited to audio playback in certain sample rates. If Cubase is set to a sample rate other than those, the synthesizer application will play back at the wrong pitch. Consult the documentation of the synthesizer application for details.


ASIO drivers

ReWire works well with ASIO drivers. By using the Cubase bus system you can route sounds from the synthesizer application to various outputs on an ASIO compatible audio card.

Key Commands

Key commands are assigned to most of main menus and functions in Cubase. They are stored as global Cubase preferences that are used for all your projects.

You can view and add key commands in the **Key Commands** dialog. Key command assignments are also shown in the tooltips.



Tooltips that show an exclamation mark at the end have no key command assigned yet.

You can save key commands settings as a key commands file, which is stored separately and can be imported into any project. This way you can quickly and easily recall customized settings, when moving projects between different computers, for example. The settings are saved in an XML file on the hard disk.

RELATED LINKS

[Saving Key Commands Presets](#) on page 975


Adding Key Commands

You can add key commands in the **Key Commands** dialog.

PROCEDURE

1. Select **File > Key Commands**.
2. Do one of the following:
 - In the **Commands** list, click the plus sign to open a category folder, and select the function to which you want to assign a key command.
 - In the search field, enter the name of the function to which you want to assign a key command.

Assigned key commands are shown in the **Keys** column as well as in the **Keys** section to the right.



3. Click the **Type in Key** field and press the keys you want to use as a key command. You can press individual keys or a combination of one or several modifier keys (**Alt**, **Ctrl/Cmd**, **Shift**) plus any key.
4. Click **Assign**.
The key command is shown in the **Keys** section.
5. Click **OK**.

NOTE

You can set up several different key commands for the same function. Adding a key command to a function that already has another key command will not replace the key command previously defined for the function.

Searching for Key Commands

You can search for key commands. This is useful, if you want to know which key command is assigned to a certain function in Cubase.

PROCEDURE

1. Select **File > Key Commands**.
 2. In the search field, enter the name of the function for which you want to know the key command.
 3. Click **Start/Continue Search**.
-

RESULT

The first matching command is selected and displayed in the **Commands** list. The **Keys** column and the **Keys** list show the assigned key commands, if any.

Removing Key Commands

PROCEDURE

1. Select **File > Key Commands**.
 2. In the **Commands** list, click the plus sign to open a category folder, and select the function for which you want to remove a key command.
 3. Select the key command in the **Keys** section and click the **Delete**.
 4. Click **Remove** to remove the selected key command.
 5. Click **OK**.
-

Setting Up Macros

You can set up a combination of several functions or commands to be performed in one go as a macro.

PROCEDURE

1. Select **File > Key Commands**.
2. Click **Show Macros**.
3. Click **New Macro**.
4. Enter a name for the macro and press **Return** to confirm it.
5. In the upper half of the dialog, select the first command you want to include in the macro.
6. Click **Add Command**.
7. Select the next command and click **Add Command**.


NOTE

Commands are added after the selected command in the list. This allows you to specify the order of commands of a macro.

8. Click **OK**.
-

RESULT

All macros are available in the **Macros** submenu of the **Edit** menu.



To remove a command from the macro, select it in the **Macros** list and click **Delete**. Similarly, to remove an entire macro, select it in the **Macros** list and click **Delete**.

AFTER COMPLETING THIS TASK

You can also assign key commands to a macro. Macros are shown in the **Commands** list in the **Macros** category folder.

Saving Key Commands Presets

You can save key commands settings as presets.

PREREQUISITE

You have set up the key commands to your liking.

PROCEDURE

1. In the **Presets** section, click **Save**.
 2. Enter a name for the preset and click **OK**.
-

RESULT

Your key commands settings are now available as a preset on the **Presets** pop-up menu.

Loading Key Command Presets

You can load key commands presets.

PROCEDURE

- In the **Presets** section, open the pop-up menu and select the preset.
-

RESULT

The key command preset replaces the current key command settings and macros.

Importing Key Command Settings

You can import key commands settings that you saved with an earlier program version.

PROCEDURE

1. Select **File > Key Commands**.
2. In the **Presets** section, click **Import Key Command File**.



3. In the file dialog, select the file that you want to import.
You can import key commands files with the file extension **.key** or macro commands files with the file extension **.mac**.
4. Click **Open**.

RESULT

The file is imported.


AFTER COMPLETING THIS TASK

You can save the imported file as a preset.

Resetting Key Commands

PROCEDURE

1. Select **File > Key Commands**.
2. Do one of the following:
 - In the **Commands** list, select the key command that you want to restore and click **Reset**.



- Click **Reset All**.



RESULT

The key commands are reset.

IMPORTANT

Any changes made to the default key commands are lost. If you want to be able to revert to these settings again, make sure to save them first.

The Default Key Commands

The default key commands are arranged in categories.

NOTE

When the **On-Screen Keyboard** is displayed, the usual key commands are blocked because they are reserved for the **On-Screen Keyboard**. The only exceptions are: **Ctrl/Cmd-S** (Save), **Num *** (Start/Stop Record), **Space** (Start/Stop Playback), **Num 1** (Jump to left locator), **Delete** or **Backspace** (Delete), **Num /** (Cycle on/off), **F2** (Show/Hide Transport panel), and **Alt-K** (Show/Hide On-Screen Keyboard).

Audio Category

Option	Key command
Adjust Fades to Range	A
Auto-Grid	Shift-Q
Crossfade	X

Automation Category

Option	Key command
Open Panel	F6
Read Automation for All Tracks On/Off	Alt-R
Write Automation for All Tracks On/Off	Alt-W

Chords Category

Option	Key command
Chord Pads	Ctrl/Cmd-Shift-C

Devices (Studio) Category

Option	Key command
Audio Connections	F4
Audio Performance	F12
MixConsole	F3
MixConsole in Project Window	Alt-F3

Option	Key command
On-Screen Keyboard	Alt-K
Video Player	F8
VST Instruments	F11

Direct Offline Processing Category

Option	Key command
Direct Offline Processing	F7

Edit Category

Option	Key command
Activate/Deactivate Focused Object	Alt-A
Auto-Scroll On/Off	F
Copy	Ctrl/Cmd-C
Cut	Ctrl/Cmd-X
Cut Time	Ctrl/Cmd-Shift-X
Delete	Delete or Backspace
Delete Time	Shift-Backspace
Duplicate	Ctrl/Cmd-D
Expand/Reduce	Alt-E
Find Track/Channel	Ctrl/Cmd-F
Group	Ctrl/Cmd-G
Group Editing on Selected Tracks On/Off	K
Insert Silence	Ctrl/Cmd-Shift-E
Invert	Alt-F
Left Selection Side to Cursor	E

Option	Key command
Lock	Ctrl/Cmd-Shift-L
Move to Cursor	Ctrl/Cmd-L
Move to Front (Uncover)	U
Mute	M
Mute Events	Shift-M
Mute/Unmute Objects	Alt-M
Open	Ctrl/Cmd-E
Paste	Ctrl/Cmd-V
Paste at Origin	Alt-V
Paste Relative to Cursor	Shift-V
Paste Time	Ctrl/Cmd-Shift-V
Primary Parameter: Decrease	Ctrl/Cmd-Shift-Down Arrow
Primary Parameter: Increase	Ctrl/Cmd-Shift-Up Arrow
Record Enable	R
Redo	Ctrl/Cmd-Shift-Z
Repeat	Ctrl/Cmd-K
Right Selection Side to Cursor	D
Secondary Parameter: Decrease	Ctrl/Cmd-Shift-Left Arrow
Secondary Parameter: Increase	Ctrl/Cmd-Shift-Right Arrow
Select All	Ctrl/Cmd-A
Select None	Ctrl/Cmd-Shift-A
Snap On/Off	J
Solo	S
Split At Cursor	Alt-X

Option	Key command
Split Range	Shift-X
Stationary Cursor	Alt-C
Undo	Ctrl/Cmd-Z
Ungroup	Ctrl/Cmd-U
Unlock	Ctrl/Cmd-Shift-U
Unmute Events	Shift-U
Write	W

Editors Category

Option	Key command
Edit In-Place	Ctrl/Cmd-Shift-I
Open Score Editor	Ctrl/Cmd-R
Open/Close Editor	Return

File Category

Option	Key command
Close	Ctrl/Cmd-W
New	Ctrl/Cmd-N
Open	Ctrl/Cmd-O
Quit	Ctrl/Cmd-Q
Save	Ctrl/Cmd-S
Save As	Ctrl/Cmd-Shift-S
Save New Version	Ctrl/Cmd-Alt-S

Media Category

Option	Key command
Open MediaBay	F5
Open/Close Attribute Inspector	Ctrl-Alt-Num6
Open/Close Favorites	Ctrl-Alt-Num8
Open/Close File Browser	Ctrl-Alt-Num4
Open/Close Filters	Ctrl-Alt-Num5
Open/Close Previewer	Ctrl-Alt-Num2
Preview Cycle On/Off	Shift-Num /
Preview Start	Shift-Enter
Preview Stop	Shift-Num 0
Search MediaBay	Shift-F5

MIDI Category

Option	Key command
Show/Hide Controller Lanes	Alt-L

MixConsole History Category

Option	Key command
Undo MixConsole Step	Alt-Z
Redo MixConsole Step	Alt-Shift-Z

Navigate Category

Option	Key command
Add Down: Expand/Undo selection in the Project window to the bottom/ Move selected event in the Key Editor down 1 octave	Shift-Down Arrow

Option	Key command
Add Left: Expand/Undo selection in the Project window/Key Editor to the left	Shift-Left Arrow
Add Right: Expand/Undo selection in the Project window/Key Editor to the right	Shift-Right Arrow
Add Up: Expand/Undo selection in the Project window to the top/Move selected event in the Key Editor up one octave	Shift-Up Arrow
Bottom: Select bottom track in the track list	End
Down: Select next in the Project window/Move selected event in the Key Editor one semitone down	Down Arrow
Left: Select previous in the Project window/Key Editor	Left Arrow
Right: Select next in the Project window/Key Editor	Right Arrow
Toggle Selection	Ctrl/Cmd-Space
Top: Select top track in the track list	Home
Up: Select next in the Project window/ Move selected event in the Key Editor one semitone up	Up Arrow

Nudge Category

Option	Key command
End Left	Alt-Shift-Left Arrow
End Right	Alt-Shift-Right Arrow

Option	Key command
Left	Ctrl/Cmd-Right Arrow
Right	Ctrl/Cmd-Right Arrow
Start Left	Alt-Left Arrow
Start Right	Alt-Right Arrow

Project Category

Option	Key command
Open Browser	Ctrl/Cmd-B
Open Markers	Ctrl/Cmd-M
Open Pool	Ctrl/Cmd-P
Open Tempo Track	Ctrl/Cmd-T
Remove Selected Tracks	Shift-Delete
Setup	Shift-S

Quantize Category

Option	Key command
Quantize	Q

Set Insert Length Category

Option	Key command
1/1	Alt-1
1/2	Alt-2
1/4	Alt-3
1/8	Alt-4
1/16	Alt-5
1/32	Alt-6

Option	Key command
1/64	Alt-7
1/128	Alt-8
Toggle Dotted	Alt-.
Toggle Triplet	Alt-,

Tool Category

Option	Key command
Draw Tool	8
Drumstick Tool	0
Erase Tool	5
Glue Tool	4
Mute Tool	7
Next Tool	F10
Play Tool	9
Previous Tool	F9
Range Tool	2
Select Tool	1
Split Tool	3
Zoom Tool	6

TrackVersions Category

Option	Key command
Duplicate Version	Ctrl/Cmd-Shift-D
New Version	Ctrl/Cmd-Shift-N
Next Version	Ctrl/Cmd-Shift-H

Option	Key command
Previous Version	Ctrl/Cmd-Shift-G

Transport Category

Option	Key command
Activate Metronome	C
Activate Punch In	I
Activate Punch Out	O
Cycle	Num /
Enter Left Locator	Shift-L
Enter Project Cursor Position	Shift-P
Enter Punch In Position	Shift-I
Enter Punch Out Position	Shift-O
Enter Right Locator	Shift-R
Enter Tempo	Shift-T
Enter Time Signature	Shift-C
Exchange Time Formats	.
Fast Forward	Shift-Num +
Fast Rewind	Shift-Num -
Forward	Num +
Go to Left Locator	Num 1
Go to Project Start	Num . or Num , or Num ;
Go to Right Locator	Num 2
Insert Marker (Windows only)	Insert
Locate Next Event	N
Locate Next Hitpoint	Alt-N

Option	Key command
Locate Next Marker	Shift-N
Locate Previous Event	B
Locate Previous Hitpoint	Alt-B
Locate Previous Marker	Shift-B
Locate Selection Start	L
Loop Selection	Alt-P
Nudge Cursor Left	Ctrl/Cmd-Num -
Nudge Cursor Right	Ctrl/Cmd-Num +
Panel (Transport panel)	F2
Play Selection Range	Alt-Space
Recall Cycle Marker 1 to 9	Shift-Num 1 to Num 9
Record	Num *
Retrospective MIDI Record	Shift-Num *
Rewind	Num -
Set Left Locator to Project Cursor Position	Ctrl/Cmd-Num 1
Set Locators to Selection Range	P
Set Marker 1	Ctrl/Cmd-1
Set Marker 2	Ctrl/Cmd-2
Set Marker 3 to 9	Ctrl/Cmd-Num 3 to 9 or Ctrl/Cmd- 3 to 9
Set Right Locator to Project Cursor Position	Ctrl/Cmd-Num 2
Start	Enter
Start/Stop	Space
Stop	Num 0
To Marker 1	Shift-1

Option	Key command
To Marker 2	Shift-2
To Marker 3 to 9	Num 3 to 9 or Shift-3 to 9
Use External Synchronization	Alt-Shift-T
Use Tempo Track	T

Window Zones Category

Option	Key command
Show/Hide Left Zone	Ctrl/Cmd-Alt-L; Alt-I
Show/Hide Right Zone	Ctrl/Cmd-Alt-R
Show/Hide Upper Zone	Ctrl/Cmd-Alt-U
Show/Hide Lower Zone	Ctrl/Cmd-Alt-E; Ctrl/Cmd-Alt-B
Show/Hide Transport Zone	Ctrl/Cmd-Alt-T
Show Previous Tab	Ctrl/Cmd-Alt-Left Arrow
Show Next Tab	Ctrl/Cmd-Alt-Right Arrow
Show Previous Page	Ctrl/Cmd-Alt-Up Arrow; Page Up
Show Next Page	Ctrl/Cmd-Alt-Down Arrow; Page Down
Show/Hide Info Line	Ctrl/Cmd-I
Show/Hide Overview	Alt-O

Windows Category

Option	Key command
Inline: Key Commands	Shift-F4
Inline: Settings	Shift-F3
Inline: View Layout	Shift-F2

Workspaces Category

Option	Key command
New	Ctrl/Cmd-Num 0
No Workspace	Alt-Num 0
Update Workspace	Alt-U
Workspace 1-9	Alt-Num 1-9
Workspace X	Ctrl/Cmd-Alt-Num 0

Zoom Category


Option	Key command
Zoom Full	Shift-F
Zoom In	H
Zoom In Tracks	Ctrl/Cmd-Down Arrow
Zoom In Vertically	Shift-H
Zoom Out	G
Zoom Out Tracks	Ctrl/Cmd-Up Arrow
Zoom Out Vertically	Shift-G
Zoom to Event	Shift-E
Zoom to Selection	Alt-S
Zoom Tracks Exclusive	Ctrl/Cmd-Alt-Down Arrow

Setting Up Tool Modifier Keys

You can set up tool modifier keys that allow you to get an alternate function when using a tool.

PROCEDURE

1. In the **Preferences** dialog, select **Editing > Tool Modifiers**.



2. Select an option in the **Categories** list, and locate the action for which you want to edit the modifier key.
3. In the **Action** list, select the action.
4. Hold down the desired modifier keys and click **Assign**.

NOTE

If the modifier keys you pressed are already assigned to another tool, you will be asked whether you want to overwrite them. If you do, this will leave the other tool without any modifier keys assigned.

5. Click **OK**.
-

RESULT

The modifier keys for the action are replaced.

Customizing

In Cubase you can organize windows and dialogs in workspaces, set up the appearance of specific elements, customize the colors, and save program settings as profiles.

RELATED LINKS

[Workspaces](#) on page 990

[Using the Setup Options](#) on page 994

[Customizing the Meter Colors](#) on page 995

[Customizing the User Interface Colors](#) on page 996

[Coloring Tracks, Parts, or Events Manually](#) on page 998

[Profiles \(Cubase Pro only\)](#) on page 1001

Workspaces

Workspaces in Cubase allow you to organize windows and specific dialogs for your common work routines.

A workspace saves the size, position, and layout or setting of important windows and dialogs, such as the **Project** window, **MixConsole**, or **Transport** panel. You can define several workspaces. This allows you to quickly switch between different working modes, either through the **Workspaces** menu or by using key commands.

You can define different workspace types that are either available for all projects on your computer or specific for one project. However, when you open a project, its last saved view is opened by default. A view is the window layout and setting that you defined for your project. The last saved view can either be a workspace view or a view that you saved without having any workspace selected. When you open an external project, the last used view on your computer is used by default.

The **Workspaces Organizer** and the **Workspaces** menu allow you to create and modify workspaces.

NOTE

- You can also work without workspaces. In this case, the last used view of the former project will be used when you create a new project.
- In the **Preferences** dialog (**General** page), you can select which view is used when you open a project.

RELATED LINKS

[Open Projects in Last Used View](#) on page 1025

Workspace Types

You can create different workspace types.

Global workspace

Allows you to save a specific layout of dialogs and windows for all projects on your computer. Global workspaces are indicated by the letter G on your **Workspaces** menu.

Project workspace

Allows you to save a specific layout of dialogs and windows that is saved with your current project. This allows you to open your project layout on other computers. Project workspaces are indicated by the letter P on your **Workspaces** menu.

Workspace Templates

Cubase provides sample templates that you can use as a starting point for your own workspaces.

The templates are made for screens with a resolution of 1280x800 px (minimal) or for screens with a resolution of 1920x1080 px (HD). You can change these templates according to your needs.

IMPORTANT

- Deleting and overwriting templates cannot be undone.
- If you have already used global workspaces in earlier Cubase versions, the sample templates are not installed.

The following workspace templates are provided on the **Workspaces** menu:

Project (minimal)

Displays the **Project** window with minimal resolution.

Project + MixConsole (minimal)

Displays the **Project** window and **MixConsole** with minimal resolution.

Project (HD)

Displays the **Project** window with HD resolution.

Project + MixConsole + Channel Settings (HD)

Displays the **Project** window, **MixConsole**, and **Channel Settings** window with HD resolution.

NOTE

To see the **Channel Settings** window, you must select an audio, MIDI, instrument, FX channel, or group channel track before you select the template.

Project + MixConsole + Racks (HD)

Displays the **Project** window, **MixConsole**, and **Racks** with HD resolution.

Workspaces for External Projects

You can determine the view of external projects when you open them in Cubase.

When you open external projects, which are projects that have been created on other computers, the window and dialog settings that you last used on your computer are applied by default. This can either be the last used view that was saved on your computer or one of your specified global workspaces.

If you want to open the original layout setting of a project, you have the following options:

- Select the project's original layout from the project workspaces on the **Workspaces** menu or in the **Workspace Organizer**.
- In the **Preferences** dialog (**General** page), select **Never** from the **Open Projects in Last Used View** menu. This opens all external projects using their original layout. However, this may lead to a modification of your custom layout.

To return to the view that you last saved without any workspace assigned, select **No Workspace** on the **Workspaces** menu.

RELATED LINKS

[Workspaces Organizer](#) on page 993

[Open Projects in Last Used View](#) on page 1025

Creating Workspaces

To save your current dialog and window setting for future use, you can create a new workspace.

PROCEDURE

1. Select **Workspaces > Add Workspace**.
2. In the **Name** field of the **New Workspace** dialog, enter a workspace name.
3. Select the type of workspace that you want to create.
 - **Global Workspace**
 - **Project Workspace**
4. Click **OK**.

RESULT

The workspace is saved and added to the **Workspaces** menu.

Editing Workspaces

You can modify your created workspaces.

NOTE

To change a global workspace to a project workspace and vice versa, you must save it as a different workspace type.

PROCEDURE

1. On the **Workspaces** menu, select the workspace that you want to modify.
2. Make your changes as required.
3. On the **Workspaces** menu, select one of the following:
 - To update your current workspace, click **Update Workspace**.
 - To save your workspace as a different workspace or workspace type, click **Add Workspace**.


RELATED LINKS

[Creating Workspaces](#) on page 992

Workspaces Organizer

The **Workspaces Organizer** allows you to manage the existing workspaces.

To open the **Workspaces Organizer**, click **Workspaces > Organize**.



The **Workspaces Organizer** displays the global workspaces and the project workspaces in separate lists. Every workspace has an assigned key command that lets you switch views quickly. Moving or deleting workspaces within the lists changes the key command assignments. When you change the position of a workspace, the key command assignments remain in their original list position. You can click a key command of a selected workspace to open the respective key command assignment in the **Workspace** category of the **Key Commands** dialog.

To organize your workspace, you have the following options:

Move Up

Moves up a workspace by one position.

Move Down

Moves down a workspace by one position.

Delete

Deletes a selected workspace.

Add

Allows you to create a new workspace using the **New Workspace** dialog.

NOTE

- You can also click and drag a workspace to another position within a list.
- You can move workspaces only within a list. For a global workspace to become a project workspace and vice versa, you must save it as a different type of workspace.
- To rename a workspace, you can double-click the workspace name.

RELATED LINKS

[Workspaces Category](#) on page 988

Using the Setup Options

You can customize the appearance of the following elements:

- Transport panel
- Status line
- Info line
- Toolbars
- Inspector

Setup Context Menus

Setup context menus are available for the **Transport** panel, the toolbars, the info lines, or the **Inspector**.


- To open the setup context menus, right-click the corresponding element.
- **NOTE**

You can also click the corresponding setup buttons  to open the context menu.

The following general options are available on the setup context menus:

- **Show All** makes all items visible.
- **Reset All** resets the interface to the default setting.
- **Setup** opens the setup dialog.

If presets are available, they can be selected on the lower half of the menu.




The info line setup context menu

Setup Dialogs

The setup dialogs allow you to specify which elements are visible/hidden and in what order they are shown. You can save and recall setup presets.

- To open a setup dialog, right-click the element that you want to set up, and select **Setup**.



The left section of the dialog shows the visible items, the right section shows the hidden items.


- To change the current show/hide status of an item, select it in one section and use the arrow buttons in the middle of the dialog to move it to the other section.
- To reorder the items list, select an item in the list of **Visible Items** and click **Move Up** or **Move Down**.
- To name the current configuration and save it as a preset, click **Store** in the **Presets** section.
- To remove a preset, select it on the presets pop-up menu and click **Delete** in the **Presets** section.
- To revert to the standard layout, open the setup context menu and select **Reset All**.

Customizing the Meter Colors

You can customize the meter colors in Cubase. This helps you to keep an overview of what levels are being reached.

PROCEDURE

1. In the **Preferences** dialog, select **Metering > Appearance**.



2. Do one of the following:
 - Click **Channel Meter** to make settings for the channel meter.
 - Click **Master Meter** to make settings for the master meter.
3. Do one of the following:
 - Double-click a level position to the right of the meter scale and enter the level (dB) value to specify the level for a color change. To enter dB values less than zero, add a minus sign before the entered number.
 - Click a level position and drag it to a specific level, and press **Shift** for more accurate positioning.
 - Click a level position and nudge it up or down with the **Up Arrow/Down Arrow** keys, and press **Shift** for faster positioning.

NOTE

You can add level position handles by clicking the **Add** button. New handles are always added at the top of the meter. You can remove a selected level position handle by clicking the **Remove** button.

4. Click the upper or lower part of a handle so that a frame is shown, and in the color selector, select a color.
5. Click **OK**.

RELATED LINKS

[Color Selector Pane](#) on page 997

Customizing the User Interface Colors

You can change the color of the Cubase desktop, the track types, the **Project** window, the editor elements, and **MixConsole** elements.

PROCEDURE

1. In the **Preferences** dialog, select **User Interface > Color Schemes**.

2. Do one of the following:
 - Activate a default color scheme by clicking on it.
 - Click **Choose Custom Color** and the color selector pane to select a new color.
-


RESULT

The color scheme is instantly applied.

RELATED LINKS

[Color Selector Pane](#) on page 997

Color Selector Pane



Color Selectors

Allow you to select a color.

Context Menu

Allows you to copy, paste or reset colors.

Current Color/New Color

Shows the current color and the new color.

Hue/Saturation/Brightness

Allows you to edit the colors numerically.

OK

Confirms the color changes.

NOTE

You must restart the application for some changes to take effect.

Coloring Tracks, Parts, or Events Manually

You can apply colors to individual tracks and events/parts for an easier overview in the **Project** window.

PROCEDURE

1. In the **Project** window, do one of the following:
 - To change the color of an event or part, select it.
 - To change the color of a track, select the track and deselect all its events or parts.
2. On the toolbar, select the **Color** tool, click again, and select a color from the pop-up menu.



RESULT

If you apply a color to a track, the corresponding events and parts are displayed in the same color.

NOTE

If you assign a different color to individual parts or events, they no longer follow color changes of the track.

Resetting the Default Track Color

You can reset the color of a track, part, or event to the default color.


PROCEDURE

1. In the **Project** window, select the track, event or part that you want to reset to the default color.
 2. On the toolbar, select the **Color** tool, click again, and select **Default Color** from the pop-up menu.
-

Auto Track Color Mode

The **Auto Track Color Mode** offers you several options for automatically assigning colors to tracks that are added to the project.

- To change the **Auto Track Color Mode** and in the **Preferences** dialog, select **Event Display > Tracks**.



The following options are available:

Use Default Track Color

The default color (gray) is assigned.

Use Previous Track Color

Analyzes the color of the selected track and uses the same color for the new track.

Use Previous Track Color +1

Analyzes the color of the selected track and uses the color that comes next in the color palette for the new track.

Use Last Applied Color

Uses the color that is selected in the **Select Colors** pop-up menu.

Use Random Track Color


Uses the color palette as a basis to assign track colors randomly.

Colorizing Track Controls

You can apply the track color to the track controls. By default, only the left part of the track in the track list is colored.

PROCEDURE

1. In the **Preferences** dialog, select **Event Display > Tracks**.
2. Drag the **Colorize Track Controls** slider to the right.



3. On the **Project** window toolbar, select the **Color Tool** and click again to select a color.

RESULT

The track controls are colored.

Colorizing Folder Track Controls Only

You can restrict the effect of the **Colorize Track Control** function to folder tracks only. This is useful in projects with a large number of tracks and folder tracks.

PROCEDURE

1. In the **Preferences** dialog, select **Event Display > Tracks**.
2. Drag the **Colorize Track Controls** slider to the right.



3. Activate **Colorize Only Folder Track Controls**.
 4. Click **OK**.
 5. In the track list, select the folder track that you want to colorize.
 6. On the **Project** window toolbar, select the **Color Tool** and click again to select a color.
-

RESULT

Only the folder track controls are colorized.

Project Colors Dialog

The **Project Colors** dialog allows you to set up a different set of colors for the tracks, events or parts.

- To open the **Project Colors** dialog, select the **Color** tool on the **Project** window toolbar. Click again to open a pop-up menu and select **Project Colors**.



Color fields

Click a field to open a color selector pane that allows you to specify a new color.

The following options are available in the **Options** pop-up menu:

Append New Color

Adds a new color button at the bottom of the color list.

Insert New Color before Selection

Adds a new color button above the selected color button.

Remove Selected Color

Removes the selected color.

Reset Selected Color

Resets the selected color to the factory settings.

Increase/Reduce Intensity of all Colors

Increases or reduces the intensity of all colors.

Increase/Reduce Brightness of all Colors

Increases or reduces the brightness of all colors.

Save Current Set as Program Defaults

Saves the current set of colors as default.

Load Program Defaults to Current Set

Applies the default set of colors.

Reset Current Set to Factory Settings

Returns to the standard color palette.

Adding and Editing Individual Colors

You can add new colors to the color palette in the **Project Colors** dialog.

PROCEDURE

1. Select the **Color** tool on the **Project** window toolbar.
2. Click again to open a pop-up menu and select **Project Colors**
3. Click **Options** and select **Insert New Color before Selection**.
4. Click the newly created color field to open the color selector pane.
5. Select a color and click **OK**.

RESULT

The color is applied to the selected color field.

RELATED LINKS

[Color Selector Pane](#) on page 997

Profiles (Cubase Pro only)

Profiles allow you to save customized program settings and preferences. You can switch between profiles, and import and export your profiles for use on different computers.

Profiles are helpful if you work on different computers if you use different settings for different kinds of projects, or in a studio environment where several users work on the same computer. Profiles are saved as files with file name extension **.srf**.

Profiles include the following:

- Preferences
- Toolbar settings for all windows
- Global workspaces
- Track control settings
- Track control presets
- Presets for input and output busses
- Plug-in collections
- Quantize presets

- Crossfade presets
- Key commands

All changes done for these settings are saved in the active profile.

IMPORTANT

The following is not included in profiles: Settings in the **Studio Setup** dialog and in the **Audio Connections** window, presets in the **Control Room** tab of the **Audio Connections** window, track presets, plug-in presets, and project templates.

Profile Manager

The **Profile Manager** allows you to save customized program settings as profiles and to organize profiles on your computer.

- To open the **Profile Manager**, click **File > Profile Manager**.



The dialog lists all available profiles. The active profile is indicated by a checkmark.

To organize your profiles, you have the following options:

New

Adds a new profile with factory settings.

Duplicate

Duplicates the selected profile.

Rename

Allows you to rename the selected profile.

Delete

Deletes the selected profile.

Import

Opens a dialog that allows you to import a profile from a file.

Export

Opens a dialog that allows you to export the selected profile to a file.

Activate Profile

Activates the selected profile. You must restart the program for the change to take effect.

Close

Closes the dialog.

Creating Profiles

The **Profile Manager** allows you to create a new profile that is based on the factory default settings.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, click **New**.
 3. In the **Add New Profile** dialog, enter a profile name and click **OK**.
-

RESULT

The new profile is added to the list.

AFTER COMPLETING THIS TASK

Activate the new profile to apply the settings.

RELATED LINKS

[Activating Profiles](#) on page 1003

Duplicating Profiles

The **Profile Manager** allows you to create a duplicate of a profile and save it under a different name.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, select the profile that you want to duplicate.
 3. Click **Duplicate**.
 4. In the **Duplicate Profile** dialog, enter a profile name and click **OK**.
-

RESULT

The new profile is added to the list.

Activating Profiles

The **Profile Manager** allows you to switch to another profile. A profile switch requires a restart of Cubase.

PREREQUISITE

You have saved at least two profiles.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, select the profile that you want to activate.
 3. Click **Activate Profile**.
 4. Click **OK**.
 5. Restart the application.
-

RESULT

The settings of the profile are now active.

Renaming Profiles

The **Profile Manager** allows you to rename profiles.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, select the profile that you want to rename.
 3. Click **Rename**.
 4. In the **Rename Profile** dialog, enter a profile name and click **OK**.
-

Deleting Profiles

The **Profile Manager** allows you to delete profiles.

PREREQUISITE

You have saved at least two profiles.

NOTE

You cannot delete the active profile.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, select the profile that you want to delete.
Select multiple profiles to delete them at once.
 3. Click **Delete**.
 4. Click **OK**.
-

RELATED LINKS

[Activating Profiles](#) on page 1003

Exporting Profiles

The **Profile Manager** allows you to export profiles for use on another computer.

PROCEDURE

1. Select **File > Profile Manager**.
 2. In the **Profile Manager**, select the profile that you want to export.
 3. Click **Export**.
 4. In the file dialog, specify the file name and the location.
 5. Click **Save**.
-

RESULT

The exported profile is saved as .srf file at the specified location.

AFTER COMPLETING THIS TASK

Import the profile on another computer.

Importing Profiles

The **Profile Manager** allows you to import profiles.

PROCEDURE

1. Select **File > Profile Manager**.
2. In the **Profile Manager**, click **Import**.
3. In the file dialog, select the profile that you want to import.
4. Click **Open**.

RESULT

The imported profile is added to the list of available profiles.

AFTER COMPLETING THIS TASK

Activate the new profile to apply the settings.

RELATED LINKS

[Activating Profiles](#) on page 1003

Where are the Settings Stored?

There is a large number of ways in which you can customize Cubase. While some of the settings you make are stored with each project, others are stored in separate preference files.

If you need to transfer your projects to another computer in another studio, for example, you can bring all your settings along by copying the desired preference files and installing them on the other computer.

NOTE

It is a good idea to make a backup copy of your preference files once you have set things up the way you want! This way, if another Cubase user wants to use his or her personal settings when working on your computer, you can restore your own preferences afterwards.

- On Windows, preference files are stored in the following location: “\Users\\AppData\Roaming\Steinberg\\”.
On macOS, preference files are stored in the following location: “/Library/Preferences/
<program name>/” under your home directory.
On the Start menu, you will find a shortcut to this folder for easy access.
The full path is: “/Users/<user name>/Library/Preferences/<program name>/”.

NOTE

The RAMpresets.xml file, which contains various presets settings, is saved when exiting the program.

NOTE

Program functions, such as crossfade, or configurations, such as panels, not used in the project will not be stored.

Updating from a Previous Version of Cubase

When you are updating from Cubase 6 or higher, most of the customized settings of your previous installation are used for the new Cubase version.

When your previous Cubase version is older than Cubase 6, its settings are discarded, and the default settings of the new version of Cubase are used.

Disabling the Preferences

Sometimes you might experience odd program behaviour that can be due to inconsistent preferences settings. In such a case, you should save your project and relaunch Cubase. You can disable or delete the current preferences settings, and load the factory defaults instead.

PROCEDURE

1. Quit Cubase.
 2. Launch Cubase, and when the splash screen appears, hold down **Shift-Ctrl/Cmd-Alt**.
 3. Select one of the following options in the dialog that appears:
 - **Use current program preferences**
Opens the program with the current preference settings.
 - **Disable program preferences**
Disables the current preferences, and opens the program with the factory default settings instead.
 - **Delete program preferences**
Deletes the preferences and opens the program with the factory default settings instead. This process cannot be undone. Note that this affects all versions of Cubase installed on your computer.
-

RELATED LINKS

[Preferences](#) on page 1011

Optimizing

Optimizing Audio Performance

This section gives you some hints and tips on how to get the most out of your Cubase system, performance-wise.

NOTE

For details and current information on system requirements and hardware properties refer to the Steinberg web site.

Performance Aspects

Tracks and Effects

The faster your computer, the more tracks, effects, and EQ you are able to play. Exactly what constitutes a fast computer is almost a science in itself, but some hints are given below.

Short Response Times (Latency)

Another aspect of performance is response time. The term “latency” refers to the buffering, that is, the temporary storing of small chunks of audio data during various steps of the recording and playback process on a computer. The more and larger those chunks, the higher the latency.

High latency is most irritating when playing VST instruments and when monitoring through the computer, that is, when listening to a live audio source via the Cubase MixConsole and effects. However, very long latency times (several hundred milliseconds) can also affect other processes like mixing, for example, when the effect of a fader movement is heard only after a noticeable delay.

While Direct Monitoring and other techniques reduce the problems associated with very long latency times, a system that responds fast will always be more convenient to work with.

- Depending on your audio hardware, it may be possible to trim your latency times, usually by lowering the size and the number of buffers.
- For details, refer to the audio hardware documentation.

Audio Hardware and Driver

The hardware and its driver can have some effect on regular performance. A badly written driver can reduce the performance of your computer. But where the hardware driver design makes the most difference is with latency.

NOTE

We recommend that you use audio hardware for which there is a specific ASIO driver.

This is especially true when using Cubase for Windows:

- Under Windows, ASIO drivers written specifically for the hardware are more efficient than the Generic Low Latency ASIO Driver and produce shorter latency times.
- Under macOS, audio hardware with properly written macOS (Core Audio) drivers can be very efficient and produce very low latency times.

However, there are additional features only available with ASIO drivers, such as the ASIO Positioning Protocol.

Settings That Affect Performance

Audio Buffer Settings

Audio buffers affect how audio is sent to and from the audio hardware. The size of the audio buffers affects both the latency and the audio performance.

Generally, the smaller the buffer size, the lower the latency. On the other hand, working with small buffers can be demanding for the computer. If the audio buffers are too small, you may get clicks, pops or other audio playback problems.

Adjusting the Buffer Size

To lower the latency, you can reduce the buffer size.

PROCEDURE

1. Select **Studio > Studio Setup**.
 2. In the **Devices** list, select your audio hardware driver.
 3. Click **Control Panel**.
 4. Do one of the following:
 - Windows: Adjust the buffer size in the driver dialog that opens.
 - macOS: Adjust the buffer size in the **CoreAudio Device Settings** dialog.
-

Multi Processing

Multi processing distributes the processing load evenly to all available CPUs, allowing Cubase to make full use of the combined power of the multiple processors.

Multi processing is activated by default. You can find the setting in the **Studio Setup** dialog (**VST Audio System** page).

Audio Performance Window

This window shows the audio processing load and the hard disk transfer rate. This allows you to verify that you do not run into performance problems when adding effects or plug-ins, for example.

- To open the **Audio Performance** window, select **Studio > Audio Performance**.



Average load

Shows how much of the available CPU power is used for audio processing.

Real-time peak

Shows the processing load in the realtime path of the audio engine. The higher this value, the higher the risk that dropouts occur.

Overload indicator

The overload indicator to the right of the **real-time peak** indicator and the **average load** indicator displays overloads of the average or real-time indicator.

If it lights up, decrease the number of EQ modules, active effects, and audio channels that play back simultaneously. You can also activate the ASIO-Guard.

Disk

Shows the hard disk transfer load.

Disk overload indicator

The overload indicator to the right of the disk indicator lights up if the hard disk does not supply data fast enough.

If it lights up, use **Disable Track** to reduce the number of tracks playing back. If this does not help, you need a faster hard disk.

NOTE

You can show a simple view of the performance meter on the **Transport** panel and on the **Project** window toolbar. These meters only feature the average and the disk indicator.

ASIO-Guard

The ASIO-Guard allows you to shift as much processing as possible from the ASIO realtime path to the ASIO-Guard processing path. This results in a more stable system.

The ASIO-Guard allows you to preprocess all channels as well as VST instruments that do not need to be calculated in realtime. This leads to fewer dropouts, the ability to process more tracks or plug-ins, and the ability to use smaller buffer sizes.

ASIO-Guard Latency

High ASIO-Guard levels lead to an increased ASIO-Guard latency. When you adjust a volume fader, for example, you will hear the parameter changes with a slight delay. The ASIO-Guard latency, in contrast to the latency of the audio hardware, is independent from live input.

Restrictions

The ASIO-Guard cannot be used for:

- Realtime-dependent signals
- External effects and instruments

NOTE

If you select **Studio > VST Plug-in Manager** and click **Show VST Plug-in Information**, you can deactivate the ASIO-Guard option for selected plug-ins.

If you activate the monitoring for an input channel, a MIDI or a VST instrument channel, the audio channel and all dependent channels are automatically switched from ASIO-Guard to realtime processing and vice versa. This results in a gentle fade out and fade in of the audio channel.

Activating the ASIO-Guard

PROCEDURE

1. Select **Studio > Studio Setup**.
2. In the **Devices** list, select **VST Audio System**.
3. Activate the **Activate ASIO-Guard** option.

NOTE

This option is only available if you activate **Multi Processing**.

4. Select an **ASIO-Guard Level**.
The higher the level, the higher the processing stability and audio processing performance. However, higher levels also lead to an increased ASIO-Guard latency and memory usage.
-


Preferences

The **Preferences** dialog provides options and settings that control the global behavior of the program.

Preferences Dialog

The **Preferences** dialog is divided into a navigation list and a settings page. Clicking one of the entries in the navigation list opens a settings page.

- To open the **Preferences** dialog, select **File > Preferences**.



In addition to the settings, the dialog provides the following options:

Preference Presets

Allows you to select a saved preference preset.

Store

Allows you to save the current preferences as a preset.

Rename

Allows you to rename a preset.

Delete

Allows you to delete a preset.

Store marked preferences only

Allows you to select which pages are included in the preset.

Help

Opens the dialog help.

Defaults

Resets the options on the active page to their default settings.

Apply

Applies any changes that you have made without closing the dialog.

OK

Applies any changes that you have made and closes the dialog.

Cancel

Closes the dialog without saving any changes.

Saving a Preference Preset

You can save complete or partial preference settings as presets.

PROCEDURE

1. In the **Preferences** dialog make your settings.
 2. Click **Store** in the lower left section of the dialog.
 3. Enter a preset name and click **OK**.
-

RESULT


Your settings are now available on the **Preferences Presets** pop-up menu.

Saving Partial Preferences Settings

You can save partial preferences settings. This is useful when you have made settings that only relate to a certain project or situation, for example. When you apply a saved partial preference preset you only change the saved settings. All other preferences will be left unchanged.

PROCEDURE

1. In the **Preferences** dialog make your settings.
2. Activate **Store marked preferences only**.
In the preferences list a **Store** column is shown.



Preferences	Store
Appearance	
Colors	
General	
Track Type Defaults	
Project	
Editors	
Rulers	
MixConsole Faders	
MixConsole Racks	
MixConsole Channel Strip	
Editing	

3. Click in the **Store** column of the preference pages that you want to save.
 4. Click **Store** in the lower left section of the dialog.
 5. Enter a preset name and click **OK**.
-

RESULT

Your settings are now available from the **Preferences Presets** pop-up menu.

Editing

'Edit Solo'/'Record in MIDI Editors' follow focus

If this option is activated, and **Record in Editor** or **Solo Editor** is activated in a MIDI editor, these options follow the focus. That is, if the **Project** window gets the focus, **Record in Editor** and **Solo Editor** are suspended in the MIDI editor.

Default Track Time Type

This allows you to specify the default track time type for new tracks. When you change this setting, all new tracks will use the selected time type.

- **Musical**
All added tracks are set to musical time type. The respective button shows a note symbol.
- **Time Linear**
All new audio tracks use linear time base. The respective button shows a clock symbol.
- **Follow Transport Main Display**
New tracks use the primary time format setting on the transport panel. When this is set to **Bars+Beats**, tracks with musical time base will be added. When this is set to any of the other options (**Seconds**, **Timecode**, **Samples**, etc.), all new tracks will use linear time base.

Display Warning before Deleting Non-Empty Tracks

If this option is activated, a warning message is displayed if you delete tracks that are not empty.

Select Track on Background Click

This allows you to select a track by clicking in the event display background.

Auto Select Events under Cursor

If this option is activated, all events in the **Project** window or in an editor that are touched by the project cursor are automatically selected. This can be helpful when you rearrange your project, because it allows you to select whole sections (on all tracks) simply by moving the project cursor.

Cycle Follows Range Selection

If this option is activated, range selections that you make in the **Sample Editor** will be mirrored in the **Project** window as well. This lets you audition a range in the **Sample Editor** as a loop with the main transport controls, rather than with the **Audition** and **Audition Loop** controls in the **Sample Editor**.

Delete Overlaps

If this option is activated and you move, size, or nudge an event so that it partly overlaps another event, the other event is automatically resized so that the overlapped (hidden) section is removed. Hold **Shift** while moving to override this setting.

Parts Get Track Names

If this option is activated and you move an event from one track to another, the moved event will automatically be named according to its new track. Otherwise, the event will retain the name of the original track.

Lock Event Attributes

This setting determines which properties are affected when you lock an event (by selecting **Lock** from the **Edit** menu). You can select any combination of the following 3 options:

- **Position**
If this is locked, the event cannot be moved.
- **Size**
If this is locked, the event cannot be resized.
- **Other**
If this is locked, all other editing of the event is disabled. This includes adjusting the fades and event volume, processing, etc.

Quick Zoom

If this option is activated, the contents of parts and events will not be continuously redrawn when you zoom manually. Instead, the contents are redrawn once you have stopped changing the zoom – activate this if screen redraws are slow on your system.

Use Up/Down Navigation Commands for Selecting Tracks only

- If this option is deactivated and no event/part is selected in the **Project** window, the **Up Arrow/Down Arrow** keys are used to step through the tracks in the track list.
- If this option is deactivated and an event/part is selected in the **Project** window however, the **Up Arrow/Down Arrow** keys still step through the tracks in the track list. Only on the selected track, the first event/part will also be selected.
- If this option is activated, the **Up Arrow/Down Arrow** keys are only used to change the track selection – the current event/part selection in the **Project** window will not be altered.

Track Selection follows Event Selection

If this option is activated and you select an event in the **Project** window, the corresponding track is also automatically selected.

Automation Follows Events

If this option is activated, automation events will automatically follow when you move an event or part on the track.

This facilitates setting up automation that is related to a specific event or part, instead of a specific position in the project. For example, you can automate the panning of a sound effect event (having the sound pan from left to right, etc.) – if you need to move the event, the automation will automatically follow. The rules are:

- All automation events for the track between the start and end of the event or part will be moved. If there are automation events in the position to which you move the part or event, these will be overwritten.
- If you duplicate an event or part, the automation events will be duplicated as well.
- This function also affects copying and pasting.

Drag Delay

When you click and drag an event, this setting determines the delay before the event is moved. This helps you avoid accidentally moving events when you click on them in the **Project** window.

Editing - Audio

Treat Muted Audio Events like Deleted

If you have 2 overlapping audio events in your project and you mute the top one (the event you hear during playback), playback of the other (obscured) event will still only start at the end of the overlapping section.

If this is not what you want, **Treat Muted Audio Events like Deleted** allows you to immediately play the obscured event when muting the top event.

Use Mouse Wheel for Event Volume and Fades

- If this option is activated, you can use the mouse wheel to move the event volume curve up or down.
- When you hold down **Shift** while moving the mouse wheel, the fade curves will be affected. To move the end point of the fade in, position the mouse in the left half of the event. To move the start point of the fade out, position the mouse in the right half of the event.

On Import Audio Files

This setting determines what happens when importing an audio file into a project:

- **Open Options Dialog**
An Import Options dialog opens when you import, allowing you to select whether you want to copy the file to the audio folder and/or convert it to the project settings.
- **Use Settings**
Allows you to set standard actions for importing audio.

Enable Automatic Hitpoint Detection

If this option is activated, and you add an audio file to your project by recording or by importing, Cubase automatically detects its hitpoints. This allows you to navigate to hitpoints of an audio file from within the **Project** window.

Remove Regions/Hitpoints on all Offline Processes

If this option is activated, and you perform offline processing on an audio range that contains regions, these will be removed.

On Processing Shared Clips

This setting determines what happens when you apply processing to a shared clip, that is, a clip that is used by more than one event in the project:

- **Open Options Dialog**
An **Options** dialog appears, allowing you to select whether you want to create a new version of the clip or apply the processing to the existing clip.
- **Create New Version**
A new editing version of the clip is automatically created, and the processing is applied to that version (leaving the original clip unaffected).
- **Process Existing Clip**
The processing is applied to the existing clip (which means that all events playing that clip will be affected).

Time Stretch Tool Algorithm

Use this option to select a default algorithm that is applied when using the Object Selection tool in **Sizing Applies Time Stretch** mode. This mode allows you to resize parts and events in the **Project** window and apply time stretch to their contents in the process, so that the audio material is adjusted to fit the new length of the part or event. The following settings are available:

- **MPEX – Preview Quality**
Use this mode only for preview purposes.
- **MPEX – Mix Fast**
This mode is a very fast mode for preview. This works best with composite music signals (mono or stereo material).
- **MPEX – Solo Fast**
Use this mode for single instruments (monophonic material) and voice.
- **MPEX – Solo Musical**
Same as above but higher quality.
- **MPEX – Poly Fast**
Use this for processing monophonic and polyphonic material. This is the fastest setting that still provides very good results. You can use this for drum loops, mixes, or chords.
- **MPEX – Poly Musical**
Use this for processing monophonic and polyphonic material. This is the recommended MPEX default quality setting. You can use this for drum loops, mixes, or chords.
- **MPEX – Poly Complex**
This high quality setting produces high CPU load. Use this setting when processing difficult material or for stretch factors above 1.3.
- **Realtime**
This algorithm is much quicker and allows for better CPU performance than MPEX, but produces a lower sound quality.

Default Warping Algorithm

Determines which warp algorithm is used for new audio clips in the project.

Editing - Chords

'X' Chords Mute Notes on Tracks That are in Follow Chord Track Mode

This determines what happens when you play back a track that follows the chord track and the cursor reaches an undefined chord event (X chord). Activate this option to mute playback. Deactivate this option to continue playback of the last defined chord event.

Disable 'Acoustic Feedback' during Playback

If you activate this option, **Acoustic Feedback** is automatically disabled on playback. This ensures that chord events are not triggered twice.

Hide muted Notes in Editors

If you set up a MIDI track to follow the chord track by activating one of the **Follow Chord Track** options, some of the original MIDI notes may be muted. Activate this option to hide these notes in the editors.

Editing - Controls

Many Cubase parameters are shown as rotary encoders, sliders, and buttons that emulate hardware interfaces. Others are edited numerically in value fields. This page allows you to select the preferred ways of controlling encoders, sliders, and value fields.

Value Box/Time Control Mode

The menu contains the following options:

- **Text Input on Left-Click**

In this mode, clicking a value box will open it for editing by typing.

- **Increment/Decrement on Left/Right-Click**

In this mode, you can click with the left or right mouse button to decrease or increase the value. To edit values by typing in this mode, please double-click. Under macOS, right-clicking is the same as **Ctrl/Cmd**-clicking. We recommend that you use a 2-button mouse and set up the right button to generate a **Ctrl/Cmd**-click.

- **Increment/Decrement on Left-Click and Drag**

In this mode, you can click and drag up or down to adjust the value (much like dragging a vertical fader). Double-click to enter values manually.

Knob Mode

The menu contains the following options:

- **Circular**

To move an encoder, click on it and drag in a circular motion, such as turning a real encoder. When you click anywhere along the encoder's edge, the setting is immediately changed.

- **Relative Circular**

Works like the **Circular** option, but clicking does not automatically change the setting. This means you can make adjustments to the current setting by clicking anywhere on an encoder and dragging. There is no need to click on the exact current position.

- **Linear**

To move an encoder, click on it and drag up or down (or left or right) with the mouse button pressed – as if the encoder was a vertical (or horizontal) slider.

Slider Mode

The menu contains the following options:

- **Jump**

In this mode, clicking anywhere on a slider will make the slider handle instantly move to that position.

- **Touch**

In this mode, you have to click on the actual slider handle to adjust the parameter. This reduces the risk of accidentally moving sliders.

- **Ramp**

In this mode, clicking anywhere on a slider (but not on the actual handle) and keeping the mouse button pressed causes the handle to move smoothly to the new position.

- **Relative**

In this mode, clicking on a slider will not immediately change the setting. Instead you click and drag up or down – the setting will be changed according to how far you drag, not according to where you click.

Editing - MIDI

Select Controllers in Note Range: Use Extended Note Context

If this option is activated and you move notes together with their controllers, for example, in the Key Editor, the extended note context will be taken into account. This means that controllers between the last selected note and the following note (or the end of the part) will also be moved. If this option is deactivated, only the controllers between the first and the last selected note will be moved.

Legato Overlap

Determines the result of the **Legato** function on the **MIDI** menu.

- If **Legato Overlap** is set to 0 Ticks, the **Legato** function extends each selected note so that it reaches the next note exactly.
- Setting **Legato Overlap** to a positive value causes the notes to overlap by the specified number of ticks.
- Setting **Legato Overlap** to a negative value makes the Legato function leave a slight gap between the notes.

Legato Mode: Between Selected Notes Only

If this option is activated, the length of selected notes will be adjusted so that they reach the next selected note, allowing you to apply **Legato** only to your bass line, for example.

Split MIDI Events

If you split a MIDI part in the **Project** window (with the **Cut** tool or one of the split functions) so that the split position intersects one or several MIDI notes, the result depends on this setting.

- If **Split MIDI Events** is activated, the intersected notes are split. This creates new notes at the beginning of the second part.
- If **Split MIDI Events** is deactivated, the notes will remain in the first part, but stick out after the end of the part.

Split MIDI Controllers

If you split a MIDI part containing controllers, the result depends on this setting:

- If Split MIDI Controllers is activated and the part contains a controller with a value other than zero at the split position, a new controller event (of the same type and value) will be inserted at the split position (at the start of the second part).
- If Split MIDI Controllers is deactivated, no new controller events will be inserted.

NOTE

If you just split a part and play back the result, it will sound the same regardless of this setting. However, if you split a part and delete the first half or move the second half to a different position in the project, you may want to activate **Split MIDI Controllers** to make sure all controllers have the correct value at the beginning of the second part.

Editing - Project & MixConsole

Select Channel/Track on Solo

When you activate this option, a track in the track list or a channel in the **MixConsole** automatically gets selected if **Solo** is activated. Deactivating this option always keeps the current selection status, regardless of the solo setting for the tracks.

Select Channel/Track on Edit Settings

When you activate this option, a track in the track list or a channel in the **MixConsole** automatically gets selected when you click **Edit Channel Settings**. Deactivating this option always keeps the current track/channel selection.

Scroll to selected Track

If you activate this option, selecting a **MixConsole** channel automatically scrolls the track list to display the respective track.

Sync Selection in Project Window and MixConsole

If this option is activated, and you select a track in the **Project** window, the corresponding channel is automatically selected in the **MixConsole** and vice versa.

This can be a very handy feature when making detailed settings for audio and MIDI channels: open the **Channel Settings** window for a track by clicking its edit button, and position it so that it can remain open without obstructing the view. Then you can simply select the track for which you want to make settings in the **Project** window. The **Channel Settings** window will automatically change to show the settings for the selected track.

Enable Record on Selected MIDI Track

If this option is activated, the selected MIDI tracks are automatically record-enabled.

Enable Record on Selected Audio Track

If this option is activated, selected audio tracks are automatically record-enabled.

Enable Solo on Selected Track

If this option is activated, the selected tracks are automatically soloed.

Deep Track Folding

If this option is activated, any folding settings that you make on the **Track Folding** submenu of the **Project** menu also affect the subelements of the tracks. For example, if you fold in a folder track that contains 10 audio tracks, of which 5 have several open automation tracks, all these audio tracks within the folder track will also be folded in.

Enlarge Selected Track

Activate this option to enter a mode where the selected track in the **Project** window will be enlarged. You can adjust the size directly in the track list if the default enlargement factor does not suit you. When you select another track in the track list, this track is automatically enlarged, and the previously selected track is displayed in its previous size.

Editing - Tool Modifiers

On this page you can specify which modifier keys are used for additional functionality when using tools.

PROCEDURE

1. Select an option in the **Categories** list.
2. Select the action for which you want to edit the modifier key in the **Action** list.
3. On your computer keyboard, hold down the modifier keys and click **Assign**.

RESULT

The current modifier keys for the action is replaced. If this tool already has assigned modifier keys, you will be asked whether you want to replace them.

Editing - Tools

Pop-up Toolbox on Right-Click

If this option is activated, the toolbox opens on right-click in the event display and editors. You can change the number of rows in which the tools are arranged on the toolbox. Keep the right mouse button pressed until the mouse pointer changes to a double arrow and drag to the bottom or right.

- To open the context menu instead of the toolbox, press any modifier key when right-clicking.

Cross Hair Cursor

This allows you to set up a cross-hair cursor when working in the event display and editors, facilitating navigation and editing, especially when arranging in large projects. You can set up the colors for the line and the mask of the cross-hair cursor, and define its width. The cross-hair cursor works as follows:

- If the **Selection** tool (or one of its subtools) is selected, the cross-hair cursor appears when you start moving or copying a part/event or when you use the event trim handles.
- If the **Draw** tool, the **Cut** tool, or any other tool that makes use of this function is selected, the cross-hair cursor appears as soon as you move the mouse over the event display.
- The cross-hair cursor is only available for tools where such a function is of any use.

NOTE

If the **Key Editor**, **Drum Editor** or the **Audio Part Editor** is open in the lower zone of the **Project** window and **Link Project and Lower Zone Cursors** is activated, the cross-hair cursor is shown in the lower zone editor and in the **Project** window.

Warn before switching Display Domain (Timewarp Tool) (Cubase Pro only)

If this option is activated, a warning opens if you select the **Timewarp** tool and the ruler is not set to **Bars & Beats**.

Zoom Tool Standard Mode: Horizontal Zooming Only

This affects the result when using the **Zoom** tool.

If this option is activated and you drag a selection rectangle with the **Zoom** tool, the window is only zoomed horizontally and the track height does not change. If this option is deactivated, the window is zoomed both horizontally and vertically.

Select Tool: Show Extra Info

Activate this to show a tooltip for the **Object Selection** tool in the **Project** window event display. This tooltip indicates the current pointer position and the name of the track and event at which you are pointing.

Editors

Use Drum Editor when Drum Map is assigned

If this option is activated, parts on MIDI tracks to which drum maps are assigned are shown with drum note symbols. The parts will automatically open in the **Drum Editor** on double-click. This overwrites the **Default MIDI Editor** setting.

Default MIDI Editor

Determines which editor is opened when you double-click a MIDI part or when you select it and press **Ctrl/Cmd-E**. Note that this setting is overwritten for tracks with drum maps if the **Use Drum Editor when Drum Map is assigned** option is activated.

Editor Content Follows Event Selection

If this option is activated, the parts or events shown in the open editor will follow the selection that you make in the **Project** window.

Double-Click opens Editor in a Window/in Lower Zone

Determines where an editor is opened when you double-click an audio event or a MIDI part or when you use the key command assigned to **Open/Close Editor**.

Open Editor Commands open Editors in a Window/in Lower Zone

Determines where an editor is opened when you use an open command from the **Audio** or **MIDI** menu or the corresponding key commands.

Event Display

The **Event Display** section contains several settings for customizing the display in the **Project** window.

Show Event Names

Determines whether the names of parts and events are shown.

Hide Truncated Event Names

When zooming or resizing elements, the events can become very small so that the name is no longer completely visible. The name gets truncated. If this option is activated, event names are hidden if they do not fit into the event.

Show Overlaps

When events overlap, this setting allows you to specify when the overlapping areas are displayed.

Grid Overlay Intensity

Increases or decreases the overlay intensity of the displayed grid lines.

Event Handling Opacity

Increases or decreases the opacity of an overlying event background when you move it.

Smallest Track Height To Show Data

Specifies from which track height the track contents are displayed.

Smallest Track Height To Show Name

Specifies from which track height the track names are displayed.

Event Display - Audio

Interpolate Audio Waveforms

If you have zoomed in to one sample per pixel or less, the appearance of the samples depends on this setting. If this option is deactivated, single sample values are drawn as steps. If this option is activated, the sample values are interpolated to form curves.

Show Event Volume Curves Always

If this option is activated, event volume curves, as created by the fade and volume handles, are shown for all events, regardless of whether they are selected or not. If this option is deactivated, volume curves are only shown for selected events. However, note that you can still adjust fades and volumes for events that are not selected, by clicking and dragging the top left, middle, or right edge respectively.

Show Waveforms

If this option is activated, audio waveforms are displayed for audio events.

Show Hitpoints on Selected Events

If this option is activated, hitpoints are displayed for audio events.

Waveform Brightness

Increases or decreases the brightness of the displayed waveforms.

Waveform Outline Intensity

Increases or decreases the intensity of the waveform outline.

Fade Handle Brightness

Increases or decreases the brightness of the set fade lines within audio events.

Background Color Modulation

If this option is activated, the backgrounds of audio waveforms reflect the waveform dynamics. This is especially useful to get an overview when working with small track heights.

Event Display - Chords & Pitches

Pitch Notation

- The **Note Name** pop-up menu lets you select between 3 ways of displaying chords: **English**, **German**, and **Solfège**.
- The **Naming Format** pop-up menu lets you determine how MIDI note names (pitches) are displayed in editors, etc. The options are: **MIDI**, **MIDI + MIDI Note Number**, and **Classic (Helmholtz)**.
- The options **Display 'Bb' as 'B'** and **Display 'B' as 'H'** allow you to change the corresponding pitch names.
- If you activate **Enharmonics from Chord Track**, and your project contains a chord track with chord events, these chord events determine if the enharmonically equivalent notes in the **Key Editor** and in the **List Editor** are displayed as sharp or flat.

Chord Font


Allows you to specify a font for all chord symbols.

Chord Symbols

There are several ways of indicating chord types, for example, major and minor chords. These options allow you to select your preferred display method for major 7th chords, minor chords, half-diminished chords, diminished chords, and augmented chords.

Custom Chord Symbols

You can modify the default chord symbols that are used on the chord track, for the chord pads, and in the **Score Editor**.



- The **New Custom Chord** button allows you to add a new custom chord symbol.
- The options to the left allow you to specify the chord for which you want to change the chord symbol.
- Click the **Type** and **Tension** fields and enter your custom symbol.

NOTE

You must define custom symbols for each set of tensions.

- The **Result** field shows how the chord will be displayed.
- The **Remove Custom Chord** button allows you to remove the custom chord symbol that is selected in the list.

EXAMPLE

To change the appearance of all minor chords from Xmin to X-, click **New Custom Chord**, activate **5** and **min3/#9** to define the chord type and change the symbol in the Type column from min to -.

Event Display - Folders

Show Event Details

If this option is activated, event details are displayed. If this option is deactivated, data blocks are displayed.

This setting depends on the **Show Data on Folder Tracks** setting.

Show Data on Folder Tracks

Determines in which case data blocks or event details are displayed on folder tracks.

- **Always Show Data**
If this option is activated, data blocks or event details are always displayed.
- **Never Show Data**
If this option is activated, nothing is displayed.
- **Hide Data When Expanded**
If this option is activated, the display of events is hidden when you open folder tracks.

Event Display - MIDI

Part Data Mode

Determines if and how events in MIDI parts are shown: not shown, as lines, as score notes, as drum notes, or as blocks. Note that this setting is overwritten for tracks with drum maps if the **Use Drum Editor when Drum Map is assigned** option is activated.

Show Controllers

Governs whether non-note events such as controllers, etc. are shown in MIDI parts.

Note Brightness

Increases or decreases the brightness of note events.

Controller Brightness

Increases or decreases the brightness of controller events.

Event Display - Tracks

Colorize Track Controls

This slider allows you to apply the track color to the track controls. Drag the slider to the right to intensify the color.

Colorize Only Folder Track Controls

Activate this to restrict the effect of the **Colorize Track Control** function to folder tracks only. This is useful in projects with a large number of tracks and folder tracks.

Default Track Name Width

Allows you to determine the default name width for all track types.

Auto Track Color Mode

This offers you several options for automatically assigning colors to tracks that are added to the project:

- **Use Default Track Color**
New tracks get the default event color.
- **Use Previous Track Color**
New tracks get the same color as the track above them in the track list.
- **Use Previous Track Color + 1**
This is similar to the **Use Previous Track Color** option, except that the new tracks get the next color in the color palette.
- **Use Last Applied Color**
New tracks get the color that you last applied to an event/part.
- **Use Random Track Color**
Inserted tracks get random track colors.

General

The **General** page contains general settings that affect the program user interface. Set these according to your preferred work methods.

Language

Allows you to select which language is used in the program. After switching the language, you must restart the program for the change to take effect.

Auto Save

If this option is activated, Cubase automatically saves backup copies of all open projects with unsaved changes. These are named Name .bak, where name is the name of the project, and are saved in the project folder. Backup copies of unsaved projects are named #UntitledX.bak where X is an incremental number, to allow multiple backup copies in the same project folder.

Auto Save Interval

Allows you to specify how often a backup copy is created.

Maximum Backup Files

Allows you to specify how many backup files will be created with the **Auto Save** function. When the maximum number of backup files is reached, the existing files will be overwritten (starting with the oldest file).

Show Tips

If this option is activated and you position the pointer over an icon or button in Cubase, an explanatory tooltip is displayed after a second.

Use Edge Hints

If this option is activated, you can position the mouse pointer at one of the **Project** window edges to show a pane with options to open or close the sections.

Maximum Undo Steps

Allows you to specify the number of undo levels.

Run Setup on Create New Project

If this option is activated, Cubase automatically displays the **Project Setup** dialog every time you create a new project. This allows you to specify the basic project configuration.

Open Projects in Last Used View

Allows you to select whether projects are opened using their original window layout and settings, or using the view that you last used on your computer. This can either be the last used view that was saved on your computer or one of your specified global workspaces.

- **Never**
Projects are always opened using their original window layout and settings.
- **Only External Projects**
Projects that have been created on a different computer are opened using the view that you last used on your computer. Projects that have been created on this computer are opened using their original window layout and settings.
- **Always**
Projects are always opened using the view that you last used on your computer.

Use Hub

Activate this option to open the **Hub** when you start Cubase or create a new project using the **File** menu.

General - Personalization

Default Author Name

Allows you to specify an author name that is used by default for new projects. This will be included as metadata when exporting audio files with an iXML chunk.

Default Company Name

Allows you to specify a company name that is used by default for new projects. This will be included as metadata when exporting audio files with an iXML chunk.

MIDI

This page contains settings that affect MIDI recording and playback.

MIDI Thru Active

If this option is activated, all MIDI tracks that are record-enabled or have monitoring activated will “echo” incoming MIDI data, sending it back out on their respective MIDI outputs and channels. This allows you to hear the correct sound from your MIDI instrument during recording.

NOTE

If you use MIDI Thru, select **Local Off** mode on your MIDI instrument to prevent each note from sounding twice.

Reset on Stop

If this option is activated, Cubase sends out MIDI Reset messages (including noteoff and controller resets) on stop.

Never Reset Chased Controllers

If this option is activated, controllers are not reset to 0 when you stop playback or move to a new position in the project.

Length Adjustment

This allows you to enter a length adjustment value in ticks by which the notes that have the same pitch and MIDI channel are adjusted. This ensures that there is always a short time between the end of one note and the start of another. By default, there are 120 ticks per 1/16 note, but you can adjust this with the **MIDI Display Resolution** setting.

Chase Events

Event types for which an option is activated are chased when you locate to a new position and start playback. This makes your MIDI instruments sound as they should when you locate to a new position and start playback.

If **Chase not limited to Part Boundaries** is activated, MIDI controllers are also chased outside the part boundaries, and the chase is performed on the part touched by the cursor as well as on all the parts to the left of it. Deactivate this for very large projects, as it slows down processes such as positioning and soloing.

MIDI Display Resolution

This allows you to set the display resolution for viewing and editing MIDI data. This only affects how MIDI events are displayed and not how they are recorded.

Extend Playback Range of Notes that start before the Part

This allows you to extend the playback range of MIDI notes that start before the part in ticks. This is useful if MIDI events start shortly before the start of the MIDI part. If you do not extend the playback range, these events are not played. This setting is also taken into account during cycle playback.

Insert Reset Events after Record

If this option is activated, a reset event is inserted at the end of each recorded part. This resets controller data, such as **Sustain, Aftertouch, Pitchbend, Modulation, Breath Control**. This is useful if you stop recording before the note off command is sent, for example.

Audition through MIDI Inserts/Sends

If this option is activated, the layering of MIDI instruments (by MIDI sends) is also active within the MIDI editors. This way, the acoustic feedback of the editors sends the MIDI data not only to the output selected for the track, but additionally through any MIDI inserts and MIDI sends assigned to it. However, this also means that MIDI events will be sent through any MIDI plug-ins assigned to this track.

MIDI Latency Mode

Allows you to specify the latency of the MIDI playback engine.

Low lowers the latency and increases the responsiveness of the MIDI playback engine. However, this setting might also decrease your computer performance if your project contains lots of MIDI data.

Normal is the default mode and the recommended setting for most workflows.

High increases the latency and the playback buffer. Use this if you work with complex VST Instrument libraries or with projects that have a very high performance level.


MIDI Max. Feedback in ms

This allows you to set the maximum length of the notes when using **Acoustic Feedback** in MIDI editors.

MIDI - MIDI File

Export Options

These options allow you to specify what data is included in exported MIDI files.



Export Inspector Patch

If this option is activated, the MIDI patch settings in the Inspector - Bank Select and Program Select (used for selecting sounds in the connected MIDI instrument) are included as MIDI Bank Select and Program Change events in the MIDI file.

Export Inspector Volume/Pan

If this option is activated, Volume and Pan settings made in the **Inspector** are included as MIDI Volume and Pan events in the MIDI file.

Export Automation

If this option is activated, the automation data (just as it is heard during playback) is converted to MIDI controller events and included in the MIDI file. This also includes automation recorded with the **MIDI Control** plug-in.

Note that if a continuous controller (CC7, for example) has been recorded but the Read button is deactivated for the automation track (that is the automation is effectively switched off for this parameter), only the part data for this controller will be exported.

If this option is deactivated and the Read Automation button is activated, no continuous controllers will be exported. If the Read button is deactivated, the controller data of the MIDI part are exported (these will now be handled like "regular" part data).

It is recommended to activate the "Export Automation" option.

Export Inserts

If this option is activated and you are using MIDI modifiers or any MIDI plug-ins as insert effects, the modifications to the original MIDI notes that occur as a result of the effects will be included in the MIDI file. A MIDI delay, for example, will produce a number of repeats to a MIDI note by actually adding additional, "echoing" notes at rhythmic intervals - these notes will be included in the MIDI file if the option is activated.

Export Sends

If this option is activated and you are using any MIDI plug-ins as send effects, the modifications to the original MIDI notes that occur as a result of the effects will be included in the MIDI file.

Export Markers

If this option is activated, any markers you have added will be included in the MIDI file as Standard MIDI File Marker events.

Export as Type 0

If this option is activated, the MIDI file will be of Type 0 (all data on a single track, but on different MIDI channels). If you do not check this option, the MIDI file will be of Type 1 (data on separate tracks). Which type to choose depends on what you want to do with the MIDI file (in which application or sequencer it is to be used).

Export Resolution

You can specify a MIDI resolution between 24 and 960 for the MIDI file. The resolution is the number of pulses, or ticks, per quarter note (PPQ) and determines the precision with which you will be able to view and edit the MIDI data. The higher the resolution, the higher the precision. The resolution should be chosen depending on the application or sequencer with which the MIDI file will be used though, because certain applications and sequencers may not be able to handle certain resolutions.

Export Locator Range


If this option is activated, only the range between the left and right locator will be exported.

Export includes Delay

If this option is activated, any delay settings you have made in the **Inspector** will be included in the MIDI file.

Import Options for MIDI Files

The **Import Options** for MIDI files allow you to specify what data is included in imported MIDI files.



Extract First Patch

Converts the first **Program Change** and **Bank Select** events for each track to **Inspector** settings for the track.

Extract First Volume/Pan

Converts the first **MIDI Volume** and **Pan** events for each track to **Inspector** settings for the track.

Import Controller as Automation Tracks

Converts **MIDI Controller** events in the MIDI file to automation data for the MIDI tracks. If this option is deactivated, controller data for the MIDI parts will be imported.

Import to Left Locator

Aligns the imported MIDI file at the position of the left locator. If this option is deactivated, MIDI files start at the project start position. If you choose to have a new project created automatically, the MIDI file always starts at the project start position.

Import Markers

Imports Standard MIDI File Markers in the file and converts them to Cubase markers.

Import Dropped File as Single Part

Places the file on one track if you drag and drop a MIDI file into the project.

Ignore Master Track Events on Merge

Ignores tempo track data if you import a MIDI file into the current project. The imported MIDI file will play according to the current Tempo track in the project.

If this option is deactivated, the **Tempo Track Editor** will be adjusted according to the tempo information in the MIDI file.

Auto Dissolve Format 0

Automatically dissolves imported MIDI files of type 0. Each embedded MIDI channel in the file is placed on a separate track in the **Project** window.

If this option is deactivated, only one MIDI track is created. This track is set to MIDI channel **Any**, allowing all MIDI events to play back on their original channels. You can also use the **Dissolve Part** function on the **MIDI** menu to distribute the events onto different tracks (or lanes) with different MIDI channels at a later stage.

Destination

Allows you to specify what happens when you drag a MIDI file into the project:

- **MIDI Tracks** creates MIDI tracks for the imported file.
- **Instrument Tracks** creates instrument tracks for each MIDI channel in the MIDI file and lets the program automatically load appropriate presets.
- **HALion Sonic SE multi-timbral** creates several MIDI tracks, each routed to a separate instance of HALion Sonic SE in the **VST Instruments** window, and loads the appropriate presets.

Import Karaoke Lyrics as Text

Converts karaoke lyrics in the MIDI file to text that can be displayed in the **Score Editor**. If this option is deactivated, lyrics are only shown in the **List Editor**.

MIDI - MIDI Filter

This page allows you to prevent certain MIDI messages from being recorded and/or echoed by the MIDI Thru function (thruput).

The page is divided into 4 sections:

Record

Activating any of these options prevents the corresponding type of MIDI message from being recorded. It will, however, be thruput, and if already recorded, it will play back normally.

Thru

Activate any of these options to prevent the corresponding type of MIDI message from being thruput. It will, however, be recorded and played back normally.

Channels

If you activate a Channel button, no MIDI messages on that MIDI Channel will be recorded or thruput. Already recorded messages will however be played back normally.

Controller

Allows you to prevent certain MIDI controller types from being recorded or thruput. To filter out a controller type, select it from the list at the top of the section and click **Add**. It will appear in the list below.

To remove a controller type from the list (allow it to be recorded and thruput), select it in the lower list and click **Remove**.

MediaBay

Maximum Items in Results List

This allows you to specify the maximum number of files that are displayed in the **Results** list. This helps you to avoid unmanageably long lists of files in the **Results** list.

Allow Editing in Results List

Activate this to edit attributes also in the **Results** list. Otherwise, editing can only be done in the **Attribute Inspector**.

Show File Extensions in Results List

Activate this to display file name extensions in the **Results** list.

Scan Folders only when MediaBay is open

Activate this to scan Cubase for media files when the **MediaBay** window is open. Otherwise, the folders are scanned in the background even when the **MediaBay** window is closed.

NOTE

During playback or recording no folder scans are performed.

Scan unknown File Types

Activate this to open and scan any file in the search location and ignore files that cannot be recognized.

Metering

Map Input Bus Metering to Audio Track (in Direct Monitoring)

This allows you to map the input bus metering to monitor-enabled audio tracks, giving you the opportunity to watch the input levels of your audio tracks when working in the **Project** window. For this to work, activate **Direct Monitoring** in the **Studio Setup** dialog.

- If this option is activated, audio tracks show the metering signal from the input bus to which they are routed as soon as the track is monitor-enabled. Note that the tracks are mirroring the input bus signal, that is, you will see the same signal in both places. When using mapped metering, any functions, such as trimming, that you apply to the audio track are not reflected in its meters.
- If this option is not activated, metering works as usual.

Meters' Peak Hold Time

This allows you to specify for how long the peak levels are held in the meters. For this to work, deactivate **Meters - Hold Forever** in the **MixConsole**.

Meters' Fallback

This allows you to specify how quickly the meters in the **MixConsole** return to lower values after signal peaks.

Metering - Appearance

On this page you can assign colors to level meter values to quickly identify what levels are reached. You can adjust the colors for the channel meter or the master meter. For the master meter you can only make changes for the **Digital Scale** scaling mode. Changes take effect when you click **Apply** or **OK**.

To adjust the levels and colors, activate the channel meter or master meter option and proceed as follows:

- To specify the level for a color change, double-click a handle to the right of the meter scale and enter the level (dB) value. Note that for dB values less than 0, you must add a minus sign before the entered number. You can also click a handle and drag it to a specific level. Press **Shift** for more accurate positioning. Alternatively, you can nudge with the **Up Arrow/Down Arrow** keys. Press **Shift** for faster positioning.
- To assign a color, click the upper or lower part of a handle, and use the color selector pane to select a color. Selecting the same color for the upper and lower part of the handle results in a meter that changes its colors gradually, while different colors indicate level changes even more precisely.
- To add more color handles, click **Add**, or **Alt**-click at a level position to the right of the meter scale. Each new handle is automatically associated with a default color.
- To remove a handle, select the handle and click **Remove**, or **Ctrl/Cmd**-click the handle.

Record

This page contains settings related to audio and MIDI recording. Select one of the available entries.

Deactivate Punch In on Stop

If this option is activated, Punch In on the Transport panel is automatically deactivated whenever you enter Stop mode.

Stop after Automatic Punch Out

If this option is activated, playback will automatically stop after automatic Punch Out (when the Project Cursor reaches the Right Locator and Punch Out is activated on the Transport panel). If the Post-roll value on the Transport panel is set to a value other than zero, playback will continue for the set time before stopping.

Record - Audio

Audio Pre-Record Seconds

This allows you to specify for how many seconds any incoming audio you play is captured in buffer memory during playback or in stop mode.

When Recording Wave Files larger than 4GB

This allows you to specify what happens if you record Wave files that are larger than 4 GB.

- To split the Wave file, activate **Split Files**.
Use this if you work on a FAT32 file system that supports only file sizes up to 4 GB.
- To save the Wave file as RF64 file, activate **Use RF64 Format**.
RF64 files use the .wav extension. However, they can only be opened with an application that supports the RF64 standard.

Create Audio Images during Record

If this option is activated, Cubase calculates the waveform image and displays it during the actual recording process.

NOTE

This realtime calculation uses some extra processing power.

Record - Audio - Broadcast Wave

This page allows you to specify the **Description**, **Author**, and **Reference** text strings that are embedded in recorded Broadcast Wave files. The settings you make here also appear as default strings in the **Broadcast Wave Chunk** dialog when you export files to certain formats (not only Broadcast Wave files can contain embedded information, but also Wave, Wave 64, and AIFF files).

Record - MIDI

Record-Enable allows MIDI Thru

Activate this option if you do not want record-enabled MIDI or instrument tracks to echo incoming MIDI data. This prevents hearing doubled notes on record-enabled tracks to which a VST instrument is assigned.

Snap MIDI Parts to Bars

Activate this to lengthen recorded MIDI parts automatically to start and end at whole bar positions. If you are working in a Bars+Beats-based context, this can make editing (Moving, Duplicating, Repeating, etc.) easier.

MIDI Record Catch Range in ms

When you record starting at the left locator, this setting helps you make sure that the very start of the recording is included. If you raise the Record Catch Range, Cubase will catch the events played just before the recording start point, eliminating this problem.

Retrospective Record

If this option is activated, the program captures MIDI input in buffer memory, even when not recording. The contents of the buffer memory can then be retrieved and turned into a MIDI part on a record-enabled MIDI track. This therefore allows you to capture any MIDI notes you play in stop mode or during playback and later turn them into a recorded MIDI part.

Use the **Retrospective Record Buffer Size** setting to determine how much MIDI data can be captured in the buffer.

ASIO Latency Compensation Active by Default

This determines the initial state of the **ASIO Latency Compensation** button in the track list for MIDI or instrument tracks.

If you record live on a VST instrument, you usually compensate the latency of your audio card by playing too early. In consequence, the timestamps are recorded too early. By activating this option, all recorded events are moved by the current latency, and playback sounds like during the recording situation.

Replace Recording in Editors

This affects the result of recording in a MIDI editor when Replace Mode is selected (Linear Record Mode on the Transport panel):

- **None**
Nothing is replaced, even though Replace Mode is selected.
- **Controller**
Only controller data is replaced, not notes.
- **All**
Replace mode works as usual - notes and controllers are replaced when recording.

Scores (Cubase Pro only)

This page allows you to make settings for the Score Editor. Please select one of the available entries.

Scores - Colors for Additional Meanings

Here, you can specify different colors to identify non-standard elements in the score.

- Click in the **Active** column to activate this function for the respective element.
- Click in the color field to the right to specify the desired color.

Scores - Editing

Display Object Selection tool after Inserting Symbol

If this option is activated, as soon as you add a symbol, the program switches back to the Object Selection tool. If this option is deactivated, the Draw tool remains active after inserting a symbol.

Double-Click Symbol to get Draw tool

If this option is activated, you need to double-click with the Object Selection tool in a Palette to activate the Draw tool. If this option is deactivated, a single click is enough to bring out the Pencil.

Keep Crescendo Symbols "Horizontal"

If this option is activated, crescendo symbols are never "slanted".

Keep moved Notes within Key

If this option is activated, and you move notes vertically (to transpose them), you will be restricted to pitches within the current key.

Tied Notes selected as Single Units

If this option is activated, and you click on either note in a tied note pair, both notes will be selected.

Global Staff Spacings with [Alt-Gr + Ctrl] (Win)/[Option]-[Command] (Mac)

If this option is activated, pressing **AltGr + Ctrl** on Windows or **Alt-Command** on macOS and adjusting the spacing of staves applies the spacing to all staves on the current page and on all the following pages. If this option is deactivated, the spacing is only applied to the current page.

Auto Layout: Don't hide first staff

This option affects the Auto Layout functions "Hide Empty Staves" and "Optimize All". When "Don't hide first staff" is activated, staves in the very first grand staff will not be hidden, even if they are empty.

Show Braces in Edit Mode

Normally, braces are only shown in Page Mode. With this option activated they will also be visible in Edit Mode.

"Apply" closes Property Windows

Normally, when you open a Property window or any non-modal score dialog, such as Set Note Info or Score Settings, you can adjust the settings and click Apply to apply the changes without closing the window. If this option is activated, clicking Apply closes the window.

Show Position Cursor

If this option is activated the Project cursor position is shown as a vertical line in the score. You can click and drag the line to move the cursor or hold down **Ctrl/Cmd** and click anywhere in the score to move the cursor directly there.

Show pitch when inserting notes

If this option is activated the pitch of inserted notes is indicated.

Show Note Info by the Mouse

If this option is activated and you insert or drag a note in the score, a tooltip will appear below the pointer, showing the current pitch and position. If you feel screen redraws are too slow, you may want to turn this feature off.

Snap Slurs when dragging

If this option is activated, the endpoints of slurs will snap to notes when you draw or move them.

Unlock Layout when editing single parts

If there are more than one part on a track, and you open score edit for one of these parts, the other parts are displayed as "empty space" to preserve the layout. If this option is activated, this empty space is avoided, so you can print this single part without endless rests.

NOTE

Note that this option will erase the layout for the whole track! The next time you open the entire track, the previous layout will be overwritten with the layout settings you made for the single edited part.

Double-click on staff flips between full score/part

If this option is activated, double-clicking on a staff will switch between display of either the whole track or the current part.

NOTE

Note that in this case, the Score Settings dialog will only open if you select the "Settings..." option on the Scores menu.

Layout Tool Compatibility Mode

The behavior of the Layout tool was different in older versions of Cubase. Activate this option if you have an old project in which the Layout tool was used to ensure that the project is displayed as expected.

Hide Notes beyond limits

If this option is activated, any notes outside the Note Limits range set in the Score Settings dialog (Staff page - Options tab) will be hidden.

Computer Keyboard Note Entry: Legato

If this option is activated, the length of the previous note is changed on inserting notes.

Computer Keyboard Note Entry: Require ALT-Key

If this option is activated, you must hold down **Alt** to insert notes.

Computer Keyboard Note Entry: Use On-Screen Keyboard Keys

If this option is activated, you can insert notes by pressing the keys that correspond to the note on the **On-Screen Keyboard** (qwerty).

Default Number of Bars per Staff

This is used in 2 cases:

- In Edit Mode to set how many bars are shown across the page.
- In Page Mode to decide how many bars there are shown across the page in a new layout.

NOTE

When using the Auto Layout function, you will be asked for the maximum number of bars across the page, overriding this setting.

Scores - Note Layer

If you are moving and editing notes, you might accidentally move other objects nearby. To avoid this, you can assign different types of objects to different Note Layers (up to 3) and instruct Cubase to lock one or 2 of these layers, making them unmovable.

This page is where you specify to which layer each object type belongs. The actual locking of layers is done on the extended toolbar of the Score Editor.

Transport

This page contains options related to playback, recording and positioning.

Playback Toggle triggers Local Preview

If this option is activated, you can use the **Space** on your keyboard to start/stop "local" playback of the selected file in the Sample Editor or the Pool.

When the Sample Editor is not open or when there is no audio file selected in the Pool, the **Space** still toggles the "global" project playback.

If this option is deactivated, the **Space** is used to start/stop playback of the project.

Show Timecode Subframes

If this option is activated, all frame based display formats (".fps" and ".dfps") will also show subframes. There are 80 subframes per frame.

User-definable Frame Rate

This is where you set the frame rate (the number of frames per second) for the Display format "User". This frame rate will then be used in every ruler for which you select the User display format.

Return to Start Position on Stop

If this option is activated and you stop playback, the project cursor automatically returns to the position where recording or playback last started.

If this option is deactivated and you stop playback, the project cursor remains at the position where you stop playback.

If you click **Stop** again, the project cursor returns to the position where recording or playback last started.

Stop playback while winding

You can use the winding functions during playback. If this option is activated, audio playback is stopped as soon as you click **Rewind** or **Fast Forward** on the **Transport** panel.

If this option is deactivated, audio playback will continue until you release **Rewind** or **Fast Forward**.

Wind Speed Options

These options affect the fast forward/rewind speed.

- If **Adjust to Zoom** is activated, the wind speed will be adapted to the horizontal zoom factor.
If you zoom in very close for detailed editing, you probably do not want to have a high fast forward/rewind speed. Because of this, the **Speed Factor** does not have any effect in this mode. The **Fast Wind Factor** still applies though.
- If **Fixed** is activated, the wind speed will always be the same regardless of the horizontal zoom factor.
- Use the **Speed Factor** option to set the wind speed. You can set a value between 2 and 50. The higher the value, the faster the wind speed will be. If **Adjust to Zoom** is activated, this has no effect.
- Use the **Fast Wind Factor** to set the wind speed multiple for fast winding. If you press **Shift** while fast forwarding or rewinding, the wind speed will increase. The increase in speed is a multiple of the **Speed Factor**. Meaning that if you set the **Fast Wind Factor** to 2, the wind speed will be twice as fast. If you set it to 4, the wind speed will be 4 times as fast, etc. You can set a value between 2 and 50.

Cursor Width

Adjusts the width of the Project Cursor line.

Zoom while Locating in Time Scale

If this option is activated, you can zoom in or out by clicking in the Ruler and dragging down or up.

Locate When Clicked in Empty Space

If this option is activated, you can move the Project Cursor by clicking anywhere in an "empty" area of the Project window.

Transport - Scrub

Scrub Volume

This lets you set the playback volume for the Scrub function in the Project window and audio editors.

Use High Quality Scrub Mode

When you activate this option, effects are enabled for scrubbing and the resampling quality is higher. However, scrubbing will be more demanding on the processor.

Use Inserts While Scrubbing

When you activate this option, you can activate insert effects for scrubbing with the shuttle speed control. By default, insert effects are bypassed.

User Interface

This page contains options that allow you to adjust the default user interface colors.

Color Schemes

Allows you to adjust the color scheme for the application and the desktop cover.

- Click one of the colors in the **Choose Color Scheme** section to apply a pre-defined color.

- Click the field in the **Choose Custom Color** section to open the color selector pane and select a custom color.

Custom Colors

Allows you to adjust the colors for the **Project** window and the editors and their specific elements.

Track Type Default Colors

Allows you to adjust the colors for the different track types.

MixConsole Fader Colors

Allows you to adjust the colors for the level faders of the channel types in the **MixConsole**.

MixConsole Rack Colors

Allows you to adjust the colors for the racks in the **MixConsole**.

MixConsole Channel Strip Colors

Allows you to adjust the colors for the channel strips in the **MixConsole**.

RELATED LINKS

[Color Selector Pane](#) on page 997

VST

This page contains settings for the VST audio engine.

Default Stereo Panner Mode (Cubase Pro only)

This allows you to specify the default pan mode for inserted audio tracks (Stereo Balance Panner, Stereo Dual Panner or Stereo Combined Panner).

Connect Sends automatically for each newly created Channel

When this option is enabled, creating a new audio or group channel will automatically connect the send routing for existing FX channels. Note that this option is disabled by default to save memory resources.

Instruments use Automation Read All and Write All

If you deactivate this option, the Read and Write automation status in VST instrument panels are not affected by the “Activate/Deactivate Read for All Tracks” and “Activate/Deactivate Write for All Tracks” automation switches.

Mute Pre-Send when Mute

If this option is activated, sends set to “Pre-fader” mode will be muted if you mute their channels.

Default Send Level

This allows you to specify a default level for your send effects.

Group Channels: Mute Sources as well

By default, when you mute a group channel no audio will pass through the group. However, other channels that are routed directly to that group channel will remain unmuted. If any of those channels have cue sends routed to other group channels, FX channels or output busses, those will still be heard.

If **Group Channels: Mute Sources as well** is activated, muting a group channel will cause all other channels directly routed to it to be muted as well. Pressing mute again will unmute the group channel and all other channels directly routed to it. Channels that were muted prior to the group channel being muted will not

remember their mute status and will be unmuted when the group channel is unmuted.

NOTE

Group Channels: Mute Sources as well does not affect how mute automation is written. Writing mute automation on a group channel only affects the group channel and not channels routed to it. When writing the automation you will see the other channels being muted when this option is checked. However, upon playback, only the group channel will respond to the automation.

Delay Compensation Threshold (for Recording)

Cubase features full delay compensation - any delay inherent in the VST plug-ins you use will automatically be compensated for during playback. However, when you play a VST instrument in realtime or record live audio (with monitoring through Cubase activated), this delay compensation may result in added latency. To avoid this, you can click the Constrain Delay Compensation button on the toolbar or the **Transport** zone of the **Project** window. This function tries to minimize the latency effects of the delay compensation, while maintaining the sound of the mix as far as possible.

The Delay Compensation Threshold setting is a kind of "tolerance" setting for the Constrain Delay Compensation function - only plug-ins with a delay higher than this threshold setting will be affected by the Constrain Delay Compensation function. By default, this is set to 0.0 ms, which means that all plug-ins will be affected when you activate Constrain Delay Compensation. If you feel that a little latency is acceptable, you can raise this threshold value.

Do not Connect Input/Output Busses When Loading External Projects

Activate this option to load external projects without automatically connecting their input and output busses to the ASIO ports of your system. If you often work with projects created on computers that have ASIO configurations different from the configurations of your own system, this option prevents unwanted audio connections.

Activate 'Link Panners' for New Tracks (Cubase Pro only)

Activate this to activate **Link Panners** by default for new tracks so that the channel sends section always mirrors the Pan settings made in the channel fader section.

Auto Monitoring

Determines how Cubase handles monitoring (listening to the input signal during recording). The following options are available:

- **Manual**
This option allows you to turn input monitoring on or off by clicking the monitor button in the track list, Inspector, or MixConsole.
- **While Record Enabled**
With this option you will hear the audio source connected to the channel input whenever the track is record-enabled.
- **While Record Running**
This option switches to input monitoring only during recording.
- **Tapemachine Style**
This option emulates standard tapemachine behavior: input monitoring in Stop mode and during recording, but not during playback.

NOTE

The automatic monitoring options apply when you are monitoring through Cubase, or when you are using ASIO Direct Monitoring. If you are monitoring externally

(listening to the input signal from an external mixer, for example), select the “Manual” mode and keep all audio monitor buttons turned off in Cubase.

Warn on Processing Overloads

When you activate this option, a warning message is displayed as soon as the CPU overload indicator (on the Transport panel) lights up during recording.

VST - Plug-ins

Warn Before Removing Modified Effects

If this option is activated, a dialog will appear whenever you remove an effect plug-in for which you have made parameter changes, asking for confirmation as to whether you really want to remove the effect.

If you do not want this dialog to appear and modified effects to be removed without confirmation, leave this option deactivated.

Open Effect Editor after Loading it

If this option is activated, loading an effect or VST instrument in one of the plug-in slots of the Send or Insert sections, for example, will automatically open the control panel for the plug-in.

Create MIDI track when loading VSTi

This pop-up menu allows you to what specify happens when you add a VSTi in the VST Instruments window. The following options are available:

- **Always**
When this is selected, a corresponding MIDI track will always be created when you add a VST instrument.
- **Do not**
When this is selected, no MIDI track will be created when you add a VSTi in the VST Instruments window. This is the behavior from earlier versions of Cubase.
- **Always ask to**
When this is selected, you will be asked whether a corresponding MIDI track is created when you add a VSTi in the VST Instruments window.

Synchronize Plug-in Program Selection to Track Selection

If you route multiple MIDI tracks to multi-timbral instruments and activate this option, track selection and plug-in program selection are synchronized.

Suspend VST 3 plug-in processing when no audio signals are received

If this option is activated, VST plug-ins will not consume any CPU power in passages where no audio is passing through them. This can improve system performance noticeably.

NOTE

Note however that this might lead to situations where you loaded more plug-ins in Stop mode than the system will be able to play back simultaneously. As a safety measure, try playing back the part of your project which contains the largest number of audio events to make sure that your computer system can handle the current number of VST plug-ins.

Plug-in Editors “Always on Top”

If this option is activated, the control panels for effect plug-ins and VST instruments will always be shown on top of other windows.

VST - Control Room (Cubase Pro only)

This page contains settings for the Control Room.

Show Control Room Volume in Transport Panel

If this option is activated, the Transport panel will display the Control Room Volume if the Control Room is enabled. If the Control Room is disabled, the volume of the Main Mix bus will be shown on the Transport panel.

Auto Disable Talkback Mode

Allows you to specify if Talkback is disabled during recording, during playback and recording, or not at all.

NOTE

Set the Talkback DIM level to 0 dB so as not to radically change the mix level when punching in and out of record mode.

Use Phones Channel as Preview Channel

If this option is activated, the Phones channel will be used for monitoring. If this option is deactivated, the Monitor channel in the Control Room will be used.

Dim Cue during Talkback

If this option is activated, the cue mix heard in a studio will be dimmed (by the amount set in the Talkback Dim Level field in the Control Room) for as long as the Talkback channel is used. If this option is deactivated, the cue mix level remains the same during Talkback.

Exclusive Device Ports for Monitor Channels

If this option is activated, the port assignment for Monitor channels is exclusive. If your scenario does not require you to assign ports to several Monitor channels, it is recommended to activate this option. This way you can make sure that you do not accidentally assign ports to inputs/outputs and Monitor channels at the same time.

NOTE

This setting is saved with the Control Room presets.

Reference Level

The reference level is the level that is used in calibrated mixing environments, such as film dubbing stages. Use this option to specify the reference level that can be assigned to the Control Room level.

NOTE

You can also manually adjust the reference level in the Control Room settings.

Main Dim Volume

Use this to set the amount of gain reduction applied to the Control Room channel when the DIM button is activated.

VariAudio (Cubase Pro only)

Inhibit warning when changing the Sample Data

When you are modifying audio material that is used in several places in the project in the Sample Editor, a warning message is shown. This message can be deactivated: If you activate the **Please, don't ask again** checkbox, the message will not be

displayed in the future (when editing the pitch or time of audio material that is used several times in one project).

To display this message again, and thus be informed whether the audio is used in other places, deactivate this option.

Inhibit warning when applying Offline Processes

When you apply offline processes, such as Envelope or Normalize, to audio material that is used in several places in the project, a warning message is shown. This message can be deactivated: If you activate the **Please, don't ask again** checkbox, the message will not be displayed in the future.

To display this message again, and thus be informed whether the audio is used in other places, deactivate this option.

Video

Extract Audio on Import Video File

If this option is activated and you import a video file, the audio data of the video is automatically extracted and saved as a separate audio clip.

Thumbnail Memory Cache Size

The value entered here determines how much memory is available for displaying thumbnails. The image of a video is buffered in the thumbnail memory cache. Whenever you move to another image and there is no memory capacity left, the "oldest" picture in the cache is replaced by the current one. If you have long video clips and/or work with a large zoom factor, you may have to raise this value.

Index

A

- ACID® loops [475](#)
- Action Target [887](#)
 - Length [887](#)
 - Name [889](#)
 - Position [887](#)
 - Set Color [889](#)
 - Track Operation [888](#)
 - Trim [889](#)
- Activate Project [91](#)
- Activate Read/Write for all tracks [616](#)
- Activate tempo track [893](#)
- Active TrackVersion [174](#)
- Adapt to Zoom [74](#)
 - Grid type [80](#)
- ADAT Lightpipe [938](#)
- Add Track [578](#)
- Add Track dialog [151](#)
- Adding chords [821](#), [824](#)
- AES/SPDIF Digital Audio [938](#)
- AES17
 - Meters [385](#)
- AIFC files
 - Exporting [927](#)
- AIFF files
 - Exporting [928](#)
- Algorithms
 - Limitations [437](#)
 - Time-stretching [435](#)
- Aligning file and project attributes
 - Pool [544](#)
- Alignment level (Meters) [385](#)
- All MIDI Inputs [19](#)
- Allow Editing in Results List [1030](#)
- Appearance
 - Colors [1036](#)
 - Metering [1030](#)
- Apple Remote [665](#)
- Archive
 - Prepare [93](#)
- Arranger track
 - Flattening [293](#), [295](#)
 - Inspector [124](#)
 - Track controls [125](#)
- Articulations [789](#), [792](#)
 - Adding sound slots [791](#)
 - Editing on the info line [798](#)
 - Groups [792](#)
 - Inserting on the controller lane [797](#)
 - Mapping sound slots [793](#)
- Articulations (*continued*)
 - Remote settings [794](#)
 - Set Remote Keys [795](#)
- ASIO Direct Monitoring [18](#), [240](#)
- ASIO Latency Compensation Active by Default [1032](#)
- ASIO ports
 - Using for data only [951](#)
- ASIO-Guard [1009](#)
- Aspect ratio
 - Video Player window [961](#)
- Attribute Filter
 - Applying in the MediaBay [569](#)
 - Context menu search [569](#)
 - MediaBay [568](#)
- Attribute Inspector
 - Color scheme [571](#)
 - MediaBay [572](#)
- Attributes
 - About [570](#)
 - Defining [574](#)
 - Editing in the MediaBay [572](#)
 - Managing lists [574](#)
 - MediaBay [568](#)
- Audio
 - Exporting [921](#)
 - Handling [186](#)
 - Mixing down [921](#)
 - Overlapping [165](#)
 - Rendering [915](#)
 - Zooming [75](#)
- Audio Click
 - Render [232](#)
- Audio clock
 - About [938](#)
- Audio Connections [21](#)
 - About [21](#)
 - Editing [36](#)
 - Exclusive port assignment [373](#)
 - Presets [29](#)
- Audio effects
 - Surround [584](#)
 - Using VST System Link [953](#)
- Audio events
 - About [185](#)
 - Auditioning [190](#)
- Audio files
 - Previewing in MediaBay [562](#)
- Audio Functions [438](#)
 - Detect Silence [438](#)
 - Spectrum Analyzer [440](#)
 - Statistics [443](#)

-
- Audio hardware
 - Connections [11](#)
 - Externally clocked [16](#)
 - Audio Part Editor
 - Lower zone [64](#)
 - Audio parts
 - Auditioning [190](#)
 - Creating [189](#)
 - Audio performance
 - Optimizing [1007](#)
 - Audio Pre-Record Seconds [1031](#)
 - Audio processing
 - Pool [542](#)
 - Audio Processing
 - Direct Offline Processing [416](#)
 - Audio Recording [243](#)
 - Downmix [244](#)
 - Pre-Record Time [245](#)
 - Preparations [242](#)
 - RAM Requirements [243](#)
 - Record File Format [242](#)
 - Record Folder [242](#)
 - Record Modes [244](#)
 - Recovering [246](#)
 - Recovering recordings [245](#)
 - Undo [245](#)
 - With Effects [244](#)
 - Audio regions
 - About [187](#)
 - Audio tracks [98](#)
 - Inspector [98](#)
 - Track controls [103](#)
 - Audition chords [826](#)
 - Audition through MIDI Inserts/Sends [1025](#)
 - Auditioning
 - Audio events [190](#)
 - Audio parts [190](#)
 - Using key commands [538](#)
 - Auto Disable Talkback Mode [1040](#)
 - Auto fades
 - Global settings [287](#)
 - Track settings [287](#)
 - Auto layout
 - Don't hide first staff [1033](#)
 - Auto Monitoring
 - Manual [1037](#)
 - Tapemachine Style [1037](#)
 - Auto Save [92](#), [1024](#)
 - Auto Save Internal [1024](#)
 - Auto Select Events under Cursor [1013](#)
 - Auto Track Color Mode [1023](#)
 - Auto-Scroll [221](#)
 - Crossfades [284](#)
 - Suspend [221](#)
 - Automatable parameters
 - Controlling with Quick Controls [649](#)
 - Automatic Hitpoint Detection
 - Enabling [1015](#)
 - Automatic scales [827](#)
 - Automatic voicings [828](#)
 - Automatically generating new audio clips
 - Pool [545](#)
 - Automation
 - About [606](#)
 - Activating Gaps [621](#)
 - Activating Loop [621](#)
 - Activating To End [621](#)
 - Activating To Punch [621](#)
 - Activating To Start [621](#)
 - Bézier curves [610](#)
 - Continuous fill [622](#)
 - Drawing Fill manually [622](#)
 - Fill options [620](#)
 - Freeze Trim [620](#)
 - Functions pop-up menu [620](#)
 - Initial value [615](#)
 - Jump curves [606](#)
 - Merge Modes [625](#)
 - One Shot [622](#)
 - Quick scaling [612](#)
 - Ramp curves [606](#)
 - Read [606](#)
 - Show options [623](#)
 - Smooth transitions [610](#)
 - Static value line [606](#)
 - Suspend options [623](#)
 - Suspend Read [623](#)
 - Trim [619](#)
 - Virgin territory [615](#)
 - VST MultiPanner [594](#)
 - Write [606](#)
 - Automation data
 - Editing [609](#)
 - Removing [613](#)
 - Selecting [610](#)
 - Automation Event Editor
 - Compress Left [611](#)
 - Compress Right [611](#)
 - Move Vertically [611](#)
 - Scale Around Absolute Center [611](#)
 - Scale Around Relative Center [611](#)
 - Scale Vertically [611](#)
 - Stretch [611](#)
 - Tilt Left [611](#)
 - Tilt Right [611](#)
 - Automation Follows Events [1013](#)
 - Automation modes
 - About [616](#)
 - Auto-Latch [618](#)
 - Cross-over [618](#)
 - Touch [617](#)
 - Automation panel
 - About [616](#)
 - Read buttons [616](#)
 - Write buttons [616](#)
 - Automation tracks
 - About [614](#)
 - Assigning parameters [614](#)
 - Hiding [614](#)
 - Muting [615](#)
 - Removing [614](#)
 - Showing [614](#)

B

- Back up Project 93
- Background Color Modulation 1021
- Bank assignments 683
- Basic chord types
 - Applying to selected notes 725
- Beat Calculator 901, 902
- Bézier curves
 - Automation 610
- Bounce MIDI 694
- Bounce Selection 186
- Braces
 - Showing in Edit Mode 1033
- Broadcast Wave files
 - Exporting 926
- Broadcast Wave Files
 - Embedded information 1032
- Buffer
 - Settings 1008
- Bulk Dumps 782
- Busses
 - Adding 28
 - Child busses 28
- Bypass
 - VST MultiPanner 593

C

- Cadence mode
 - Chord Assistant 822
 - Complexity filters 822
- Change Release Length
 - Note Expression Event Editor 809
- Channel linking 333
- Channel names
 - Searching 325
- Channel overview
 - MixConsole 317
- Channel racks 328, 343
 - EQ 349
 - Filters 346
 - Gain 347
 - Inserts 347
 - Phase 347
 - Pre 346
 - Routing 344
 - Sends 359
 - Strips 351
- Channel rotation 807
- Channel settings 339
 - Copying 343
- Channel strip rack 351
 - Compressor 351
 - EQ position 351
 - Gate 351
 - Limiter 351
 - Presets 358
 - Saturation 351
 - Transformer 351
- Channel types
 - MixConsole 326

- Channels
 - Adding to link groups 333
 - Controlling with VCA faders 365
 - Linking 330
 - Removing from link groups 334
- Chase Events 232, 1025
- Child busses 28
 - Surround configurations 586
- Chord Assistant 822, 841
 - Assigning chords 844, 845
 - Cadence mode 822
 - Circle of Fifths 841, 842
 - Common notes mode 822
 - Complexity 822
 - Gap mode 822
 - Proximity 841
- Chord Editor 820
 - Adding chords 824
 - Assigning chords 844
 - MIDI Input 822
- Chord events 820
 - Adding 821
 - Adding chords 821
 - Assigning to MIDI effects or VSTis 830
 - Auditioning 826
 - Chord type 820
 - Converting to MIDI 830
 - Editing 821
 - Extracting from MIDI 834
 - Getting suggestions 824
 - Mapping offset 828
 - Resolving Display Conflicts 827
 - Tension 820
 - Voicings 828
- Chord Font 1022
- Chord Pad Controls 838
- Chord Pad Settings
 - Pad layout 857
 - Players 852
 - Remote Control 848
- Chord Pads 837–841
 - Adaptive voicing 855
 - Assigning chords 844–846
 - Context menu 839
 - Controls 841
 - Creating events 858
 - Functions menu 840
 - Moving and Copying 846
 - Multiple tracks 857
 - Pads remote range 849, 852
 - Pattern player 856
 - Players 855
 - Playing back 847
 - Preparations 840
 - Presets 858
 - Recording chords 847, 848
 - Remote assignment 850
 - Saving presets 858
 - Setting up 841
 - Voicings 855
 - Zone 841
- Chord symbols 1022

- Chord track [126](#)
 - About [819](#)
 - Assign Pads [846](#)
 - Controlling MIDI or audio playback [831](#)
 - Inspector [126](#)
 - Live transform [831](#)
 - Track controls [127](#)
- Chord voicing
 - Changing [724](#)
- Chords
 - Changing pitch [723](#)
 - Changing voicing [724](#)
 - Editing [724](#)
 - Inserting [725](#)
- Click Pattern [224](#)
 - Setting up [226](#)
 - Signature events [226](#)
- Click Pattern Editor [225](#)
- Click Sounds
 - Custom Sounds [230](#)
- Click Track
 - Render [232](#)
- Clip editing
 - Pool [538](#)
- Clips
 - Renaming [531](#)
- Clock sources [938](#)
- Color Selector Pane [997](#)
- Coloring
 - Note events [703](#)
 - Tracks [160](#)
- Colorize Only Folder Track Controls [1023](#)
- Colorize Track Controls [1023](#)
- Colors
 - Events [998](#)
 - Parts [998](#)
 - Preferences [1036](#)
 - Project [1000](#)
 - Track Controls [999](#)
 - Tracks [998](#)
 - User Interface [996](#)
- Colors for Additional Meanings
 - Scores [1033](#)
- Common notes mode
 - Chord Assistant [822](#)
 - Complexity filters [822](#)
- Complexity filters
 - Cadence mode [822](#)
 - Common notes mode [822](#)
- Compress Left
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Compress Right
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Compressor
 - Strip module [351](#)
- Connect Sends automatically for each newly created Channel [1037](#)
- Connecting
 - Audio [11](#)
 - MIDI [18](#)
- Constrain Delay Compensation [636](#)
- Continuous controllers
 - Controller display [729](#)
 - Controller lane [733](#)
- Continuous Fill
 - Fill options [622](#)
- Control link [330](#), [333](#)
- Control Room [372](#)
 - Adding channels [372](#)
 - Channels section [376](#)
 - Cue channels [376](#)
 - Downmix Presets section [377](#)
 - Exclusive port assignment [373](#)
 - External section [375](#)
 - Input gain [380](#)
 - Input phase [380](#)
 - Insert effects [380](#)
 - Inserts [380](#)
 - Main [374](#)
 - Main mix output [373](#)
 - Monitors section [377](#)
 - Opening [372](#)
 - Outputs [373](#)
 - Phones section [378](#)
 - Right zone [72](#)
 - Routing [373](#)
- Control Room channels [373](#), [376](#)
 - Adding [372](#)
 - Control Room [378](#)
 - Cues [374](#)
 - External inputs [374](#)
 - Monitors [373](#), [380](#)
 - Phones [373](#)
 - Talkback [374](#), [380](#)
- Control Room Volume
 - Showing in Transport Panel [1040](#)
- Controller Brightness [1023](#)
- Controller curves
 - Smart controls for scaling [735](#)
- Controller Data
 - Thinning Out [699](#)
- Controller display [728](#)
 - Adding events [730](#)
 - Continuous controllers [729](#)
 - Deleting events [737](#)
 - Drum Editor [761](#)
 - Editing events [730](#)
 - Editing events with Draw tool [732](#)
 - Editing events with Line tool [731](#)
 - Key Editor [719](#)
 - Moving events [736](#)
- Controller Event Editor
 - Compress Left [735](#)
 - Compress Right [735](#)
 - Move Vertically [735](#)
 - Scale Around Absolute Center [735](#)
 - Scale Around Relative Center [735](#)
 - Scale Vertically [735](#)
 - Stretch [735](#)

- Controller Event Editor (*continued*)
 - Tilt Left [735](#)
 - Tilt Right [735](#)
- Controller events [800](#)
- Controller lane
 - Continuous controllers [733](#)
 - Editor [736](#)
 - Inserting articulations [797](#)
 - Presets [729](#)
 - Selecting event types [728](#)
 - Setting up as preset [729](#)
- Controller settings
 - Global settings [804](#)
- Controllers
 - Selecting [737](#)
 - Showing [1023](#)
- Convert to Real Copy [199](#)
- Converting chord events to MIDI [830](#)
- Create Audio Images During Record [1031](#)
- Create Chord Symbols [834](#)
- Create MIDI track when loading VSTi [1039](#)
- Creating gaps
 - Automation [615](#)
- Cross-hair cursor [81](#), [1019](#)
- Crossfades
 - Auto Zoom [284](#)
 - Auto-Scroll [284](#)
 - Creating [283](#)
 - Editing in dialog [284](#)
 - Equal Gain [284](#)
 - Equal Power [284](#)
 - Presets [284](#)
 - Simple Crossfade Editor [284](#)
 - Symmetric Fades [284](#)
- Cue Mix
 - Setting up [382](#)
- Cue Sends [383](#)
 - Adjusting the volume [383](#)
 - Cue mix [382](#)
- Cursor
 - Setting [220](#)
- Cursor Width [1035](#)
- Custom Chord Symbols [1022](#)
- Customizing
 - Colors [997](#)
 - Info line [994](#)
 - Inspector [994](#)
 - Meter Colors [995](#)
 - Toolbars [994](#)
 - Transport panel [994](#)
 - User Interface Colors [996](#)
- Cycle Follows Range Selection [1013](#)
- Cycle markers
 - About [307](#)
 - Editing with tools [308](#)
 - Using [307](#)
 - Zooming [77](#), [308](#)
- Cycle recording [238](#)
- D**
- Data on Folder Tracks
 - Showing [1023](#)
- DC Offset
 - Removing [430](#)
- Deactivate Read/Write for all tracks [616](#)
- Deep Track Folding [1018](#)
- Default MIDI Editor [1020](#)
- Delay compensation
 - Constraining [636](#)
 - Threshold for Recording [1037](#)
- Delete Overlaps [1013](#)
- Deleting
 - Continuous Controllers [698](#)
 - Controllers [698](#)
 - Doubles [698](#)
 - MIDI controllers [698](#)
- Deleting Overlaps
 - Poly (MIDI) [697](#)
 - Poly (Mono) [697](#)
- Designating a new pool record folder
 - Pool [541](#)
- Detect Silence
 - Audio Functions [438](#)
- Device panels
 - About [687](#)
- Device ports
 - Selecting for busses [28](#)
- Dim Cue during Talkback [1040](#)
- Direct Offline Processing
 - About [416](#)
 - Applying [420](#)
 - Applying permanently [424](#)
 - Applying to multiple events [421](#)
 - Auto Apply [421](#)
 - Bypassing [424](#)
 - Deleting [422](#)
 - Envelope [425](#)
 - Extend Process Range [422](#)
 - Fade In [425](#)
 - Fade Out [425](#)
 - Gain [426](#)
 - Key Commands [433](#)
 - Modifying [422](#)
 - Normalize [427](#)
 - Phase Reverse [427](#)
 - Pitch Shift [427](#)
 - Pool [542](#)
 - Remove DC Offset [430](#)
 - Resample [430](#)
 - Reverse [431](#)
 - Silence [431](#)
 - Stereo Flip [431](#)
 - Tail [422](#)
 - Time Stretch [431](#)
 - Toolbar [419](#)
 - Using key commands [433](#)
 - Window [417](#)
 - Workflow [417](#)
- Direct Routing
 - About [360](#)
 - Automatic downmixing [361](#)
 - Setting up [360](#)
- Disable Acoustic Feedback during Playback [1016](#)
- Disable Track [164](#)

- Display format
 - Ruler [47](#)
 - Display line
 - Fader section [332](#)
 - Display Object Selection tool after Inserting Symbol [1033](#)
 - Dithering
 - Applying [407](#)
 - Effects [407](#)
 - Divider
 - Project window toolbar [43](#)
 - Double-Click on staff flips between full score/part [1033](#)
 - Double-Click Symbol to get Draw tool [1033](#)
 - Drag Delay [1013](#)
 - Draw tool
 - Drawing note events [720](#)
 - Drum Editor [750](#)
 - Controller display [761](#)
 - Info line [759](#)
 - Lower zone [64](#)
 - Note display [760](#)
 - Status line [759](#)
 - Toolbar [753](#)
 - Drum maps [767, 770](#)
 - Key Editor [726](#)
 - Selecting [763](#)
 - Setting up [768, 769](#)
 - Drum sounds [762](#)
 - Changing the Note Length [765](#)
 - Setup [762](#)
 - Visibility [763](#)
 - Drum Sounds
 - Settings [769](#)
 - Drum Visibility Agents [753, 763](#)
 - Dump request messages
 - MIDI SysEx Editor [782](#)
 - Duplicating
 - Events [198](#)
 - Tracks [164](#)
 - Dynamics
 - Editing [733](#)
- E**
- Edge Hints
 - Using [1024](#)
 - Edit History dialog [82](#)
 - Editing
 - Project window info line [48](#)
 - Editing events
 - Group editing [201](#)
 - Editor Content Follows Event Selection [1020](#)
 - Editor Inspector
 - Opening [54](#)
 - Score [55](#)
 - Switch Score Editor Inspector Content [55](#)
 - Effect parameters
 - Track Quick Controls [647](#)
 - Effect Plug-in Presets
 - Loading in MediaBay [576](#)
 - Effects
 - About [391](#)
 - Comparing settings [409](#)
 - Effects (*continued*)
 - Control panel [408](#)
 - Copying presets [412](#)
 - Direct Offline Processing [416](#)
 - Dithering [407](#)
 - Exporting system component information files [415](#)
 - External effects [408](#)
 - Extracting insert effect settings from track presets [414](#)
 - Insert effects [391, 393](#)
 - Managing system components [415](#)
 - Multi-channel configuration [398](#)
 - Pasting presets [412](#)
 - Plug-in delay compensation [393](#)
 - Pre/Post fader sends [402](#)
 - Presets [409](#)
 - Presets browser [409](#)
 - Routing [398, 402](#)
 - Saving insert presets [412](#)
 - Saving presets [411](#)
 - Selecting presets [410](#)
 - Send effects [391, 400](#)
 - Side-chain inputs [405](#)
 - System Component Information window [414](#)
 - Tempo sync [393](#)
 - VST 3 [392](#)
 - élastique algorithm
 - About [435](#)
 - Enable Record on Selected Audio Track [1018](#)
 - Enable Record on Selected MIDI Track [1018](#)
 - Enable Solo on Selected Track [1018](#)
 - Enable Track [164](#)
 - Enharmonic shift [748](#)
 - Enlarge Selected Track [162, 1018](#)
 - Envelope
 - Direct Offline Processing [425](#)
 - Realtime processing [288](#)
 - Envelope editor
 - Sampler Control [522](#)
 - EQ
 - Channel racks [349](#)
 - Presets [351](#)
 - EQ position
 - Strip module [351](#)
 - Equal Gain
 - Crossfades [284](#)
 - Equal Power
 - Crossfades [284](#)
 - Equalizer curve
 - MixConsole [317](#)
 - Event Details
 - Showing [1023](#)
 - Event display
 - About [45](#)
 - Editing events [781](#)
 - Folder tracks [167](#)
 - Modifying on folder tracks [167](#)
 - Project Browser [912](#)
 - Event Handling Opacity [1021](#)
 - Event lengths
 - Changing with Trim tool [723](#)

- Event list
 - Editing events [781](#)
 - Filtering events [781](#)
 - Event name
 - Showing [1021](#)
 - Event Volume Curves
 - Showing [1021](#)
 - Events
 - About [185](#)
 - Copying and Pasting [197](#)
 - Creating new files from events [186](#)
 - Displaying on folder tracks [167](#)
 - Duplicating [198](#)
 - Editing [190](#)
 - Envelopes [288](#)
 - Gluing [197](#)
 - Group editing [201](#)
 - Grouping [200](#)
 - Locking [202](#)
 - Move to [193](#)
 - Moving [192](#)
 - Moving via Info Line [193](#)
 - Moving with Nudge [193](#)
 - Moving with Object Selection [193](#)
 - Muting [202](#)
 - Normal resizing [194](#)
 - Pasting [197](#)
 - Removing [192](#)
 - Renaming [194](#)
 - Repeating [198](#)
 - Resizing [194](#)
 - Resizing with Object Selection [194](#), [195](#)
 - Resizing with Scrub [196](#)
 - Resizing with Trim [195](#)
 - Sizing Applies Time Stretch [195](#)
 - Sizing Moves Contents [195](#)
 - Sliding the contents [200](#)
 - Splitting [196](#)
 - Splitting repeatedly [197](#)
 - Exclusive Device Ports for Monitor Channels [1040](#)
 - Export Audio Mixdown [920](#)
 - AIFC files [927](#)
 - AIFF files [928](#)
 - Audio Engine Output section [932](#)
 - Broadcast Wave files [926](#)
 - Channel Batch Export [922](#)
 - Channel selection [922](#)
 - Channel selection section [922](#)
 - Cycle Marker Selection [923](#)
 - Defining Naming Schemes [925](#)
 - Export Cycle Marker(s) [923](#)
 - File Format section [926](#)
 - File Location section [923](#)
 - File name conflicts [925](#)
 - Flac files [931](#)
 - Import Into Project section [933](#)
 - MP3 files [928](#)
 - Naming Scheme dialog [924](#)
 - Ogg Vorbis files [931](#)
 - Post Process section [934](#)
 - Real-Time Export [932](#)
 - Surround mixes [605](#)
 - Wave 64 files [931](#)
 - Export Audio Mixdown (*continued*)
 - Wave files [926](#)
 - Windows Media Audio files [929](#)
 - Exporting
 - MIDI files [157](#)
 - OMF [964](#)
 - Profiles [1004](#)
 - Selected tracks [156](#)
 - Track archives [156](#)
 - Expression Map Setup [789](#)
 - Expression maps [788](#)
 - Creating [790](#)
 - Extracting from VST instruments [795](#)
 - Inspector [790](#)
 - List Editor [799](#)
 - Loading [796](#)
 - Project window [790](#)
 - Saving [796](#)
 - Score Editor [797](#)
 - Setup [789](#)
 - External effects
 - About [30](#), [408](#)
 - Favorites [35](#)
 - Freezing [35](#)
 - Missing plug-ins [35](#)
 - Setting up [31](#)
 - External instruments
 - About [30](#)
 - Favorites [35](#)
 - Freezing [35](#)
 - Missing plug-ins [35](#)
 - Setting up [33](#)
 - External monitoring [240](#)
 - Extract Audio on Import Video File [1041](#)
 - Extracting
 - Audio from video [259](#), [962](#)
 - MIDI Automation [699](#)
 - Extracting chord events from MIDI [834](#)
- ## F
- Fade Handle Brightness [1021](#)
 - Fade In
 - Direct Offline Processing [425](#)
 - Fade Out
 - Direct Offline Processing [425](#)
 - Fader section (MixConsole) [336](#)
 - Fades
 - Auto fades [285](#)
 - Editing in dialog [281](#)
 - Presets [281](#)
 - With Range Selection tool [280](#)
 - Favorites
 - Adding [552](#), [555](#)
 - Media rack [551](#)
 - File Browser
 - Media rack [551](#)
 - File Extensions
 - Showing in results list [1030](#)
 - Fill Loop [199](#)
 - Filter Target
 - Color Name [884](#)
 - Combining Condition Lines [885](#)

- Filter Target (*continued*)
 - Combining Filter Types [880](#)
 - Container Type [879](#), [880](#)
 - Length [883](#)
 - Media Type [878](#)
 - Name [881](#)
 - Position [881](#), [882](#)
 - Property [884](#), [885](#)
 - Filter Track Types [46](#)
 - Find Tracks [46](#)
 - Fixed lengths [696](#)
 - Fixed tempo
 - Mode [892](#)
 - Fixed Tempo
 - Mode [900](#)
 - Setting up [900](#)
 - Fixed velocity [696](#)
 - Flac files
 - Exporting [931](#)
 - FLAC files
 - Importing [256](#)
 - Flattening
 - Arranger track [293](#), [295](#)
 - Realtime Processing [481](#), [501](#)
 - Folder parts [189](#)
 - Folder tracks [134](#)
 - Displaying events [167](#)
 - Inspector [134](#)
 - Modifying event display [167](#)
 - Track controls [134](#)
 - Follow Chord Track [832](#)
 - Auto [832](#)
 - Chords [832](#)
 - Directly [833](#)
 - Scale events [833](#)
 - Single Voice [832](#)
 - Synchronizing Track Data [833](#)
 - Using [831](#)
 - Frame count [936](#)
 - Frame rates
 - Mismatch [959](#)
 - Synchronization [936](#)
 - Video [959](#)
 - Freeze
 - VST instruments [634](#)
 - Freeze MIDI Modifiers [674](#)
 - Freeze Trim
 - Automation [620](#)
 - FX chain presets [348](#)
 - FX Chain Presets
 - Loading in MediaBay [577](#)
 - FX channel tracks [128](#)
 - Adding [401](#)
 - Inspector [128](#)
 - Setting up [30](#)
 - Track controls [132](#)
 - FX Plug-in Presets
 - Loading in MediaBay [576](#)
- ## G
- Gain
 - Direct Offline Processing [426](#)
 - Gap mode
 - Chord Assistant [822](#)
 - Gaps
 - Fill options [621](#)
 - Gate
 - Strip module [351](#)
 - Generic Remote [656](#)
 - Global track controls [45](#)
 - Filter Track Types [46](#)
 - Find Tracks [46](#)
 - Global workspaces [991](#)
 - Gluing
 - Events [197](#)
 - Grid Overlay Intensity [1021](#)
 - Grid type
 - Project window [80](#)
 - Groove quantizing [270](#)
 - Group channel tracks [135](#)
 - Inspector [135](#)
 - Track controls [139](#)
 - Group channels
 - Adding insert effects [395](#)
 - Routing [346](#)
 - Setting up [30](#)
 - Group Channels - Mute Sources as well [1037](#)
 - Group editing [201](#)
 - Grouping events [200](#)
- ## H
- Hardware controls
 - Activating pick-up mode [651](#)
 - Hardware setup
 - Control panel [12](#)
 - Hermode tuning [673](#)
 - Hide muted Notes in Editors [1016](#)
 - Hide Notes beyond limits [1033](#)
 - Hide Truncated Event Names [1021](#)
 - High Quality Scrub Mode [1036](#)
 - History
 - Edit History [82](#)
 - MixConsole [322](#), [326](#)
 - Project window [40](#)
 - Hitpoints
 - About [465](#)
 - Showing [1021](#)
 - HMT Type
 - Hermode tuning [674](#)
 - Horizontal Snap
 - Note Expression Event Editor [809](#)
 - Hub [84](#)
 - Deactivating [85](#)
 - Using [1024](#)
- ## I
- I-notes (Input notes) [770](#)
 - Importing
 - Audio files [256](#)
 - Audio from video files [259](#)
 - Compressed audio files [256](#)
 - FLAC files [256](#)
 - MIDI files [157](#), [261](#)

- Importing (*continued*)
 - MP3 files [256](#)
 - MPEG files [256](#)
 - Ogg Vorbis files [256](#)
 - OMF files [964](#)
 - Profiles [1005](#)
 - REX files [260](#)
 - Track archives [156](#)
 - Tracks from a project [153](#)
 - Tracks from a track archive [155](#)
 - Tracks from projects [154](#)
 - Video files [958](#)
 - WMA files [256](#)
 - In-Place Editor
 - Editing controllers [785](#)
 - Editing MIDI notes [785](#)
 - Toolbar [785](#)
 - Independent track loop
 - Audio Part Editor [511](#)
 - Independent Track Loop
 - MIDI [708](#)
 - Indicate Transpositions
 - Key Editor [304](#)
 - Info line
 - Editing articulations [798](#)
 - Project window [48](#)
 - Score Editor [742](#)
 - Transpose [305](#)
 - Inhibit warning when applying Offline Processes [1040](#)
 - Inhibit warning when changing the Sample Data [1040](#)
 - Initial value
 - Automation [615](#)
 - Input busses
 - Adding [28](#)
 - Renaming [27](#)
 - Routing [345](#)
 - Surround configurations [588](#)
 - Input gain
 - MixConsole [347](#)
 - Input levels [12](#)
 - Input ports [17](#)
 - Inputs
 - Meter position options [341](#)
 - Insert effects [391](#)
 - About [393](#)
 - Adding to busses [394](#)
 - Adding to Group channels [395](#)
 - Routing [394](#)
 - Insert Reset Events after Record [1025](#)
 - Inserting and finding media
 - Pool [536](#)
 - Inserts
 - FX chain presets [348](#)
 - MIDI [675](#)
 - MixConsole [347](#)
 - Monitor channels [380](#)
 - Talkback channel [380](#)
 - Using while scrubbing [1036](#)
 - Inspector
 - About [52](#)
 - Editor Inspector [54](#)
 - Expression maps [790](#)
 - Settings Dialog [56](#)
 - Inspector (*continued*)
 - Surround Pan [592](#)
 - Synchronizing track and channel visibility [60](#)
 - Track Inspector [53](#)
 - Track Visibility [58](#)
 - Visibility [58](#)
 - VST MultiPanner [592](#)
 - Zones Visibility [60](#)
 - Inspector Sections
 - Showing/Hiding [56](#)
 - Instrument Freeze [634](#)
 - Instrument parameters
 - Track Quick Controls [648](#)
 - Instrument Presets
 - Applying [579](#)
 - Loading in MediaBay [576](#)
 - Results [579](#)
 - Instrument tracks [105](#)
 - Inspector [105](#)
 - Track controls [110](#)
 - Instruments use Automation Read All and Write All [1037](#)
 - Interpolate Audio Waveforms [1021](#)
- ## K
- Keep Crescendo Symbols Horizontal [1033](#)
 - Keep moved Notes within Key [1033](#)
 - Key commands
 - About [973](#)
 - Default [977](#)
 - Importing [976](#)
 - Loading [975](#)
 - Modifying [973](#)
 - Removing [974](#)
 - Resetting [976](#)
 - Saving [975](#)
 - Searching for [974](#)
 - Key Editor [709](#)
 - Controller display [719](#)
 - Info line [717](#)
 - Inspector [717](#)
 - Lower zone [64](#)
 - Note display [718](#)
 - Note expression data [726](#)
 - Status line [716](#)
 - Toolbar [710](#)
 - Keyboard focus
 - Activating for a zone [74](#)
 - Zones [73](#)
 - Keyboard navigation
 - MixConsole [363](#)
 - Knob Mode [1016](#)
- ## L
- Lanes [167](#)
 - Assembling a perfect take [168](#)
 - Assembling operations [169](#)
 - Audio Part Editor [510](#)
 - Language (Preferences) [1024](#)
 - Latch Buffer
 - Note expression [808](#)

- Latency
 - Optimizing [1007](#)
 - VST System Link [947](#)
 - Layout Tool Compatibility Mode [1033](#)
 - Left Locator [219](#)
 - Left zone [51](#)
 - Inspector [52](#)
 - Track Visibility [58](#)
 - Visibility [58](#)
 - Zones Visibility [60](#)
 - Legato [695](#)
 - Legato Mode - Between Selected Notes Only [1017](#)
 - Legato Overlap [1017](#)
 - Length Adjustment [1025](#)
 - Level meters (MixConsole) [342](#)
 - Limiter
 - Strip module [351](#)
 - Line tool [721](#)
 - Drawing note events [721](#)
 - Editing controller display events [731](#)
 - Linear Time Base [892](#)
 - Link groups [330](#)
 - Adding channels [333](#)
 - Assigning VCA faders [368](#)
 - Changing settings [333](#)
 - Creating [333](#)
 - Q-Link [334](#)
 - Removing channels [334](#)
 - Removing VCA faders [368](#)
 - Settings [331](#)
 - Unlink [333](#)
 - Link Project and Lower Zone Cursors [66](#)
 - List Editor [771](#)
 - Editing events [781](#)
 - Editing operations [780](#)
 - Event display [779](#)
 - Event list [778](#)
 - Filters bar [777](#)
 - Inserting events [780](#)
 - Showing/Hiding events [777](#)
 - Status line [777](#)
 - Toolbar [772](#)
 - Value display [779](#)
 - Listen
 - MixConsole [339](#)
 - Live transform
 - Chord track [831](#)
 - Loading Multi-Track Presets [183](#)
 - Locate When Clicked in Empty Space [1035](#)
 - Locators [219](#)
 - Setting [219](#)
 - Setting ranges [219](#)
 - Lock
 - Transpose track [303](#)
 - Lock Event Attributes [202](#), [1013](#)
 - Lock Punch Points to Locators [223](#)
 - Lock Record [252](#)
 - Logical Editor
 - About [860](#)
 - Actions [871](#)
 - Functions [870](#)
 - Presets [874](#)
 - Logical Filter
 - Advanced Text Search [568](#)
 - Applying [567](#)
 - MediaBay [566](#)
 - Looping
 - Audio Part Editor [511](#)
 - Fill options [621](#)
 - Loops and Samples
 - Loading in MediaBay [575](#)
 - Loudness
 - About [385](#), [386](#)
 - LU [386](#)
 - LUFS [386](#)
 - Meter [387](#)
 - Settings [389](#)
 - Statistics [443](#)
 - Units [386](#)
 - Lower zone [61](#)
 - Chord Pads [62](#)
 - Editor [64](#)
 - Link Project and Lower Zone Cursors [66](#)
 - MixConsole [63](#)
 - Sampler [64](#)
 - Selecting a MIDI editor [65](#)
 - Setting up [62](#)
- ## M
- Machine control
 - About [935](#)
 - Input source [941](#)
 - Output destinations [940](#)
 - macOS
 - Port activation [27](#)
 - Port selection [27](#)
 - Macros [974](#)
 - Main Dim Volume [1040](#)
 - Main mix
 - Output [373](#)
 - Setting up [28](#)
 - Managing media files
 - Pool [527](#)
 - Map Input Bus Metering to Audio Track [1030](#)
 - Mapping offset [828](#)
 - Marker track [312](#)
 - Inspector [141](#)
 - Track controls [141](#)
 - Marker tracks [140](#)
 - Marker window
 - About [308](#)
 - Functions [309](#)
 - Marker list [309](#)
 - Markers
 - About [307](#)
 - Attributes [310](#)
 - Cycle markers [307](#)
 - Exporting [315](#)
 - Exporting markers as track archive [316](#)
 - Exporting via MIDI [315](#)
 - IDs [311](#)
 - Importing [315](#)
 - Importing markers as track archive [316](#)
 - Importing via MIDI [315](#)

- Markers (*continued*)
 - Position markers 307
 - Settings 310
- Max. Record Time Display 252
- Maximum Backup Files 1024
- Maximum Items in Results List 1030
- Maximum Undo Steps 1024
- Media rack
 - Adding Favorites 552
 - Favorites 548, 551
 - File Browser 551
 - Instruments tile 551
 - Results 548, 549
 - Right zone 70, 71
 - Right Zone 546, 548
- MediaBay
 - About 546
 - Adding Favorites 555
 - Allow Editing in Results list 572
 - Attribute Filter 568, 569
 - Attribute Inspector 570, 572
 - Attributes 568
 - Defining user attributes 574
 - Editing attributes 572
 - Editing attributes of multiple files 573
 - Favorites 556
 - File Browser 554
 - Filters 566, 568
 - Finding file locations 558
 - Hiding sections 554
 - Instrument Presets 579
 - Key commands 583
 - Logical Filter 566–568
 - Media Type Filter 558
 - Media Types 559
 - Navigation controls 554
 - Previewer 562
 - Rating filter 560
 - Refresh Views 556
 - Related windows 578
 - Reset Filter 570
 - Results 557, 558, 561
 - Scanning 555
 - Scanning operations 554
 - Select Media Type 558
 - Settings 582
 - Show in Explorer/Reveal in Finder 558
 - Showing sections 554
 - Shuffle Results 558
 - Tagging 572
 - Text search 560, 561
 - Track Presets 579
 - Using Media Files 575
 - Volume databases 580–582
 - Window 552
 - Write-protected files 573
- MediaBay results
 - Managing media files 558
 - Resetting 561
 - Setting up 557
 - Shuffling 558
- Merge MIDI in Loop 691, 692
- Metadata
 - Author Name 1025
 - Company Name 1025
- Meter
 - Right zone 72
- Meter Colors 995
- Meter peak options 341
 - Hold forever 341
 - Hold peaks 341
- Meter position options 341
 - Input 341
 - Post-Fader 341
 - Post-Panner 341
- Meter section
 - MixConsole 385, 386
 - Project window 385
- Metering
 - About 385
- Meters
 - AES17 385
 - Alignment level 385
 - Peak meter display 385
 - RMS display 385
 - Scale standards 385
 - Settings 341
- Meters' Fallback 1030
- Meters' Peak Hold Time 1030
- Metronome 224, 228, 229, 231
 - Click Pattern Editor 225, 226
 - Setup window 227
- Metronome Click
 - Setting up 226
- Metronome Setup 227
 - Click Pattern 224
 - Click Patterns 231
 - Click Sounds 229
 - General 228
- MIDI channels
 - Send effects 676
 - Separating for drum map sounds 770
- MIDI Click
 - Render 232
- MIDI clock
 - Destinations 943
 - Synchronization 938
- MIDI Controller Automation 625
 - Setting up 626
- MIDI controller parameters
 - Note Expression 801
- MIDI devices
 - Defining new for patch selection 681, 682
 - Device Manager 680
 - Editing patches 684
 - Installing 682
 - Selecting patches 684
- MIDI Display Resolution 1025
- MIDI editors
 - Cutting and pasting 703
- MIDI effects
 - About 675
 - Inserts 675
 - Presets 678
 - Sends 676

- MIDI events
 - About [188](#)
- MIDI Export Options [1027](#)
- MIDI files [157](#), [261](#)
 - Previewing in MediaBay [562](#)
- MIDI Filter [1029](#)
- MIDI Import Options [1027](#), [1028](#)
- MIDI Input
 - Chord Editor [822](#)
- MIDI Inputs
 - Setting up [247](#)
- MIDI insert effects
 - Recording [676](#)
- MIDI interface
 - Connecting [18](#)
- MIDI Latency Mode [1025](#)
- MIDI Loops
 - Previewing in MediaBay [563](#)
- MIDI Max. Feedback in ms [1025](#)
- MIDI Merge Options [692](#)
- MIDI modifiers [670](#)
 - Hermod tuning [673](#), [674](#)
 - Random variations [672](#)
 - Range [672](#)
- MIDI note numbers [769](#)
- MIDI notes
 - Transpose (function) [690](#)
- MIDI outputs
 - Send effects [676](#)
- MIDI pan
 - MIDI track parameters [668](#)
- MIDI parts
 - Creating [189](#)
 - Handling several [707](#)
 - Independent Track Loop [708](#)
 - Processing [702](#)
- MIDI Port Setup [246](#)
- MIDI ports
 - Setting up [18](#)
- MIDI Record Catch Range in ms [1032](#)
- MIDI Record Mode [250](#)
- MIDI Recording
 - Channel and Output [247](#)
 - Continuous messages [249](#)
 - Different types of messages [249](#)
 - Instruments and channels [246](#)
 - MIDI Input setting [247](#)
 - Naming MIDI ports [246](#)
 - Notes [249](#)
 - Preparations [246](#)
 - Program Change Messages [249](#)
 - Record mode [250](#)
 - Recovering recordings [252](#)
 - Reset [250](#)
 - Retrospective Record [252](#)
 - Sound selection [247](#)
 - System Exclusive Messages [250](#)
- MIDI recordings
 - Exporting to MIDI file [771](#)
- MIDI SysEx Editor
 - Dump request messages [782](#)
- MIDI Thru Active [1025](#)
 - Monitoring [241](#)
- MIDI timecode
 - Destinations [942](#)
- MIDI track delay
 - MIDI track parameters [668](#)
- MIDI track parameters [668](#)
- MIDI tracks [112](#)
 - Expression Maps [726](#)
 - Freezing MIDI Modifiers [674](#)
 - Inspector [112](#)
 - Routing to device [783](#)
 - Track controls [117](#)
- MIDI Velocity
 - Editing [697](#)
- MIDI volume
 - MIDI track parameters [668](#)
- Mirror
 - MIDI [700](#)
- Missing ports
 - Re-routing [91](#)
- MixConsole [317](#)
 - Channel linking [330](#)
 - Channel overview [317](#)
 - Channel racks [328](#)
 - Channel selector [322](#)
 - Channel types [326](#)
 - Creating VCA faders [367](#)
 - Direct Routing [360](#)
 - Display line [332](#)
 - EQ presets [351](#)
 - Equalizer curve [317](#)
 - Fader section [336](#)
 - FX chain presets [348](#)
 - History tab [322](#)
 - Level meters [342](#)
 - Listen [339](#)
 - Lower zone [63](#)
 - Meter section [385](#), [386](#)
 - Mute [338](#)
 - Notepad [363](#)
 - Opening [317](#)
 - Panning [337](#)
 - Pre rack [346](#)
 - Racks [343](#)
 - Sections [317](#)
 - Setting volume [341](#)
 - Solo [338](#)
 - Solo Defeat [338](#)
 - Strip presets [358](#)
 - Surround Pan [592](#)
 - Undoing parameter changes [322](#), [326](#)
 - Visibility agents [328](#)
 - Visibility tab [322](#)
 - VST MultiPanner [592](#)
 - Zones tab [322](#)
 - Zoom tools [323](#)
- MixConsole in Project Window [63](#)
- MixConsole parameters
 - Track Quick Controls [648](#)
- MixConvert V6
 - Channel configurations [604](#)
 - In surround setups [601](#)
- Modifier keys [988](#)

- Monitoring [239](#)
 - About [18](#)
 - ASIO Direct Monitoring [240](#)
 - External [240](#)
 - MIDI [241](#)
 - Via Cubase [240](#)
 - Mouse Wheel for Event Volume and Fades [1015](#)
 - Move Vertically
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
 - Moving
 - Events [192](#)
 - Moving tracks [159](#)
 - MP3 files
 - Exporting [928](#)
 - Importing [256](#)
 - MPEG files
 - Importing [256](#)
 - MPEX algorithm
 - About [436](#)
 - Pitch Shift [427](#)
 - Multi processing [1008](#)
 - Musical Articulations
 - Editing [733](#)
 - Musical Mode
 - About [475](#)
 - Musical Time Base [892](#)
 - Musical track time base [170](#)
 - Mute
 - MixConsole [338](#)
 - Surround channels [600](#)
 - Transpose track [303](#)
 - Mute Pre-Send when Mute [1037](#)
 - Muting events [202](#)
- N**
- Navigating
 - MixConsole [363](#)
 - Never Reset Chased Controllers [1025](#)
 - Normalize
 - Direct Offline Processing [427](#)
 - Note Brightness [1023](#)
 - Note display
 - Drum Editor [760](#)
 - Enharmonic Shift [748](#)
 - Key Editor [718](#)
 - Note events
 - Adding in controller display [730](#)
 - Coloring [703](#)
 - Creating in Score Editor [747](#)
 - Cutting [706](#)
 - Deleting [706](#)
 - Drawing with Draw tool [720](#)
 - Drawing with Line tool [721](#)
 - Duplicating [706](#), [748](#)
 - Editing [706](#)
 - Editing via MIDI [726](#)
 - Excluding from playback [705](#)
 - Gluing [723](#), [748](#)
 - Moving [721](#), [766](#)
 - Muting [705](#)
 - Note events (*continued*)
 - Repeating [706](#)
 - Resizing [722](#)
 - Selecting [704](#)
 - Setting values [747](#)
 - Setting velocity values [707](#)
 - Setting with Snap [707](#)
 - Splitting [723](#), [748](#)
 - Transposing [721](#), [766](#)
 - Note Expression [800](#)
 - Adding events [811](#)
 - Adding release phases [814](#)
 - Channel rotation [807](#)
 - Controller parameter filter [802](#)
 - Controller parameter list [802](#)
 - Controller parameter mapping [805](#)
 - Controller settings [803](#)
 - Converting events [817](#)
 - Deleting events [812](#)
 - Global settings [804](#)
 - Inspector section [801](#)
 - Key Editor [726](#)
 - Latch Buffer [808](#)
 - Mapping controller parameters [805](#), [806](#)
 - Mapping presets [806](#)
 - MIDI controller parameters [801](#)
 - MIDI learn [806](#)
 - Moving events [813](#)
 - Overdubbing [808](#)
 - Overlaps [817](#)
 - Pasting events [812](#)
 - Pasting events to different parameters [813](#)
 - Recording [806](#), [807](#)
 - Recording by overdubbing [808](#)
 - Recording via MIDI Input [809](#)
 - Removing events [815](#)
 - Repeating events [813](#)
 - Sustain pedal [807](#)
 - Tools [804](#)
 - Trimming events [816](#)
 - Trimming to note length [814](#)
 - VST 3 controllers [800](#), [801](#)
 - Note Expression Event Editor
 - Change Editor Size [809](#)
 - Change Release Length [809](#)
 - Compress Left [809](#)
 - Compress Right [809](#)
 - Horizontal Snap [809](#)
 - Move Vertically [809](#)
 - One-Shot Mode [809](#)
 - Parameter Range [809](#)
 - Parameter Selection [809](#)
 - Scale Around Absolute Center [809](#)
 - Scale Around Relative Center [809](#)
 - Scale Vertically [809](#)
 - Stretch [809](#)
 - Tilt Left [809](#)
 - Tilt Right [809](#)
 - Vertical Snap [809](#)
 - Note Expression MIDI Input [804](#)
 - Note Expression MIDI Setup [815](#)
 - Note Info
 - Showing [1033](#)

- Note Layer
 - Scores [1035](#)
 - Note lengths
 - Changing [748](#)
 - Note stems
 - Flipping the direction [748](#)
 - Note values
 - Setting [747](#)
 - Notepad
 - MixConsole [363](#)
 - Number of Bars per Staff [1033](#)
- O**
- O-notes (Output notes) [770](#)
 - Offline Processing
 - Applying permanently [424](#)
 - Ogg Vorbis files
 - Exporting [931](#)
 - Importing [256](#)
 - OMF files [964](#)
 - On Import Audio Files [1015](#)
 - On Processing Shared Clips [1015](#)
 - On-Screen Keyboard
 - About [234](#)
 - Computer keyboard [235](#)
 - Modulation [235](#)
 - Note velocity level [235](#)
 - Octave offset [235](#)
 - Options [235](#)
 - Piano keyboard [235](#)
 - Pitchbend [235](#)
 - Recording MIDI [234](#)
 - One Shot
 - Fill options [622](#)
 - One-Shot Mode
 - Note Expression Event Editor [809](#)
 - Open Effect Editor after Loading it [1039](#)
 - Open External Projects in Last Used View [1024](#)
 - Organizing files in subfolders
 - Pool [541](#)
 - Output busses
 - Adding [28](#)
 - Default [28](#)
 - Renaming [27](#)
 - Routing [346](#)
 - Surround configurations [586](#)
 - Output Mapping [793](#)
 - Output ports [17](#)
 - Overlapping Audio [165](#)
 - Overlaps
 - Showing [1021](#)
 - Overview line
 - Project window [49](#)
 - Overview Mode
 - VST MultiPanner [597](#)
- P**
- Panning
 - Bypass [338](#)
 - Constant power [589](#)
 - MixConsole [337](#)
 - Panning (*continued*)
 - MixConvert V6 [601](#)
 - Surround [589](#)
 - Using a joystick [601](#), [665](#)
 - VST MultiPanner [589](#)
 - Parameter Range
 - Note Expression Event Editor [809](#)
 - Parameter Selection
 - Note Expression Event Editor [809](#)
 - Part Data Mode [1023](#)
 - Parts
 - About [185](#), [188](#)
 - Editing [190](#)
 - Folder [189](#)
 - Sliding the contents [200](#)
 - Parts Get Track Names [1013](#)
 - Paste at Origin [197](#)
 - Paste Relative to Cursor [197](#)
 - Patch Banks [683](#)
 - Pattern
 - Chord Pads [852](#)
 - Pattern Banks
 - Loading in MediaBay [578](#)
 - Previewing in MediaBay [565](#)
 - Peak meter display [385](#)
 - Pedals
 - To note length [696](#)
 - Performance
 - Aspects [1007](#)
 - Audio performance [1008](#)
 - Optimizing [1007](#)
 - Phase
 - MixConsole [347](#)
 - Phase Reverse
 - Direct Offline Processing [427](#)
 - Phones channel
 - Source buttons [378](#)
 - Phones Channel
 - Using as Preview Channel [1040](#)
 - Piano voicings [828](#)
 - Pick-up Mode [651](#)
 - Pitch
 - Changing for chords [723](#)
 - Pitch Notation [1022](#)
 - Pitch Shift
 - Algorithm [435](#)
 - Direct Offline Processing [427](#)
 - Limitations [437](#)
 - Plain Chords
 - Chord Pads [852](#)
 - Playback
 - Disable Acoustic Feedback [1016](#)
 - Excluding note events [705](#)
 - Playback Toggle triggers Local Preview [433](#), [1035](#)
 - Plug-in delay compensation [393](#)
 - Plug-in Editors Always on Top [1039](#)
 - Plug-in processing
 - Suspending [392](#)
 - Plug-ins
 - Installing [641](#)
 - Managing [641](#)
 - Surround [584](#)
 - Poly Pressure events [734](#)

- Polyphony
 - Restricting 699
- Pool
 - Aligning file and project attributes 544
 - Applying different processing methods 532
 - Audio processing 542
 - Automatically generating new audio clips 545
 - Clip editing 538
 - Designating a new pool record folder 541
 - Inserting and finding media 536
 - Key commands 538
 - Managing large sound databases 536
 - Managing media files 527
 - Organizing files in subfolders 541
 - Reducing the project size 542
 - Reference file 527
 - Renaming clips and regions 531
 - Resolve missing files dialog 537
 - Sampler track 527
 - Toolbar 530
 - Transferring media from a library to a project 543
- Pop-up Toolbox on Right-Click 1019
- Position Cursor
 - Showing 1033
- Position markers
 - About 307
- Post fader sends 402
- Post-roll
 - Recording 238
 - Transport panel 222
- Pre fader sends 402
- Pre-Record time
 - Audio recording 245
- Pre-roll
 - Recording 238
 - Transport panel 222
- Preferences
 - Colors 1036
 - Dialog 1011
 - Disabling 1006
 - Saving presets 1012
 - Store marked preferences only 1012
- Presets
 - Previewing in MediaBay 564, 565
 - Previewing using a MIDI file 564
 - Previewing using the Memo Recorder 565
 - Previewing via MIDI Input 564
 - Previewing via the Computer Keyboard 565
- Presets browser
 - Effects 409
- Primary Time Format
 - Selecting 221
- Process Bars 906
- Process Tempo 905
- Profiles
 - About 1001
 - Activating 1003
 - Adding 1003
 - Creating 1003
 - Deleting 1004
 - Duplicating 1003
 - Exporting 1004
 - Importing 1005
- Profiles (*continued*)
 - Managing 1002
 - Renaming 1004
 - Switching 1003
- Project Assistant 85
- Project Browser 911
 - Deleting events 914
 - Editing Note Expression data 914
 - Event display 911, 912
 - Info line 911
 - Project structure 911, 912
 - Toolbar 911
- Project Colors Dialog 1000
- Project cursor
 - Setting 220
- Project Logical Editor
 - About 876
 - Actions 886–889
 - Applying Actions 890
 - Filter conditions 877–885
 - Functions 889
 - Macros 890
 - Overview 876
 - Presets 890
 - Setting up Key Commands 891
 - Storing Presets 891
- Project Root Key
 - About 299
 - Assigning to a Project 300
 - Assigning to Parts or Events 300
 - Changing 301, 302
 - Recording with 301
- Project Setup Dialog 87
- Project structure
 - Automation 912
 - Track data 912
- Project window
 - Creating VCA faders 367
 - Event display 45
 - Global track controls 45
 - History 40
 - Info line 48
 - Inspector 52
 - Keyboard focus 73
 - Left zone 51
 - Lower zone 61–64
 - Meter section 385
 - Overview 38
 - Overview line 49
 - Project zone 39
 - Right zone 67
 - Ruler 46
 - Showing/Hiding Zones 39
 - Snap 78
 - Snap to zero crossings 78
 - Status line 48
 - Toolbar 40
 - Toolbox 43
 - Track list 44
 - Track Visibility 58
 - Transport 49, 215
 - Transport pop-up window 217
 - Visibility 58

Project window (*continued*)

- Zones Visibility [60](#)
- Zoom presets [76](#)
- Zoom submenu [75](#)
- Zooming [74](#)

Project workspaces [991](#)Project zone [39](#)

- Event display [45](#)
- Global track controls [45](#)
- Ruler [46](#)
- Toolbar [40](#)
- Track list [44](#)

Projects

- About project files [85](#)
- About template files [86](#)
- Activating [91](#)
- Back up [93](#)
- Creating new [83](#), [85](#)
- Hub [84](#)
- Location [92](#)
- Missing ports [91](#)
- Opening [90](#)
- Opening recent [91](#)
- Prepare archive [93](#)
- Project Assistant [85](#)
- Revert [92](#)
- Saving [91](#)
- Saving templates [86](#)
- Setting up [87](#)

Punch In [223](#), [238](#)

- On Stop [1031](#)

Punch In/Out

- Common Record Modes [239](#)

Punch Out [223](#), [238](#)

- Stop after automatic [1031](#)

Punch Points [223](#)**Q**Q-Link [334](#)

QC Learn Mode

- Track Quick Controls [647](#)

Quantize Panel

- About [269](#)
- Quantizing to a grid [270](#)
- Quantizing to a groove [272](#)

Quantize value [746](#)

Quantizing

- About [264](#)
- Catch Range [270](#)
- Crossfades section [276](#)
- MIDI event starts [392](#)
- Multiple audio tracks [267](#)
- Original position [272](#)
- Pre-Quantize [272](#)
- Swing [270](#)
- Tuplets [270](#)
- Using groove presets [270](#)

Quick Zoom [1013](#)**R**Rack settings [329](#)

- Copying [343](#)

Racks

- MixConsole [343](#)

RAM

- Recording [243](#)

Range Editing [204](#)Range Selection tool [204](#)

- Creating fades [280](#)

Re-Record

- Activating [239](#)
- Common Record Modes [239](#)

Read automation [606](#)Real-Time Export [932](#)Recent projects [91](#)

Record File Format

- Audio [242](#)

Record Folder

- Audio [242](#)

Record-Enable allows MIDI Thru [1032](#)

Recording

- About [236](#)
- Activating [237](#)
- Common Record Modes [239](#)
- Cycle [238](#)
- Levels [12](#)
- Lock Record [252](#)
- Notes and Note Expression [807](#)
- Pre-roll and post-roll [238](#)
- Remaining Record Time [252](#)
- Stopping [237](#)
- With Effects [244](#)

Recovering recordings

- Audio [245](#)
- MIDI [252](#)

ReCycle files [260](#)

Reducing the project size

- Pool [542](#)

Reference file

- Pool [527](#)

Reference Level [1040](#)

Refresh Views

- MediaBay [556](#)

Regions

- About [187](#)
- Creating with Detect Silence [440](#)
- Event or Range as Region [187](#)
- Events from Regions [187](#)
- Renaming [531](#)

Remote control

- About [652](#)
- Apple Remote [665](#)
- Assigning commands [655](#)
- Automation [655](#)
- Connections [652](#)
- Control Assignment [658](#)
- Generic Remote [656](#)
- Global Options [654](#)
- Joysticks [665](#)
- MIDI Port Setup [652](#)
- MIDI remote control configuration [657](#)

- Remote control (*continued*)
 - Remote Control Editor 661
 - Resetting 654
 - Setting up 653
 - Remote Control Editor 661
 - Control settings 662
 - Layout 664
 - Parameter assignment 664
 - Toolbar 662
 - Remote Controllers
 - Connecting Track Quick Controls 651
 - Connecting VST Quick Controls 638
 - Remove DC Offset
 - Direct Offline Processing 430
 - Remove Empty Tracks 159
 - Remove Regions/Hitpoints on all Offline Processes 1015
 - Remove Selected Tracks 159
 - Removing
 - Events 192
 - Silence 440
 - Renaming
 - Clips 531
 - Events 194
 - Regions 531
 - Tracks 160
 - Render Audio Click between Locators 232
 - Render MIDI Click between Locators 232
 - Rendering Audio 915
 - Rendering Selections 917
 - Rendering Tracks 915, 917
 - Repeat Events 198
 - Repeat Loop 695
 - Replace Recording in Editors 1032
 - Resample
 - Direct Offline Processing 430
 - Reset on Stop 1025
 - Resizing events 194
 - Retrospective Record 1032
 - MIDI 252
 - Return to Start Position on Stop 1035
 - Reverse
 - Audio 431
 - Direct Offline Processing 431
 - MIDI 700
 - ReWire
 - About 968
 - Activating channels 970
 - Channels 971
 - Enabling applications 968
 - Routing MIDI 971
 - Setup 968
 - REX files 260
 - Right Locator 219
 - Right zone 67
 - Control Room 72
 - Media rack 70, 71, 546, 549
 - Meter 72, 385
 - VSTi rack 68, 69
 - RMS display
 - Meters 385
 - Root Key
 - Sampler Control 525
 - Routing
 - For surround setups 587
 - Group channels 346
 - Input busses 345
 - MixConsole 344
 - Output busses 346
 - Through insert effects 394
 - Routing Editor 398
 - Ruler
 - Display format 47
 - Project window 46
 - Timeline 702
 - Ruler track 142
 - Track controls 142
 - Run Setup on Create New Project 1024
- ## S
- Sample editing
 - Sampler Control 524
 - Sample Editor 455
 - About 445
 - Info Line 451
 - Inspector 452
 - Lower zone 64
 - Overview Line 451
 - Regions 461
 - Ruler 455
 - Showing multiple waveforms 455
 - Snap 463
 - Toolbar 447
 - Undo zoom operations 456
 - Sampler
 - Lower zone 64
 - Sampler Control 515
 - Amp section 521
 - AudioWarp section 519
 - Envelope editor 522
 - Filter section 521
 - Keyboard section 524
 - Pitch section 520
 - Playing back samples 525
 - Root Key 525
 - Sample editing 524
 - Sound parameter section 519
 - Toolbar 516
 - Transferring samples to VST instruments 526
 - Waveform display 518
 - Sampler track
 - Inspector 119
 - Loading Audio Samples 514
 - Loading MIDI Parts 514
 - Sampler Control 514
 - Track controls 123
 - Transferring Samples to Instruments 526
 - Sampler tracks 118
 - Creating 515
 - Pool 527
 - Samplerate
 - Externally clocked 16
 - Saturation
 - Strip module 351
 - Save as Template 86

- Save partial preferences settings [1012](#)
- Save Track Preset [181](#), [182](#)
- Scale Around Absolute Center
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Scale Around Relative Center
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Scale events
 - About [827](#)
 - Adding [827](#)
 - Auditioning [827](#)
 - Automatic scales [827](#)
 - Changing [827](#)
 - Follow Chord Track [833](#)
 - Showing [827](#)
- Scale standards
 - Meters [385](#)
- Scale Vertically
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Scan Folders only when MediaBay is open [1030](#)
- Scan unknown File Types [1030](#)
- Scanning
 - MediaBay [555](#)
- Score display [743](#)
- Score Editor [737](#)
 - Display [743](#)
 - Info line [742](#)
 - Lower zone [64](#)
 - Staff settings [744](#)
 - Status line [742](#)
 - Toolbar [739](#)
- Score font
 - Setting [749](#)
- Score text
 - Adding [749](#)
 - Editing [749](#)
- Scores
 - Printing [750](#)
- Scroll to selected Track [1018](#)
- Scrub Tool [191](#)
- Scrub Volume [1036](#)
- Scrubbing
 - Scrub tool [190](#)
- Secondary Time Format
 - Selecting [222](#)
- Sections
 - Chord Pads [852](#)
- Select Channel/Track on Edit Settings [1018](#)
- Select Channel/Track on Solo [1018](#)
- Select Controllers in Note Range - Use Extended Note Context [1017](#)
- Select Media Type
 - MediaBay [558](#)
- Select Tool - Show Extra Info [1019](#)
- Select Track for Auditioning [826](#)
- Select Track on Background Click [1013](#)
- Selecting
 - Tracks [163](#)
- Selection Ranges
 - Creating [204](#)
 - Editing [205](#)
 - Editing in controller lane editor [736](#)
- Selections
 - Rendering [917](#)
- Send effects [391](#)
 - About [400](#)
 - Adding FX channel tracks [401](#)
 - Setting level [404](#)
 - Setting pan [403](#)
- Send Level [1037](#)
- Sends
 - MixConsole [359](#)
- Settings
 - Factory defaults [1003](#)
- Shared Copies
 - Convert to Real Copy [199](#)
 - Creating [199](#)
- Show Note Expression Data [804](#)
- Show Scales [827](#)
- Side-chain [405](#)
 - Ducking delay [406](#)
 - Effect inputs [393](#)
 - Inserts rack [348](#)
 - Trigger signals [407](#)
- Side-chain inputs [393](#)
- Signature track [143](#)
 - Inspector [143](#)
 - Track controls [143](#)
- Silence
 - Detecting [438](#)
 - Direct Offline Processing [431](#)
 - Inserting [207](#)
 - Removing [440](#)
- Simple Crossfade Editor [284](#)
- Single Voice
 - Follow Chord Track [832](#)
- Slices
 - About [465](#)
- Slider Mode [1016](#)
- Smallest Track Height To Show Data [1021](#)
- Smallest Track Height To Show Name [1021](#)
- Snap
 - About [78](#)
 - Sample Editor [463](#)
- Snap MIDI Parts to Bars [1032](#)
- Snap point
 - Setting [78](#)
- Snap Point To Cursor [78](#)
- Snap Slurs when dragging [1033](#)
- Snap to zero crossings
 - About [78](#)
- Snap type
 - Project window [79](#)
- Solo
 - MixConsole [338](#)
 - Surround channels [600](#)
- Solo Defeat
 - MixConsole [338](#)
- Solo Record in MIDI Editors [1032](#)
- Spectrum Analyzer [442](#)
 - Audio Functions [440](#)

- Split MIDI Controllers [1017](#)
 - Split MIDI Events [1017](#)
 - Splitting
 - By ranges [207](#)
 - Events [196](#)
 - Into equal events [197](#)
 - Standard algorithm
 - About [436](#)
 - Start Recording at Cursor
 - Common Record Modes [239](#)
 - Start Recording at Left Locator
 - Common Record Modes [239](#)
 - Static value line
 - Automation [606](#)
 - Stationary Cursors [1035](#)
 - Statistics
 - Audio Functions [443](#)
 - Status line
 - Project window [48](#)
 - Score Editor [742](#)
 - Step recording [727](#)
 - Stereo Flip
 - Direct Offline Processing [431](#)
 - Stereo Panner Mode [1037](#)
 - Stop playback while winding [1035](#)
 - Stretch
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
 - Strip presets [358](#)
 - Strip Presets
 - Loading in MediaBay [577](#)
 - Surround [598](#)
 - About [584](#)
 - Applying plug-ins [584](#)
 - Automatic downmixing [361](#)
 - Automation [594](#)
 - Constant power [589](#)
 - Deliverables [584](#)
 - Disable channels [600](#)
 - Divergence [599](#)
 - Exporting to file [605](#)
 - Input bus configuration [588](#)
 - Inspector [589](#)
 - MixConsole [589](#)
 - MixConvert V6 [601](#)
 - Mute channels [600](#)
 - Output bus configuration [586](#)
 - Panning [597](#)
 - Positioning [594](#)
 - Rotating signals [597](#)
 - Routing [587](#)
 - Signal distribution [598](#), [599](#)
 - Solo channels [600](#)
 - Supported channel configurations [585](#)
 - VST MultiPanner [589](#)
 - Suspend Auto-Scroll when Editing [221](#)
 - Suspend Read
 - Suspend options [623](#)
 - Suspend VST 3 plug-in processing when no audio signals are received [1039](#)
 - Suspend Write
 - Suspend options [623](#)
 - Swing
 - Quantizing [270](#)
 - Sync Selection in Project Window and MixConsole [1018](#)
 - Synchronization
 - About [935](#)
 - Operation (Sync mode) [943](#)
 - Setting up [939](#)
 - Speed references [938](#)
 - Timecode [936](#)
 - Timecode preferences [940](#)
 - Timecode source [939](#)
 - Synchronize Plug-in Program Selection to Track Selection [1039](#)
 - Synchronizing Track Data
 - Follow Chord Track [833](#)
 - SysEx
 - Changing settings [783](#)
 - Editing values [784](#)
 - Messages [782](#)
 - System component information
 - Exporting [415](#)
 - Managing system components [415](#)
 - System Component Information [414](#)
- ## T
- Tail
 - Direct Offline Processing [422](#)
 - Tap Tempo [901](#)
 - Tapemachine Style
 - Monitoring [1037](#)
 - Template projects [86](#)
 - Templates
 - Renaming [87](#)
 - Workspaces [991](#)
 - Tempo
 - Process Bars [906](#)
 - Process Tempo [905](#)
 - Set Definition from Tempo [908](#)
 - Tempo Changes
 - Tempo Detection [898](#)
 - Tempo Detection [898](#), [903](#)
 - Corrections [899](#)
 - Panel [903](#)
 - Tempo Editor
 - Toolbar [893](#)
 - Tempo Event Editor [895](#)
 - Compress Left [895](#)
 - Compress Right [895](#)
 - Move Vertically [895](#)
 - Scale Around Absolute Center [895](#)
 - Scale Around Relative Center [895](#)
 - Scale Vertically [895](#)
 - Stretch [895](#)
 - Tilt Left [895](#)
 - Tilt Right [895](#)
 - Tempo Events
 - Editing [899](#)
 - Tempo modes
 - Fixed Tempo [892](#)
 - Tempo track [892](#)
 - Tempo related tracks [892](#)

- Tempo track [144](#), [892](#)
 - About [894](#)
 - Activate [893](#)
 - Editor [893](#)
 - Exporting [904](#)
 - Importing [904](#)
 - Inspector [144](#)
 - Mode [892](#)
 - Tempo changes [896](#)
 - Track controls [145](#)
- Terminator point
 - Automation [615](#)
- Thumbnail Memory Cache Size [1041](#)
- Thumbnails
 - About [959](#)
 - Thumbnail cache files [959](#)
- Tied Notes selected as Single Units [1033](#)
- Tilt Left
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Tilt Right
 - Automation Event Editor [611](#)
 - Controller Event Editor [735](#)
 - Tempo Event Editor [895](#)
- Time Base
 - Default track time base [171](#)
 - Linear [892](#)
 - Musical [892](#)
 - Tracks [170](#)
- Time display [221](#)
- Time Display Window [218](#)
- Time Format [221](#)
- Time linear track time base [170](#)
- Time related tracks [892](#)
- Time Signature Events
 - Adding [909](#)
 - Adding on the Signature Track [909](#)
 - Setting up [908](#)
 - Setting up Click Patterns [909](#)
- Time Stretch
 - Algorithms [435](#)
 - Direct Offline Processing [431](#)
 - Limitations [437](#)
- Time Stretch Tool Algorithm [1015](#)
- Time Warp [906](#)
- Timecode
 - Standards [936](#)
 - Synchronization [936](#)
- Timecode Subframes
 - Showing [1035](#)
- Timeline
 - Ruler [702](#)
- Tips
 - Showing [1024](#)
- To End
 - Fill options [621](#)
- To Punch
 - Fill options [621](#)
- To Start
 - Fill options [621](#)
- Toggle Time Base [892](#)
- Tool modifier keys [988](#), [1019](#)
- Toolbar
 - Pool [530](#)
 - Project Browser [911](#)
 - Project window [40](#)
 - Score Editor [739](#)
- Toolbar Divider
 - Project window [43](#)
- Toolbox
 - Project window [43](#)
- Track archives
 - Exporting [156](#)
 - Importing [155](#)
- Track Area Width [1023](#)
- Track Color
 - Automatic [998](#)
 - Resetting [998](#)
- Track Controls Settings [96](#)
- Track Folding [166](#)
- Track Height [162](#)
- Track Inspector
 - Opening [53](#)
- Track list
 - About [44](#)
 - Dividing [44](#)
- Track Name Width [1023](#)
- Track parameters
 - Track Quick Controls [646](#)
- Track Pictures [161](#)
 - Browser [161](#)
 - Showing [161](#)
- Track presets
 - Quick Control assignment [649](#)
- Track Presets
 - About [179](#)
 - Applying [182](#), [579](#)
 - Audio [179](#)
 - creating [182](#)
 - Creating [181](#)
 - Extracting Sounds [183](#)
 - Instrument [179](#)
 - Loading [182](#)
 - Loading in MediaBay [576](#)
 - Loading Inserts and EQ [183](#)
 - MIDI [180](#)
 - Multi-Track [180](#)
 - Pattern Banks [181](#)
 - Previewing in MediaBay [564](#)
 - Saving Track Quick Control Assignment Presets [184](#)
 - Track Quick Controls [184](#)
 - VST Presets [181](#)
- Track Quick Controls [666](#), [667](#)
 - About [645](#)
 - Assigning effect parameters [647](#)
 - Assigning instrument parameters [648](#)
 - Assigning MixConsole parameters [648](#)
 - Assigning parameters [646](#)
 - Automatable Parameters [649](#)
 - Connecting with Remote Controllers [651](#)
 - Inspector [646](#)
 - Loading presets [649](#)
 - Parameter assignment [646](#)
 - Presets [184](#)

- Track Quick Controls (*continued*)
 - QC Learn Mode [647](#)
 - Removing assignments [648](#)
 - Saving assignments as presets [184](#), [649](#)
 - Showing automated assignments [650](#)
 - Track Selection follows Event Selection [1013](#)
 - Track Time Base [170](#), [892](#)
 - Track Time Type [1013](#)
 - Track Visibility
 - Inspector [58](#)
 - Track Zoom [162](#)
 - Tracks
 - About [95](#)
 - Audio [98](#)
 - Chord [126](#)
 - Coloring [160](#)
 - Customizing track controls [96](#)
 - Disabling audio tracks [164](#)
 - Duplicating [164](#)
 - Folder [134](#)
 - FX channel [128](#)
 - Group Channel [135](#)
 - Importing from a project [153](#)
 - Importing from a track archive [155](#)
 - Instrument [105](#)
 - Marker [140](#)
 - MIDI [112](#)
 - Moving [159](#)
 - Removing [159](#)
 - Renaming [160](#)
 - Rendering [915](#), [917](#)
 - Ruler [142](#)
 - Sampler [118](#)
 - Selecting [163](#)
 - Signature [143](#)
 - Tempo [144](#)
 - Transpose [145](#)
 - VCA fader [146](#)
 - Video [148](#)
 - TrackVersion IDs [174](#)
 - TrackVersions
 - About [171](#)
 - Activating [174](#)
 - Copying and Pasting [176](#)
 - Creating [173](#)
 - Creating from lanes [178](#)
 - Creating lanes from TrackVersions [178](#)
 - Deleting [176](#)
 - Duplicating [175](#)
 - Names [177](#)
 - Renaming [177](#)
 - Renaming on multiple tracks [177](#)
 - Transformer
 - Strip module [351](#)
 - Transports track
 - Track controls [146](#)
 - Transport [215](#)
 - Overview [215](#)
 - Project window [49](#)
 - Sections [215](#)
 - Transport menu
 - Functions [210](#)
 - Transport panel [208](#)
 - Display format [221](#)
 - Overview [208](#)
 - Post-roll [222](#)
 - Pre-roll [222](#)
 - Sections [208](#)
 - Transport pop-up window [217](#)
 - Transpose
 - Exclude Parts or Events [306](#)
 - Global [306](#)
 - Independent [306](#)
 - Indicate Transpositions [304](#)
 - Info line [305](#)
 - Lock [303](#)
 - MIDI function [690](#)
 - Mute [303](#)
 - Project Root Key [299](#)
 - Transpose functions
 - About [299](#)
 - Transpose track [145](#)
 - About [302](#)
 - Inspector [145](#)
 - Lock [303](#)
 - Mute [303](#)
 - Recording [305](#)
 - Transposing [303](#)
 - Treat Muted Audio Events like Deleted [1015](#)
 - Trim
 - Automation [619](#)
 - Trim tool
 - Changing event lengths [723](#)
 - Tuplets
 - Quantizing [270](#)
 - Type of New Tempo Points [893](#)
- ## U
- Undoing
 - Edit History [82](#)
 - Maximum undo steps [82](#)
 - Maximum Undo Steps [1024](#)
 - MixConsole parameter changes [322](#), [326](#)
 - Offline processing [422](#), [542](#)
 - Project window [40](#)
 - Recording audio [245](#)
 - Zoom operations [456](#)
 - Unlock Layout when editing single parts [1033](#)
 - Use Drum Editor when Drum Map is assigned [1020](#)
 - Use Up/Down Navigation Commands for Selecting Tracks only [1013](#)
 - User-definable Frame Rate [1035](#)
- ## V
- Value Box/Time Control Mode [1016](#)
 - Value display
 - Editing in List Editor [782](#)
 - VariAudio
 - About [483](#)
 - VCA fader track
 - Inspector [147](#)
 - Track controls [148](#)
 - VCA fader tracks [146](#)

- VCA faders [365](#)
 - Assigning to link groups [368](#)
 - Automation [369](#)
 - Creating [367](#)
 - Nesting [369](#)
 - Removing from link groups [368](#)
 - Settings [365](#)
 - Velocity
 - Changing for note events [732](#)
 - MIDI function [697](#)
 - Vertical Snap
 - Note Expression Event Editor [809](#)
 - Video
 - Codecs [956](#)
 - Editing [962](#)
 - Extracting audio from [962](#)
 - Formats [956](#)
 - Importing [958](#)
 - Output devices [957](#)
 - Playback [960](#)
 - Scrubbing [962](#)
 - Studio Setup [960](#)
 - Thumbnails [959](#)
 - Video Player window [961](#)
 - Aspect ratio [961](#)
 - Setting window size [961](#)
 - Video track [148](#)
 - Inspector [149](#)
 - Track controls [149](#)
 - Virgin territory
 - Automation [615](#)
 - Creating gaps [615](#)
 - Defining a terminator point [615](#)
 - Visibility
 - Inspector [58](#), [59](#)
 - MixConsole [322](#)
 - Synchronizing track and channel visibility [60](#)
 - Voicings [828](#)
 - Automatic voicings [828](#)
 - Configuring parameters [828](#)
 - Library [828](#)
 - Library subset [828](#)
 - Octave offset [828](#)
 - Piano [828](#)
 - Range [828](#)
 - Volume
 - MixConsole [341](#)
 - Volume curve [288](#)
 - Volume databases
 - Creating in the MediaBay [581](#)
 - Mounting in the MediaBay [582](#)
 - Removing from the MediaBay [581](#)
 - Unmounting in the MediaBay [582](#)
 - VST
 - Input ports [17](#)
 - Output ports [17](#)
 - VST 2 [392](#)
 - VST 3 [392](#)
 - VST 3
 - Suspend plug-in processing [634](#)
 - VST 3 controllers
 - HALion Sonic SE [801](#)
 - Note Expression [800](#)
 - VST Audio System [12](#)
 - VST instruments
 - Extracting expression maps [795](#)
 - Freezing [634](#)
 - Presets [632](#)
 - Saving presets [633](#)
 - Setting up [628](#)
 - Using VST System Link [953](#)
 - VST MultiPanner [598](#)
 - About [589](#)
 - Automation [594](#)
 - Constant power [589](#)
 - Disable channels [600](#)
 - Divergence [599](#)
 - Movement restrictions [595](#)
 - Mute channels [600](#)
 - Overview Mode [597](#)
 - Panning [597](#)
 - Panning restrictions [595](#)
 - Plug-in panel [590](#)
 - Positioning [594](#)
 - Remote controlling [601](#)
 - Rotating signals [597](#)
 - Signal distribution [598](#), [599](#)
 - Solo channels [600](#)
 - VST Plug-in Manager [641](#)
 - Collections [641](#)
 - Window [641](#)
 - VST plug-ins
 - Installing [641](#)
 - VST Presets
 - Loading [182](#)
 - Previewing in MediaBay [564](#)
 - VST Quick Controls
 - Connecting with Remote Controllers [638](#)
 - VST System Link
 - About [945](#)
 - Activating [948](#)
 - Connections [946](#)
 - Latency [947](#)
 - MIDI [951](#)
 - Putting computers online [950](#)
 - Requirements [945](#)
 - Setting up sync [946](#)
 - Settings [947](#)
 - VSTi rack
 - Right zone [68](#), [69](#)
- ## W
- Warn before removing modified effects [1039](#)
 - Warn on Processing Overloads [1037](#)
 - Warping Algorithm [1015](#)
 - Wave 64 files
 - Exporting [931](#)
 - Wave files
 - Exporting [926](#)
 - Waveform Brightness [1021](#)
 - Waveform display [455](#)
 - Sample Editor [455](#)
 - Waveform Outline Intensity [1021](#)
 - Waveforms
 - Showing [1021](#)

- When Recording Wave Files larger than 4 GB [1031](#)
- Wind Speed Options [1035](#)
- Windows Media Audio files
 - Exporting [929](#)
 - Importing [256](#)
- Word clock
 - About [938](#)
- Working with MIDI data
 - Tools and functions for [759](#)
- Workspaces
 - Adding [992](#)
 - Creating [992](#)
 - Editing [992](#)
 - External projects [991](#)
 - Modifying [992](#)
 - Organizing [993](#)
 - Saving [992](#)
 - Templates [991](#)
 - Types [991](#)
 - Updating [992](#)
- Workspaces Organizer [993](#)
- Writing automation [606](#)
 - Automatically [607](#)
 - Manually [607](#), [608](#)
 - Tools [608](#)

Z

- Zones
 - Keyboard focus [73](#)
 - Left zone [51](#)
 - Lower zone [61](#)
 - MixConsole [322](#)
 - Project zone [39](#)
 - Right zone [67](#)
- Zones Visibility
 - Inspector [60](#)
- Zoom
 - Adapt Grid to Zoom [74](#)
 - Audio Contents [75](#)
 - Cycle Markers [77](#)
 - Project window [74](#)
- Zoom history
 - Project window [78](#)
- Zoom presets
 - Project window [76](#)
- Zoom Tool Standard Mode - Horizontal Zooming Only [1019](#)
- Zoom while Locating in Time Scale [1035](#)
- Zooming
 - To cycle markers [308](#)
- Zooming tracks [162](#)